

# globus gsi sysconfig Reference Manual

## 5.1

Generated by Doxygen 1.3.9.1

Thu Jan 26 14:47:26 2012

# Contents

<b>1</b>	<b>Globus GSI System Config API</b>	<b>1</b>
<b>2</b>	<b>globus gsi sysconfig Module Index</b>	<b>1</b>
<b>3</b>	<b>globus gsi sysconfig Module Documentation</b>	<b>1</b>

## 1 Globus GSI System Config API

This API provides helper functions for detecting installation and environment specific settings applicabale to GSI. It also servers as a abstraction layer for OS specific programming details. This is achieves by defining preprocessor symbols that point at the correct platform specific function. **You should never use the platform specific functions directly..** Any program that uses Globus GSI System Config functions must include "globus\_gsi\_system\_config.h".

## 2 globus gsi sysconfig Module Index

### 2.1 globus gsi sysconfig Modules

Here is a list of all modules:

<b>Defines</b>	<b>1</b>
<b>Functions for UNIX platforms</b>	<b>5</b>
<b>Functions for Win32 platforms</b>	<b>13</b>
<b>Functions for all platforms</b>	<b>20</b>
<b>Activation</b>	<b>21</b>
<b>Datatypes</b>	<b>22</b>

## 3 globus gsi sysconfig Module Documentation

### 3.1 Defines

These precompiler defines allow for a platform (ie Win32 vs UNIX) independent API.

#### Defines

- #define **GLOBUS\_GSI\_SYSCONFIG\_SET\_KEY\_PERMISSIONS**
- #define **GLOBUS\_GSI\_SYSCONFIG\_GET\_HOME\_DIR**
- #define **GLOBUS\_GSI\_SYSCONFIG\_CHECK\_KEYFILE**
- #define **GLOBUS\_GSI\_SYSCONFIG\_CHECK\_CERTFILE**
- #define **GLOBUS\_GSI\_SYSCONFIG\_FILE\_EXISTS**
- #define **GLOBUS\_GSI\_SYSCONFIG\_DIR\_EXISTS**
- #define **GLOBUS\_GSI\_SYSCONFIG\_GET\_CERT\_DIR**

- **#define GLOBUS\_GSI\_SYSCONFIG\_GET\_USER\_CERT\_FILENAME**
- **#define GLOBUS\_GSI\_SYSCONFIG\_GET\_HOST\_CERT\_FILENAME**
- **#define GLOBUS\_GSI\_SYSCONFIG\_GET\_SERVICE\_CERT\_FILENAME**
- **#define GLOBUS\_GSI\_SYSCONFIG\_GET\_PROXY\_FILENAME**
- **#define GLOBUS\_GSI\_SYSCONFIG\_GET\_SIGNING\_POLICY\_FILENAME**
- **#define GLOBUS\_GSI\_SYSCONFIG\_GET\_CA\_CERT\_FILES**
- **#define GLOBUS\_GSI\_SYSCONFIG\_GET\_CURRENT\_WORKING\_DIR**
- **#define GLOBUS\_GSI\_SYSCONFIG\_MAKE\_ABSOLUTE\_PATH\_FOR\_FILENAME**
- **#define GLOBUS\_GSI\_SYSCONFIG\_SPLIT\_DIR\_AND\_FILENAME**
- **#define GLOBUS\_GSI\_SYSCONFIG\_REMOVE\_ALL\_OWNED\_FILES**
- **#define GLOBUS\_GSI\_SYSCONFIG\_GET\_GRIDMAP\_FILENAME**
- **#define GLOBUS\_GSI\_SYSCONFIG\_GET\_AUTHZ\_CONF\_FILENAME**
- **#define GLOBUS\_GSI\_SYSCONFIG\_GET\_GAA\_CONF\_FILENAME**
- **#define GLOBUS\_GSI\_SYSCONFIG\_IS\_SUPERUSER**
- **#define GLOBUS\_GSI\_SYSCONFIG\_GET\_USER\_ID\_STRING**
- **#define GLOBUS\_GSI\_SYSCONFIG\_GET\_PROC\_ID\_STRING**
- **#define GLOBUS\_GSI\_SYSCONFIG\_GET\_USERNAME**
- **#define GLOBUS\_GSI\_SYSCONFIG\_GET\_UNIQUE\_PROXY\_FILENAME**

### 3.1.1 Detailed Description

These precompiler defines allow for a platform (ie Win32 vs UNIX) independent API.

### 3.1.2 Define Documentation

#### 3.1.2.1 **#define GLOBUS\_GSI\_SYSCONFIG\_SET\_KEY\_PERMISSIONS**

Set the correct file permissions on a private key.

See **globus\_gsi\_sysconfig\_set\_key\_permissions\_unix()**(p. 7) and **globus\_gsi\_sysconfig\_set\_key\_permissions\_win32()**(p. 15)

#### 3.1.2.2 **#define GLOBUS\_GSI\_SYSCONFIG\_GET\_HOME\_DIR**

Get the current users home directory.

See **globus\_gsi\_sysconfig\_get\_home\_dir\_unix()**(p. 9) and **globus\_gsi\_sysconfig\_get\_home\_dir\_win32()**

#### 3.1.2.3 **#define GLOBUS\_GSI\_SYSCONFIG\_CHECK\_KEYFILE**

Check for the correct file permissions on a private key.

See **globus\_gsi\_sysconfig\_check\_keyfile\_unix()**(p. 9) and **globus\_gsi\_sysconfig\_check\_keyfile\_win32()**

#### 3.1.2.4 **#define GLOBUS\_GSI\_SYSCONFIG\_CHECK\_CERTFILE**

Check for the correct file permissions on a certificate.

See **globus\_gsi\_sysconfig\_check\_certfile\_unix()**(p. 10) and **globus\_gsi\_sysconfig\_check\_certfile\_win32()**

#### 3.1.2.5 **#define GLOBUS\_GSI\_SYSCONFIG\_FILE\_EXISTS**

Check whether a given file exists.

See **globus\_gsi\_sysconfig\_file\_exists\_unix()**(p. 9) and **globus\_gsi\_sysconfig\_file\_exists\_win32()**(p. 16)

### **3.1.2.6 #define GLOBUS\_GSI\_SYSCONFIG\_DIR\_EXISTS**

Check whether a given directory exists.

See `globus_gsi_sysconfig_dir_exists_unix()`(p. 9) and `globus_gsi_sysconfig_dir_exists_win32()`(p. 16)

### **3.1.2.7 #define GLOBUS\_GSI\_SYSCONFIG\_GET\_CERT\_DIR**

Determine the location of the trusted certificates directory.

See `globus_gsi_sysconfig_get_cert_dir_unix()`(p. 10) and `globus_gsi_sysconfig_get_cert_dir_win32()`(p. 17)

### **3.1.2.8 #define GLOBUS\_GSI\_SYSCONFIG\_GET\_USER\_CERT\_FILENAME**

Determine the location of the users certificate and private key.

See `globus_gsi_sysconfig_get_user_cert_filename_unix()`(p. 10) and `globus_gsi_sysconfig_get_user_cert_filename_win32()`(p. 17)

### **3.1.2.9 #define GLOBUS\_GSI\_SYSCONFIG\_GET\_HOST\_CERT\_FILENAME**

Determine the location of the host certificate and private key.

See `globus_gsi_sysconfig_get_host_cert_filename_unix()`(p. 11) and `globus_gsi_sysconfig_get_host_cert_filename_win32()`(p. 17)

### **3.1.2.10 #define GLOBUS\_GSI\_SYSCONFIG\_GET\_SERVICE\_CERT\_FILENAME**

Determine the location of a service certificate and private key.

See `globus_gsi_sysconfig_get_service_cert_filename_unix()`(p. 11) and `globus_gsi_sysconfig_get_service_cert_filename_win32()`(p. 18)

### **3.1.2.11 #define GLOBUS\_GSI\_SYSCONFIG\_GET\_PROXY\_FILENAME**

Determine the location of a proxy certificate and private key.

See `globus_gsi_sysconfig_get_proxy_filename_unix()`(p. 11) and `globus_gsi_sysconfig_get_proxy_filename_win32()`(p. 18)

### **3.1.2.12 #define GLOBUS\_GSI\_SYSCONFIG\_GET\_SIGNING\_POLICY\_FILENAME**

Determine the name of the signing policy file for a given CA.

See `globus_gsi_sysconfig_get_signing_policy_filename_unix()`(p. 12) and `globus_gsi_sysconfig_get_signing_policy_filename_win32()`(p. 20)

### **3.1.2.13 #define GLOBUS\_GSI\_SYSCONFIG\_GET\_CA\_CERT\_FILES**

Get a list of trusted CA certificate filenames in a trusted CA certificate directory.

See `globus_gsi_sysconfig_get_ca_cert_files_unix()`(p. 12) and `globus_gsi_sysconfig_get_ca_cert_files_win32()`(p. 19)

### **3.1.2.14 #define GLOBUS\_GSI\_SYSCONFIG\_GET\_CURRENT\_WORKING\_DIR**

Get the current working directory.

See `globus_gsi_sysconfig_get_current_working_dir_unix()`(p. 9) and `globus_gsi_sysconfig_get_current_working_dir_win32()`(p. 16)

### **3.1.2.15 #define GLOBUS\_GSI\_SYSCONFIG\_MAKE\_ABSOLUTE\_PATH\_FOR\_FILENAME**

Prepend the current working directory to the give filename.

See `globus_gsi_sysconfig_make_absolute_path_for_filename_unix()`(p. 8) and `globus_gsi_sysconfig_make_absolute_path_for_filename_win32()`(p. 16)

### **3.1.2.16 #define GLOBUS\_GSI\_SYSCONFIG\_SPLIT\_DIR\_AND\_FILENAME**

Split directory component of path from filename.

See `globus_gsi_sysconfig_split_dir_and_filename_unix()`(p. 8) and `globus_gsi_sysconfig_split_dir_and_filename_win32()`(p. 16)

### **3.1.2.17 #define GLOBUS\_GSI\_SYSCONFIG\_REMOVE\_ALL\_OWNED\_FILES**

Remove all proxies owned by current uid.

See `globus_gsi_sysconfig_remove_all_owned_files_unix()`(p. 12) and `globus_gsi_sysconfig_remove_all_owned_files_win32()`(p. 19)

### **3.1.2.18 #define GLOBUS\_GSI\_SYSCONFIG\_GET\_GRIDMAP\_FILENAME**

Determine the location of the grid map file.

See `globus_gsi_sysconfig_get_gridmap_filename_unix()`(p. 13) and `globus_gsi_sysconfig_get_gridmap_filename_win32()`(p. 19)

### **3.1.2.19 #define GLOBUS\_GSI\_SYSCONFIG\_GET\_AUTHZ\_CONF\_FILENAME**

Determine the location of the authorization callout config file.

See `globus_gsi_sysconfig_get_authz_conf_filename_unix()`(p. 13)

### **3.1.2.20 #define GLOBUS\_GSI\_SYSCONFIG\_GET\_GAA\_CONF\_FILENAME**

Determine the location of the GAA callout config file.

See `globus_gsi_sysconfig_get_gaa_conf_filename_unix()`(p. 13)

### **3.1.2.21 #define GLOBUS\_GSI\_SYSCONFIG\_IS\_SUPERUSER**

Determine whether the current user is the super user.

See `globus_gsi_sysconfig_is_superuser_unix()`(p. 13) and `globus_gsi_sysconfig_is_superuser_win32()`(p. 20)

### **3.1.2.22 #define GLOBUS\_GSI\_SYSCONFIG\_GET\_USER\_ID\_STRING**

Get the current UID in string form.

See `globus_gsi_sysconfig_get_user_id_string_unix()`(p. 7) and `globus_gsi_sysconfig_get_user_id_string_win32()`

### **3.1.2.23 #define GLOBUS\_GSI\_SYSCONFIG\_GET\_PROC\_ID\_STRING**

Get the current PID in string form.

See `globus_gsi_sysconfig_get_proc_id_string_unix()`(p. 8) and `globus_gsi_sysconfig_get_proc_id_string_win32()`

### 3.1.2.24 **#define GLOBUS\_GSI\_SYSCONFIG\_GET\_USERNAME**

Get the current user name.

See `globus_gsi_sysconfig_get_username_unix()`(p. 8) and `globus_gsi_sysconfig_get_username_win32()`

### 3.1.2.25 **#define GLOBUS\_GSI\_SYSCONFIG\_GET\_UNIQUE\_PROXY\_FILENAME**

Generate a unique proxy file name.

See `globus_gsi_sysconfig_get_unique_proxy_filename()`(p. 21)

## 3.2 **Functions for UNIX platforms**

These functions implement the UNIX version of the Globus GSI System Configuration API.

### **UNIX - Set Key Permissions**

- `globus_result_t globus_gsi_sysconfig_set_key_permissions_unix` (char \*filename)

### **UNIX - Get User ID**

- `globus_result_t globus_gsi_sysconfig_get_user_id_string_unix` (char \*\*user\_id\_string)

### **UNIX - Get Username**

- `globus_result_t globus_gsi_sysconfig_get_username_unix` (char \*\*username)

### **UNIX - Get Process ID**

- `globus_result_t globus_gsi_sysconfig_get_proc_id_string_unix` (char \*\*proc\_id\_string)

### **UNIX - Make Absolute Path**

- `globus_result_t globus_gsi_sysconfig_make_absolute_path_for_filename_unix` (char \*filename, char \*\*absolute\_path)

### **UNIX - Split Directory and Filename**

- `globus_result_t globus_gsi_sysconfig_split_dir_and_filename_unix` (char \*full\_filename, char \*\*dir\_string, char \*\*filename\_string)

### **UNIX - Get Current Working Directory**

- `globus_result_t globus_gsi_sysconfig_get_current_working_dir_unix` (char \*\*working\_dir)

### **UNIX - Get HOME Directory**

- `globus_result_t globus_gsi_sysconfig_get_home_dir_unix` (char \*\*home\_dir)

## UNIX - File Exists

- globus\_result\_t **globus\_gsi\_sysconfig\_file\_exists\_unix** (const char \*filename)

## UNIX - Directory Exists

- globus\_result\_t **globus\_gsi\_sysconfig\_dir\_exists\_unix** (const char \*filename)

## UNIX - Check File Status for Key

- globus\_result\_t **globus\_gsi\_sysconfig\_check\_keyfile\_unix** (const char \*filename)

## UNIX - Check File Status for Cert

- globus\_result\_t **globus\_gsi\_sysconfig\_check\_certfile\_unix** (const char \*filename)

## UNIX - Get Trusted CA Cert Dir

- globus\_result\_t **globus\_gsi\_sysconfig\_get\_cert\_dir\_unix** (char \*\*cert\_dir)

## UNIX - Get User Certificate and Key Filenames

- globus\_result\_t **globus\_gsi\_sysconfig\_get\_user\_cert\_filename\_unix** (char \*\*user\_cert, char \*\*user\_key)

## UNIX - Get Host Certificate and Key Filenames

- globus\_result\_t **globus\_gsi\_sysconfig\_get\_host\_cert\_filename\_unix** (char \*\*host\_cert, char \*\*host\_key)

## UNIX - Get Service Certificate and Key Filenames

- globus\_result\_t **globus\_gsi\_sysconfig\_get\_service\_cert\_filename\_unix** (char \*service\_name, char \*\*service\_cert, char \*\*service\_key)

## UNIX - Get Proxy Filename

- globus\_result\_t **globus\_gsi\_sysconfig\_get\_proxy\_filename\_unix** (char \*\*user\_proxy, globus\_gsi\_proxy\_file\_type\_t proxy\_file\_type)

## UNIX - Get Signing Policy Filename

- globus\_result\_t **globus\_gsi\_sysconfig\_get\_signing\_policy\_filename\_unix** (X509\_NAME \*ca\_name, char \*cert\_dir, char \*\*signing\_policy\_filename)

## UNIX - Get CA Cert Filenames

- globus\_result\_t **globus\_gsi\_sysconfig\_get\_ca\_cert\_files\_unix** (char \*ca\_cert\_dir, globus\_fifo\_t \*ca\_cert\_list)

### UNIX - Remove all proxies owned by current uid

- globus\_result\_t globus\_gsi\_sysconfig\_remove\_all\_owned\_files\_unix (char \*default\_filename)

### UNIX - Check if the current user is root

- globus\_result\_t globus\_gsi\_sysconfig\_is\_superuser\_unix (int \*is\_superuser)

### UNIX - Get the path and file name of the grid map file

- globus\_result\_t globus\_gsi\_sysconfig\_get\_gridmap\_filename\_unix (char \*\*filename)

### UNIX - Get the path and file name of the authorization callback configuration file

- globus\_result\_t globus\_gsi\_sysconfig\_get\_authz\_conf\_filename\_unix (char \*\*filename)

### UNIX - Get the path and file name of the authorization callback configuration file

- globus\_result\_t globus\_gsi\_sysconfig\_get\_authz\_lib\_conf\_filename\_unix (char \*\*filename)

### UNIX - Get the path and file name of the gaa configuration file

- globus\_result\_t globus\_gsi\_sysconfig\_get\_gaa\_conf\_filename\_unix (char \*\*filename)

## 3.2.1 Detailed Description

These functions implement the UNIX version of the Globus GSI System Configuration API.

**They should never be called directly, please use the provided platform independent defines.**

## 3.2.2 Function Documentation

### 3.2.2.1 globus\_result\_t globus\_gsi\_sysconfig\_set\_key\_permissions\_unix (char \*filename)

Set the file permissions of a file to read-write only by the user which are the permissions that should be set for all private keys.

#### Parameters:

*filename*

#### Returns:

GLOBUS\_SUCCESS or an error object id

### 3.2.2.2 globus\_result\_t globus\_gsi\_sysconfig\_get\_user\_id\_string\_unix (char \*\*user\_id\_string)

Get a unique string representing the current user. This is just the uid converted to a string.

#### Parameters:

*user\_id\_string* A unique string representing the user

#### Returns:

GLOBUS\_SUCCESS unless an error occurred



### 3.2.2.3 `globus_result_t globus_gsi_sysconfig_get_username_unix (char ** username)`

Get the username of the current user.

#### Parameters:

*username* This parameter will contain the current user name upon a successful return. It is the users responsibility to free memory allocated for this return value.

#### Returns:

GLOBUS\_SUCCESS unless an error occurred

### 3.2.2.4 `globus_result_t globus_gsi_sysconfig_get_proc_id_string_unix (char ** proc_id_string)`

Get a unique string representing the current process. This is just the pid converted to a string.

#### Parameters:

*proc\_id\_string* A unique string representing the process

#### Returns:

GLOBUS\_SUCCESS unless an error occurred

### 3.2.2.5 `globus_result_t globus_gsi_sysconfig_make_absolute_path_for_filename_unix (char * filename, char ** absolute_path)`

Make the filename into an absolute path string based on the current working directory.

#### Parameters:

*filename* the filename to get the absolute path of.

*absolute\_path* The resulting absolute path. This needs to be freed when no longer needed.

#### Returns:

GLOBUS\_SUCCESS if no error occurred, otherwise an error object ID is returned

### 3.2.2.6 `globus_result_t globus_gsi_sysconfig_split_dir_and_filename_unix (char * full_filename, char ** dir_string, char ** filename_string)`

Split the directory and filename portions of a filename string into two separate strings

#### Parameters:

*full\_filename* The filename to split. Splits on the last occurrence of '/' where the directory is everything before the last '/', and the filename is everything after.

*dir\_string* The directory portion of the filename string. If no '/' is found throughout the string, this variable points to NULL. This needs to be freed when no longer needed.

*filename\_string* The filename portion of the filename string. If no '/' is found throughout, this variable is a duplicate of the *full\_filename* parameter. This needs to be freed when no longer needed.

#### Returns:

GLOBUS\_SUCCESS if no error occurred. Otherwise an error object ID is returned.

### 3.2.2.7 `globus_result_t globus_gsi_sysconfig_get_current_working_dir_unix (char ** working_dir)`

Get the current working directory on the system.

**Parameters:**

*working\_dir* The current working directory

**Returns:**

GLOBUS\_SUCCESS or an error object identifier

### 3.2.2.8 `globus_result_t globus_gsi_sysconfig_get_home_dir_unix (char ** home_dir)`

Get the HOME Directory of the current user. Should be the \$HOME environment variable.

**Parameters:**

*home\_dir* The home directory of the current user

**Returns:**

GLOBUS\_SUCCESS if no error occurred, otherwise an error object is returned.

### 3.2.2.9 `globus_result_t globus_gsi_sysconfig_file_exists_unix (const char * filename)`

Check if the file exists.

**Parameters:**

*filename* The filename of the file to check for

**Returns:**

GLOBUS\_SUCCESS if the file exists and is readable, otherwise an error object identifier

### 3.2.2.10 `globus_result_t globus_gsi_sysconfig_dir_exists_unix (const char * filename)`

Check if the directory exists.

**Parameters:**

*filename* The filename of the directory to check for

**Returns:**

GLOBUS\_SUCCESS if the directory exists, otherwise an error object identifier.

### 3.2.2.11 `globus_result_t globus_gsi_sysconfig_check_keyfile_unix (const char * filename)`

This is a convenience function used to check the status of a private key file. The desired status is only the current user has ownership and read permissions, everyone else should not be able to access it.

**Parameters:**

*filename* The name of the file to check the status of

**Returns:**

GLOBUS\_SUCCESS if the status of the file was able to be determined. Otherwise, an error object identifier

### 3.2.2.12 `globus_result_t globus_gsi_sysconfig_check_certfile_unix (const char *filename)`

This is a convenience function used to check the status of a certificate file. The desired status is the current user has ownership and read/write permissions, while group and others only have read permissions.

#### Parameters:

*filename* The name of the file to check the status of

#### Returns:

GLOBUS\_SUCCESS if the status of the file was able to be determined. Otherwise, an error object identifier

### 3.2.2.13 `globus_result_t globus_gsi_sysconfig_get_cert_dir_unix (char **cert_dir)`

Get the Trusted Certificate Directory containing the trusted Certificate Authority certificates. This directory is determined in the order shown below. Failure in one method results in attempting the next.

1. **X509\_CERT\_DIR environment variable** - if this is set, the trusted certificates will be searched for in that directory. This variable allows the end user to specify the location of trusted certificates.
2. **\$HOME/.globus/certificates** - If this directory exists, and the previous methods of determining the trusted certs directory failed, this directory will be used.
3. **/etc/grid-security/certificates** - This location is intended to be independent of the globus installation (\$GLOBUS\_LOCATION), and is generally only writeable by the host system administrator.
4. **\$GLOBUS\_LOCATION/share/certificates**

#### Parameters:

*cert\_dir* The trusted certificates directory

#### Returns:

GLOBUS\_SUCCESS if no error occurred, and a sufficient trusted certificates directory was found. Otherwise, an error object identifier returned.

### 3.2.2.14 `globus_result_t globus_gsi_sysconfig_get_user_cert_filename_unix (char **user_cert, char **user_key)`

Get the User Certificate Filename based on the current user's environment. The following locations are searched for cert and key files in order:

1. environment variables X509\_USER\_CERT and X509\_USER\_KEY
2. \$HOME/.globus/usercert.pem and \$HOME/.globus/userkey.pem
3. \$HOME/.globus/usercred.p12 - this is a PKCS12 credential

#### Parameters:

*user\_cert* pointer the filename of the user certificate

*user\_key* pointer to the filename of the user key

#### Returns:

GLOBUS\_SUCCESS if the cert and key files were found in one of the possible locations, otherwise an error object identifier is returned

### 3.2.2.15 **globus\_result\_t globus\_gsi\_sysconfig\_get\_host\_cert\_filename\_unix** (char \*\* *host\_cert*, char \*\* *host\_key*)

Get the Host Certificate and Key Filenames based on the current user's environment. The host cert and key are searched for in the following locations (in order):

1. X509\_USER\_CERT and X509\_USER\_KEY environment variables
2. registry keys x509\_user\_cert and x509\_user\_key in software\Globus\GSI
3. \<GLOBUS\_LOCATION\>\etc\host[cert|key].pem
4. \<users home directory\>\.globus\host[cert|key].pem

#### **Parameters:**

*host\_cert* pointer to the host certificate filename

*host\_key* pointer to the host key filename

#### **Returns:**

GLOBUS\_SUCCESS if the host cert and key were found, otherwise an error object identifier is returned

### 3.2.2.16 **globus\_result\_t globus\_gsi\_sysconfig\_get\_service\_cert\_filename\_unix** (char \* *service\_name*, char \*\* *service\_cert*, char \*\* *service\_key*)

Get the Service Certificate Filename based on the current user's environment. The host cert and key are searched for in the following locations (in order):

1. X509\_USER\_CERT and X509\_USER\_KEY environment variables
2. \etc\grid-security\{service\_name}\{service\_name}[cert|key].pem
3. GLOBUS\_LOCATION\etc\{service\_name}\{service\_name}[cert|key].pem So for example, if my service was named: myservice, the location of the certificate would be: GLOBUS\_LOCATION\etc\myservice\myservicecert.pem
4. \<users home\>\.globus\{service\_name}\{service\_name}[cert|key].pem

#### **Parameters:**

*service\_name* The name of the service which allows us to determine the locations of cert and key files to look for

*service\_cert* pointer to the host certificate filename

*service\_key* pointer to the host key filename

#### **Returns:**

GLOBUS\_SUCCESS if the service cert and key were found, otherwise an error object identifier

### 3.2.2.17 **globus\_result\_t globus\_gsi\_sysconfig\_get\_proxy\_filename\_unix** (char \*\* *user\_proxy*, globus\_gsi\_proxy\_file\_type\_t *proxy\_file\_type*)

Get the proxy cert filename based on the following search order:

1. X509\_USER\_PROXY environment variable - This environment variable is set by the at run time for the specific application. If the proxy\_file\_type variable is set to GLOBUS\_PROXY\_OUTPUT (a proxy filename for writing is requested), and the X509\_USER\_PROXY is set, this will be the resulting value of the user\_proxy filename string passed in. If the proxy\_file\_type is set to GLOBUS\_PROXY\_INPUT and X509\_USER\_PROXY is set, but the file it points to does not exist, or has some other readability issues, the function will continue checking using the other methods available.

2. Check the default location for the proxy file of `\tmp\x509_u\<user_id\>` where `\<user id\>` is some unique string for that user on the host

**Parameters:**

*user\_proxy* the proxy filename of the user

*proxy\_file\_type* Switch for determining whether to return a existing proxy filename or if a filename suitable for creating a proxy should be returned

**Returns:**

GLOBUS\_SUCCESS or an error object identifier

**3.2.2.18 globus\_result\_t globus\_gsi\_sysconfig\_get\_signing\_policy\_filename\_unix (X509\_NAME \* *ca\_name*, char \* *cert\_dir*, char \*\* *signing\_policy\_filename*)**

Get the Signing Policy Filename on the current system, based on the CA's subject name, and the trusted certificates directory

**Parameters:**

*ca\_name* The X509 subject name of the CA to get the signing policy of. The hash of the CA is generated from this

*cert\_dir* The trusted CA certificates directory, containing the signing\_policy files of the trusted CA's.

*signing\_policy\_filename* The resulting signing\_policy filename

**Returns:**

GLOBUS\_SUCCESS if no error occurred, otherwise an error object ID

**3.2.2.19 globus\_result\_t globus\_gsi\_sysconfig\_get\_ca\_cert\_files\_unix (char \* *ca\_cert\_dir*, globus\_fifo\_t \* *ca\_cert\_list*)**

Gets a list of trusted CA certificate filenames in a trusted CA certificate directory.

**Parameters:**

*ca\_cert\_dir* The trusted CA certificate directory to get the filenames from

*ca\_cert\_list* The resulting list of CA certificate filenames. This is a a globus list structure.

**See also:**

globus\_fifo\_t

**Returns:**

GLOBUS\_SUCCESS if no error occurred, otherwise an error object ID is returned

**3.2.2.20 globus\_result\_t globus\_gsi\_sysconfig\_remove\_all\_owned\_files\_unix (char \* *default\_filename*)**

Removes all proxies (ie. all delegated and grid-proxy-init generated proxies) found in the secure tmp directory that are owned by the current user.

**Parameters:**

*default\_filename* The filename of the default proxy

**Returns:**

GLOBUS\_SUCCESS if no error occurred, otherwise an error object ID is returned

### 3.2.2.21 `globus_result_t globus_gsi_sysconfig_is_superuser_unix (int * is_superuser)`

Checks whether the current user is root.

#### Parameters:

*is\_superuser* 1 if the user is the superuser 0 if not

#### Returns:

GLOBUS\_SUCCESS if no error occurred, otherwise an error object ID is returned

### 3.2.2.22 `globus_result_t globus_gsi_sysconfig_get_gridmap_filename_unix (char ** filename)`

Get the path and file name of the grid map file.

#### Parameters:

*filename* Contains the location of the grid map file upon successful return

#### Returns:

GLOBUS\_SUCCESS if no error occurred, otherwise an error object ID is returned

### 3.2.2.23 `globus_result_t globus_gsi_sysconfig_get_authz_conf_filename_unix (char ** filename)`

Get the path and file name of the authorization callback configuration file

#### Parameters:

*filename* Contains the location of the authorization callback configuration file upon successful return

#### Returns:

GLOBUS\_SUCCESS if no error occurred, otherwise an error object ID is returned

### 3.2.2.24 `globus_result_t globus_gsi_sysconfig_get_authz_lib_conf_filename_unix (char ** filename)`

Get the path and file name of the authorization callback configuration file

#### Parameters:

*filename* Contains the location of the authorization callback configuration file upon successful return

#### Returns:

GLOBUS\_SUCCESS if no error occurred, otherwise an error object ID is returned

### 3.2.2.25 `globus_result_t globus_gsi_sysconfig_get_gaa_conf_filename_unix (char ** filename)`

Get the path and file name of the GAA configuration file.

#### Parameters:

*filename* Contains the location of the GAA callback configuration file upon successful return

#### Returns:

GLOBUS\_SUCCESS if no error occurred, otherwise an error object ID is returned

## 3.3 Functions for Win32 platforms

These functions implement the Win32 version of the Globus GSI System Configuration API.

### Win32 - Set Key Permissions

- globus\_result\_t **globus\_gsi\_sysconfig\_set\_key\_permissions\_win32** (char \*filename)

### Win32 - File Exists

- globus\_result\_t **globus\_gsi\_sysconfig\_file\_exists\_win32** (const char \*filename)

### Win32 - Directory Exists

- globus\_result\_t **globus\_gsi\_sysconfig\_dir\_exists\_win32** (const char \*filename)

### Win32 - Get Current Working Directory

- globus\_result\_t **globus\_gsi\_sysconfig\_get\_current\_working\_dir\_win32** (char \*\*working\_dir)

### Win32 - Make Absolute Path

- globus\_result\_t **globus\_gsi\_sysconfig\_make\_absolute\_path\_for\_filename\_win32** (char \*filename, char \*\*absolute\_path)

### Win32 - Split Directory and Filename

- globus\_result\_t **globus\_gsi\_sysconfig\_split\_dir\_and\_filename\_win32** (char \*full\_filename, char \*\*dir\_string, char \*\*filename\_string)

### Win32 - Get Trusted CA Cert Dir

- globus\_result\_t **globus\_gsi\_sysconfig\_get\_cert\_dir\_win32** (char \*\*cert\_dir)

### Win32 - Get User Certificate Filename

- globus\_result\_t **globus\_gsi\_sysconfig\_get\_user\_cert\_filename\_win32** (char \*\*user\_cert, char \*\*user\_key)

### Win32 - Get Host Certificate and Key Filenames

- globus\_result\_t **globus\_gsi\_sysconfig\_get\_host\_cert\_filename\_win32** (char \*\*host\_cert, char \*\*host\_key)

### Win32 - Get Service Certificate and Key Filenames

- globus\_result\_t **globus\_gsi\_sysconfig\_get\_service\_cert\_filename\_win32** (char \*service\_name, char \*\*service\_cert, char \*\*service\_key)

### Win32 - Get Proxy Filename

- globus\_result\_t **globus\_gsi\_sysconfig\_get\_proxy\_filename\_win32** (char \*\*user\_proxy, globus\_gsi\_proxy\_file\_type\_t proxy\_file\_type)

### Win32 - Get CA Cert Filenames

- globus\_result\_t **globus\_gsi\_sysconfig\_get\_ca\_cert\_files\_win32** (char \*ca\_cert\_dir, globus\_fifo\_t \*ca\_cert\_list)

### Win32 - Remove all proxies owned by current uid

- globus\_result\_t **globus\_gsi\_sysconfig\_remove\_all\_owned\_files\_win32** (char \*default\_filename)

### Win32 - Get the path and file name of the grid map file

- globus\_result\_t **globus\_gsi\_sysconfig\_get\_gridmap\_filename\_win32** (char \*\*filename)

### Win32 - Get the path and file name of the grid map file

- globus\_result\_t **globus\_gsi\_sysconfig\_get\_authz\_conf\_filename\_win32** (char \*\*filename)

### Win32 - Get the path and file name of the gaa config file

- globus\_result\_t **globus\_gsi\_sysconfig\_get\_gaa\_conf\_filename\_win32** (char \*\*filename)

### Win32 - Check if the current user is root

- globus\_result\_t **globus\_gsi\_sysconfig\_is\_superuser\_win32** (int \*is\_superuser)

### Win32 - Get Signing Policy Filename

- globus\_result\_t **globus\_gsi\_sysconfig\_get\_signing\_policy\_filename\_win32** (X509\_NAME \*ca\_name, char \*cert\_dir, char \*\*signing\_policy\_filename)

## 3.3.1 Detailed Description

These functions implement the Win32 version of the Globus GSI System Configuration API.

**They should never be called directly, please use the provided platform independent defines.**

## 3.3.2 Function Documentation

### 3.3.2.1 globus\_result\_t globus\_gsi\_sysconfig\_set\_key\_permissions\_win32 (char \*filename)

Set the file permissions of a file to read only by the user which are the permissions that should be set for all private keys.

#### Parameters:

*filename*

#### Returns:

GLOBUS\_SUCCESS or an error object id



### 3.3.2.2 globus\_result\_t globus\_gsi\_sysconfig\_file\_exists\_win32 (const char \* *filename*)

Check that the file exists.

#### Parameters:

*filename* the file to check

#### Returns:

GLOBUS\_SUCCESS (even if the file doesn't exist) - in some abortive cases an error object identifier is returned

### 3.3.2.3 globus\_result\_t globus\_gsi\_sysconfig\_dir\_exists\_win32 (const char \* *filename*)

Check that the directory exists.

#### Parameters:

*filename* the file to check

#### Returns:

GLOBUS\_SUCCESS if the directory exists, otherwise an error object identifier.

### 3.3.2.4 globus\_result\_t globus\_gsi\_sysconfig\_get\_current\_working\_dir\_win32 (char \*\* *working\_dir*)

Get the current working directory on a windows system.

#### Parameters:

*working\_dir* The working directory to get

#### Returns:

GLOBUS\_SUCCESS if no error occurred, otherwise an error object ID is returned

### 3.3.2.5 globus\_result\_t globus\_gsi\_sysconfig\_make\_absolute\_path\_for\_filename\_win32 (char \* *filename*, char \*\* *absolute\_path*)

Make the filename into an absolute path string based on the current working directory.

#### Parameters:

*filename* the filename to get the absolute path of.

*absolute\_path* The resulting absolute path

#### Returns:

GLOBUS\_SUCCESS if no error occurred, otherwise an error object ID is returned

### 3.3.2.6 globus\_result\_t globus\_gsi\_sysconfig\_split\_dir\_and\_filename\_win32 (char \* *full\_filename*, char \*\* *dir\_string*, char \*\* *filename\_string*)

Split the directory and filename portions of a filename string into two separate strings

#### Parameters:

*full\_filename*

*dir\_string*

*filename\_string*

#### Returns:

### 3.3.2.7 globus\_result\_t globus\_gsi\_sysconfig\_get\_cert\_dir\_win32 (char \*\* cert\_dir)

Get the Trusted Certificate Directory containing the trusted Certificate Authority certificates. This directory is determined in the order shown below. Failure in one method results in attempting the next.

1. **X509\_CERT\_DIR environment variable** - if this is set, the trusted certificates will be searched for in that directory. This variable allows the end user to specify the location of trusted certificates.
2. **x509\_cert\_dir registry key** - If this registry key is set on windows, the directory it points to should contain the trusted certificates. The path to the registry key is software\Globus\GSI
3. **<user home directory>\.globus\certificates** - If this directory exists, and the previous methods of determining the trusted certs directory failed, this directory will be used.
4. **Host Trusted Cert Dir** - This location is intended to be independent of the globus installation (\$GLOBUS\_LOCATION), and is generally only writeable by the host system administrator.
5. **Globus Install Trusted Cert Dir** - this is \$GLOBUS\_LOCATION\share\certificates.

#### Parameters:

*cert\_dir* The trusted certificates directory

#### Returns:

GLOBUS\_SUCCESS if no error occurred, and a sufficient trusted certificates directory was found. Otherwise, an error object identifier returned.

### 3.3.2.8 globus\_result\_t globus\_gsi\_sysconfig\_get\_user\_cert\_filename\_win32 (char \*\* user\_cert, char \*\* user\_key)

Get the User Certificate Filename based on the current user's environment. The following locations are searched for cert and key files in order:

1. environment variables X509\_USER\_CERT and X509\_USER\_KEY
2. registry keys x509\_user\_cert and x509\_user\_key in software\Globus\GSI
3. <users home directory>\.globus\usercert.pem and <users home directory>\.globus\userkey.pem
4. <users home directory>\.globus\usercred.p12 - this is a PKCS12 credential

#### Parameters:

*user\_cert* pointer the filename of the user certificate

*user\_key* pointer to the filename of the user key

#### Returns:

GLOBUS\_SUCCESS if the cert and key files were found in one of the possible locations, otherwise an error object identifier is returned

### 3.3.2.9 globus\_result\_t globus\_gsi\_sysconfig\_get\_host\_cert\_filename\_win32 (char \*\* host\_cert, char \*\* host\_key)

Get the Host Certificate and Key Filenames based on the current user's environment. The host cert and key are searched for in the following locations (in order):

1. X509\_USER\_CERT and X509\_USER\_KEY environment variables

2. registry keys x509\_user\_cert and x509\_user\_key in software\Globus\GSI
3. <GLOBUS\_LOCATION>\etc\host[cert|key].pem
4. <users home directory>\.globus\host[cert|key].pem

**Parameters:**

*host\_cert* pointer to the host certificate filename

*host\_key* pointer to the host key filename

**Returns:**

GLOBUS\_SUCCESS if the host cert and key were found, otherwise an error object identifier is returned

**3.3.2.10 globus\_result\_t globus\_gsi\_sysconfig\_get\_service\_cert\_filename\_win32 (char \* service\_name, char \*\* service\_cert, char \*\* service\_key)**

Get the Service Certificate Filename based on the current user's environment. The host cert and key are searched for in the following locations (in order):

1. X509\_USER\_CERT and X509\_USER\_KEY environment variables
2. registry keys x509\_user\_cert and x509\_user\_key in software\Globus\GSI
3. GLOBUS\_LOCATION\etc\{service\_name}\{service\_name}[cert|key].pem So for example, if my service was named: myservice, the location of the certificate would be: GLOBUS\_LOCATION\etc\myservice\myservicecert.pem
4. <users home>\.globus\{service\_name}\{service\_name}[cert|key].pem

**Parameters:**

*service\_name* The name of the service which allows us to determine the locations of cert and key files to look for

*service\_cert* pointer to the host certificate filename

*service\_key* pointer to the host key filename

**Returns:**

GLOBUS\_SUCCESS if the service cert and key were found, otherwise an error object identifier

**3.3.2.11 globus\_result\_t globus\_gsi\_sysconfig\_get\_proxy\_filename\_win32 (char \*\* user\_proxy, globus\_gsi\_proxy\_file\_type\_t proxy\_file\_type)**

Get the proxy cert filename based on the following search order:

1. X509\_USER\_PROXY environment variable - This environment variable is set by the at run time for the specific application. If the proxy\_file\_type variable is set to GLOBUS\_PROXY\_OUTPUT (a proxy filename for writing is requested), and the X509\_USER\_PROXY is set, this will be the resulting value of the user\_proxy filename string passed in. If the proxy\_file\_type is set to GLOBUS\_PROXY\_INPUT and X509\_USER\_PROXY is set, but the file it points to does not exist, or has some other readability issues, the function will continue checking using the other methods available.
2. check the registry key: x509\_user\_proxy. Just as with the environment variable, if the registry key is set, and proxy\_file\_type is GLOBUS\_PROXY\_OUTPUT, the string set to be the proxy filename will be this registry key's value. If proxy\_file\_type is GLOBUS\_PROXY\_INPUT, and the file doesn't exist, the function will check the next method for the proxy's filename.

3. Check the default location for the proxy file. The default location should be set to reside in the temp directory on that host, with the filename taking the format: x509\_u<user id> where <user id> is some unique string for that user on the host

**Parameters:**

*user\_proxy* the proxy filename of the user

*proxy\_file\_type* Switch for determining whether to return a existing proxy filename or if a filename suitable for creating a proxy should be returned

**Returns:**

GLOBUS\_SUCCESS or an error object identifier

**3.3.2.12 globus\_result\_t globus\_gsi\_sysconfig\_get\_ca\_cert\_files\_win32 (char \* *ca\_cert\_dir*, globus\_fifo\_t \* *ca\_cert\_list*)**

Gets a list of trusted CA certificate filenames in a trusted CA certificate directory.

**Parameters:**

*ca\_cert\_dir* The trusted CA certificate directory to get the filenames from

*ca\_cert\_list* The resulting list of CA certificate filenames. This is a a globus list structure.

**See also:**

globus\_fifo\_t

**Returns:**

GLOBUS\_SUCCESS if no error occurred, otherwise an error object ID is returned

**3.3.2.13 globus\_result\_t globus\_gsi\_sysconfig\_remove\_all\_owned\_files\_win32 (char \* *default\_filename*)**

Removes all proxies (ie. all delegated and grid-proxy-init generated proxies) found in the secure tmp directory that are owned by the current user.

**Parameters:**

*default\_filename* The filename of the default proxy

**Returns:**

GLOBUS\_SUCCESS if no error occurred, otherwise an error object ID is returned

**3.3.2.14 globus\_result\_t globus\_gsi\_sysconfig\_get\_gridmap\_filename\_win32 (char \*\* *filename*)**

Get the path and file name of the grid map file.

**Parameters:**

*filename* Contains the location of the grid map file upon successful return

**Returns:**

GLOBUS\_SUCCESS if no error occurred, otherwise an error object ID is returned

### 3.3.2.15 globus\_result\_t globus\_gsi\_sysconfig\_get\_authz\_conf\_filename\_win32 (char \*\**filename*)

Get the path and file name of the authorization callback configuration file

#### Parameters:

*filename* Contains the location of the authorization callback configuration file upon successful return

#### Returns:

GLOBUS\_SUCCESS if no error occurred, otherwise an error object ID is returned

### 3.3.2.16 globus\_result\_t globus\_gsi\_sysconfig\_get\_gaa\_conf\_filename\_win32 (char \*\**filename*)

Get the path and file name of the gaa config configuration file .

#### Parameters:

*filename* Contains the location of the authorization callback configuration file upon successful return

#### Returns:

GLOBUS\_SUCCESS if no error occurred, otherwise an error object ID is returned

### 3.3.2.17 globus\_result\_t globus\_gsi\_sysconfig\_is\_superuser\_win32 (int \**is\_superuser*)

Checks whether the current user is root.

#### Parameters:

*is\_superuser* 1 if the user is the superuser 0 if not

#### Returns:

GLOBUS\_SUCCESS if no error occurred, otherwise an error object ID is returned

### 3.3.2.18 globus\_result\_t globus\_gsi\_sysconfig\_get\_signing\_policy\_filename\_win32 (X509\_NAME \* *ca\_name*, char \* *cert\_dir*, char \*\* *signing\_policy\_filename*)

Get the Signing Policy Filename on the current system, based on the CA's subject name, and the trusted certificates directory

#### Parameters:

*ca\_name* The X509 subject name of the CA to get the signing policy of. The hash of the CA is generated from this

*cert\_dir* The trusted CA certificates directory, containing the signing\_policy files of the trusted CA's.

*signing\_policy\_filename* The resulting signing\_policy filename

#### Returns:

GLOBUS\_SUCCESS if no error occurred, otherwise an error object ID

## 3.4 Functions for all platforms

These functions are platform independent members of the Globus GSI System Configuration API.

### Get Unique Proxy Filename

- globus\_result\_t globus\_gsi\_sysconfig\_get\_unique\_proxy\_filename (char \*\**unique\_filename*)

### 3.4.1 Detailed Description

These functions are platform independent members of the Globus GSI System Configuration API.

### 3.4.2 Function Documentation

#### 3.4.2.1 `globus_result_t globus_gsi_sysconfig_get_unique_proxy_filename (char ** unique_filename)`

Get a unique proxy cert filename. This is mostly used for delegated proxy credentials. Each filename returned is going to be unique for each time the function is called.

**Parameters:**

*unique\_filename* the unique filename for a delegated proxy cert

**Returns:**

GLOBUS\_SUCCESS or an error object identifier

## 3.5 Activation

Globus GSI System Configuration API uses standard Globus module activation and deactivation.

**Defines**

- `#define GLOBUS_GSI_SYSCONFIG_MODULE`

### 3.5.1 Detailed Description

Globus GSI System Configuration API uses standard Globus module activation and deactivation.

Before any Globus GSI System Configuration API functions are called, the following function must be called:

```
globus_module_activate(GLOBUS_GSI_SYSCONFIG_MODULE)
```

This function returns GLOBUS\_SUCCESS if the Globus GSI System Configuration API was successfully initialized, and you are therefore allowed to subsequently call Globus GSI System Configuration API functions. Otherwise, an error code is returned, and Globus GSI Credential functions should not be subsequently called. This function may be called multiple times.

To deactivate Globus GSI System Configuration API, the following function must be called:

```
globus_module_deactivate(GLOBUS_GSI_SYSCONFIG_MODULE)
```

This function should be called once for each time Globus GSI System Configuration API was activated.

### 3.5.2 Define Documentation

#### 3.5.2.1 `#define GLOBUS_GSI_SYSCONFIG_MODULE`

Module descriptor.

## 3.6 Datatypes

### Enumerations

- `enum globus_gsi_sysconfig_error_t {`  
    `GLOBUS_GSI_SYSCONFIG_ERROR_SUCCESS = 0,`  
    `GLOBUS_GSI_SYSCONFIG_ERROR_GETTING_CERT_DIR = 1,`  
    `GLOBUS_GSI_SYSCONFIG_ERROR_GETTING_CERT_STRING = 2,`  
    `GLOBUS_GSI_SYSCONFIG_ERROR_GETTING_KEY_STRING = 3,`  
    `GLOBUS_GSI_SYSCONFIG_ERROR_GETTING_HOME_DIR = 4,`  
    `GLOBUS_GSI_SYSCONFIG_ERROR_ERRNO = 5,`  
    `GLOBUS_GSI_SYSCONFIG_ERROR_CHECKING_FILE_EXISTS = 6,`  
    `GLOBUS_GSI_SYSCONFIG_ERROR_GETTING_CERT_FILENAME = 7,`  
    `GLOBUS_GSI_SYSCONFIG_ERROR_GETTING_PROXY_FILENAME = 8,`  
    `GLOBUS_GSI_SYSCONFIG_ERROR_GETTING_DELEG_FILENAME = 9,`  
    `GLOBUS_GSI_SYSCONFIG_ERROR_GETTING_CA_CERT_FILENAMES = 10,`  
    `GLOBUS_GSI_SYSCONFIG_ERROR_GETTING_CWD = 11,`  
    `GLOBUS_GSI_SYSCONFIG_ERROR_REMOVING_OWNED_FILES = 12,`  
    `GLOBUS_GSI_SYSCONFIG_ERROR_GETTING_GRIDMAP_FILENAME = 13,`  
    `GLOBUS_GSI_SYSCONFIG_ERROR_CHECKING_SUPERUSER = 14,`  
    `GLOBUS_GSI_SYSCONFIG_ERROR_SETTING_PERMS = 15,`  
    `GLOBUS_GSI_SYSCONFIG_ERROR_GETTING_SIGNING_POLICY = 16,`  
    `GLOBUS_GSI_SYSCONFIG_ERROR_GETTING_PW_ENTRY = 17,`  
    `GLOBUS_GSI_SYSCONFIG_ERROR_GETTING_AUTHZ_FILENAME = 18,`  
    `GLOBUS_GSI_SYSCONFIG_ERROR_FILE_NOT_REGULAR = 19,`  
    `GLOBUS_GSI_SYSCONFIG_ERROR_FILE_DOES_NOT_EXIST = 20,`  
    `GLOBUS_GSI_SYSCONFIG_ERROR_FILE_BAD_PERMISSIONS = 21,`  
    `GLOBUS_GSI_SYSCONFIG_ERROR_FILE_NOT_OWNED = 22,`  
    `GLOBUS_GSI_SYSCONFIG_ERROR_FILE_IS_DIR = 23,`  
    `GLOBUS_GSI_SYSCONFIG_ERROR_FILE_ZERO_LENGTH = 24,`  
    `GLOBUS_GSI_SYSCONFIG_INVALID_ARG = 25,`  
    `GLOBUS_GSI_SYSCONFIG_ERROR_FILE_HAS_LINKS = 26,`  
    `GLOBUS_GSI_SYSCONFIG_ERROR_FILE_HAS_CHANGED = 27,`  
    `GLOBUS_GSI_SYSCONFIG_ERROR_GETTING_AUTHZ_LIB_FILENAME = 28,`  
    `GLOBUS_GSI_SYSCONFIG_ERROR_GETTING_GAA_FILENAME = 29,`  
    `GLOBUS_GSI_SYSCONFIG_ERROR_FILE_NOT_DIR = 30,`  
    `GLOBUS_GSI_SYSCONFIG_ERROR_LAST = 31 }`  
• `enum globus_gsi_proxy_file_type_t {`  
    `GLOBUS_PROXY_FILE_INPUT,`  
    `GLOBUS_PROXY_FILE_OUTPUT }`

### 3.6.1 Enumeration Type Documentation

#### 3.6.1.1 enum globus\_gsi\_sysconfig\_error\_t

GSI System Config Error codes.

##### Enumeration values:

- GLOBUS\_GSI\_SYSCONFIG\_ERROR\_SUCCESS** Success - never used.
- GLOBUS\_GSI\_SYSCONFIG\_ERROR\_GETTING\_CERT\_DIR** Unable to determine trusted certificates directory.
- GLOBUS\_GSI\_SYSCONFIG\_ERROR\_GETTING\_CERT\_STRING** Error while generating certificate filename.
- GLOBUS\_GSI\_SYSCONFIG\_ERROR\_GETTING\_KEY\_STRING** Error while generating private key filename.
- GLOBUS\_GSI\_SYSCONFIG\_ERROR\_GETTING\_HOME\_DIR** Unable to determine user's home directory.
- GLOBUS\_GSI\_SYSCONFIG\_ERROR\_ERRNO** System Error – see underlying error for details.
- GLOBUS\_GSI\_SYSCONFIG\_ERROR\_CHECKING\_FILE\_EXISTS** Unable to determine whether file exists.
- GLOBUS\_GSI\_SYSCONFIG\_ERROR\_GETTING\_CERT\_FILENAME** Unable to determine the location of the certificate file.
- GLOBUS\_GSI\_SYSCONFIG\_ERROR\_GETTING\_PROXY\_FILENAME** Unable to determine the location of the proxy file.
- GLOBUS\_GSI\_SYSCONFIG\_ERROR\_GETTING\_DELEG\_FILENAME** Unable to determine the location of the delegated proxy file.
- GLOBUS\_GSI\_SYSCONFIG\_ERROR\_GETTING\_CA\_CERT\_FILENAMES** Unable to generate a list of CA certificate filenames.
- GLOBUS\_GSI\_SYSCONFIG\_ERROR\_GETTING\_CWD** Error while discovering the current working directory.
- GLOBUS\_GSI\_SYSCONFIG\_ERROR\_REMOVING\_OWNED\_FILES** Failed to remove all proxy files.
- GLOBUS\_GSI\_SYSCONFIG\_ERROR\_GETTING\_GRIDMAP\_FILENAME** Unable to determine the location of the grid map file.
- GLOBUS\_GSI\_SYSCONFIG\_ERROR\_CHECKING\_SUPERUSER** Failure while checking whether the current user is the super user.
- GLOBUS\_GSI\_SYSCONFIG\_ERROR\_SETTING\_PERMS** Error while trying to set file permissions.
- GLOBUS\_GSI\_SYSCONFIG\_ERROR\_GETTING\_SIGNING\_POLICY** Unable to determine the location of a signing policy file.
- GLOBUS\_GSI\_SYSCONFIG\_ERROR\_GETTING\_PW\_ENTRY** Could not find password entry for user.
- GLOBUS\_GSI\_SYSCONFIG\_ERROR\_GETTING\_AUTHZ\_FILENAME** Failed to locate the authorization callout configuration file.
- GLOBUS\_GSI\_SYSCONFIG\_ERROR\_FILE\_NOT\_REGULAR** File is not a regular file.
- GLOBUS\_GSI\_SYSCONFIG\_ERROR\_FILE\_DOES\_NOT\_EXIST** File does not exist.
- GLOBUS\_GSI\_SYSCONFIG\_ERROR\_FILE\_BAD\_PERMISSIONS** File has incorrect permissions for operation.
- GLOBUS\_GSI\_SYSCONFIG\_ERROR\_FILE\_NOT\_OWNED** File is not owned by current user.
- GLOBUS\_GSI\_SYSCONFIG\_ERROR\_FILE\_IS\_DIR** File is a directory.
- GLOBUS\_GSI\_SYSCONFIG\_ERROR\_FILE\_ZERO\_LENGTH** File has zero length.
- GLOBUS\_GSI\_SYSCONFIG\_INVALID\_ARG** Invalid argument.



***GLOBUS\_GSI\_SYSCONFIG\_ERROR\_FILE\_HAS\_LINKS*** File has more than one link.

***GLOBUS\_GSI\_SYSCONFIG\_ERROR\_FILE\_HAS\_CHANGED*** File has changed in the meantime.

***GLOBUS\_GSI\_SYSCONFIG\_ERROR\_GETTING\_AUTHZ\_LIB\_FILENAME*** Failed to locate the authorization callout library configuration file.

***GLOBUS\_GSI\_SYSCONFIG\_ERROR\_GETTING\_GAA\_FILENAME*** Failed to locate the gaa configuration file.

***GLOBUS\_GSI\_SYSCONFIG\_ERROR\_FILE\_NOT\_DIR*** File is not a directory.

***GLOBUS\_GSI\_SYSCONFIG\_ERROR\_LAST*** Last marker - never used.

### **3.6.1.2 enum globus\_gsi\_proxy\_file\_type\_t**

Enumerator used to keep track of input/output types of filenames.

#### **Enumeration values:**

***GLOBUS\_PROXY\_FILE\_INPUT*** The proxy filename is intended for reading (it should already exist).

***GLOBUS\_PROXY\_FILE\_OUTPUT*** The proxy filename is intended for writing (it does not need to exist).

## Index

Activation, 21

Datatypes, 22

Defines, 1

Functions for all platforms, 20

Functions for UNIX platforms, 5

Functions for Win32 platforms, 13

globus\_gsi\_proxy\_file\_type\_t

    globus\_gsi\_sysconfig\_datatypes, 24

globus\_gsi\_sysconfig\_activation

    GLOBUS\_GSI\_SYSCONFIG\_MODULE, 21

GLOBUS\_GSI\_SYSCONFIG\_CHECK\_-  
    CERTFILE

    globus\_gsi\_system\_config\_defines, 2

globus\_gsi\_sysconfig\_check\_certfile\_unix

    globus\_gsi\_sysconfig\_unix, 9

GLOBUS\_GSI\_SYSCONFIG\_CHECK\_KEYFILE

    globus\_gsi\_system\_config\_defines, 2

globus\_gsi\_sysconfig\_check\_keyfile\_unix

    globus\_gsi\_sysconfig\_unix, 9

globus\_gsi\_sysconfig\_datatypes

    globus\_gsi\_proxy\_file\_type\_t, 24

    GLOBUS\_GSI\_SYSCONFIG\_ERROR\_-

        CHECKING\_FILE\_EXISTS, 23

    GLOBUS\_GSI\_SYSCONFIG\_ERROR\_-

        CHECKING\_SUPERUSER, 23

    GLOBUS\_GSI\_SYSCONFIG\_ERROR\_-

        ERRNO, 23

    GLOBUS\_GSI\_SYSCONFIG\_ERROR\_-

        FILE\_BAD\_PERMISSIONS, 23

    GLOBUS\_GSI\_SYSCONFIG\_ERROR\_-

        FILE\_DOES\_NOT\_EXIST, 23

    GLOBUS\_GSI\_SYSCONFIG\_ERROR\_-

        FILE\_HAS\_CHANGED, 24

    GLOBUS\_GSI\_SYSCONFIG\_ERROR\_-

        FILE\_HAS\_LINKS, 23

    GLOBUS\_GSI\_SYSCONFIG\_ERROR\_-

        FILE\_IS\_DIR, 23

    GLOBUS\_GSI\_SYSCONFIG\_ERROR\_-

        FILE\_NOT\_DIR, 24

    GLOBUS\_GSI\_SYSCONFIG\_ERROR\_-

        FILE\_NOT\_OWNED, 23

    GLOBUS\_GSI\_SYSCONFIG\_ERROR\_-

        FILE\_NOT\_REGULAR, 23

    GLOBUS\_GSI\_SYSCONFIG\_ERROR\_-

        FILE\_ZERO\_LENGTH, 23

    GLOBUS\_GSI\_SYSCONFIG\_ERROR\_-

        GETTING\_AUTHZ\_FILENAME, 23

    GLOBUS\_GSI\_SYSCONFIG\_ERROR\_-

        GETTING\_AUTHZ\_LIB\_FILENAME,

24

    GLOBUS\_GSI\_SYSCONFIG\_ERROR\_-  
        GETTING\_CA\_CERT\_FILENAMES,  
23

    GLOBUS\_GSI\_SYSCONFIG\_ERROR\_-  
        GETTING\_CERT\_DIR, 23

    GLOBUS\_GSI\_SYSCONFIG\_ERROR\_-  
        GETTING\_CERT\_FILENAME, 23

    GLOBUS\_GSI\_SYSCONFIG\_ERROR\_-  
        GETTING\_CERT\_STRING, 23

    GLOBUS\_GSI\_SYSCONFIG\_ERROR\_-  
        GETTING\_CWD, 23

    GLOBUS\_GSI\_SYSCONFIG\_ERROR\_-  
        GETTING\_DELEG\_FILENAME, 23

    GLOBUS\_GSI\_SYSCONFIG\_ERROR\_-  
        GETTING\_GAA\_FILENAME, 24

    GLOBUS\_GSI\_SYSCONFIG\_ERROR\_-  
        GETTING\_GRIDMAP\_FILENAME,  
23

    GLOBUS\_GSI\_SYSCONFIG\_ERROR\_-  
        GETTING\_HOME\_DIR, 23

    GLOBUS\_GSI\_SYSCONFIG\_ERROR\_-  
        GETTING\_KEY\_STRING, 23

    GLOBUS\_GSI\_SYSCONFIG\_ERROR\_-  
        GETTING\_PROXY\_FILENAME, 23

    GLOBUS\_GSI\_SYSCONFIG\_ERROR\_-  
        GETTING\_PW\_ENTRY, 23

    GLOBUS\_GSI\_SYSCONFIG\_ERROR\_-  
        GETTING\_SIGNING\_POLICY, 23

    GLOBUS\_GSI\_SYSCONFIG\_ERROR\_-  
        LAST, 24

    GLOBUS\_GSI\_SYSCONFIG\_ERROR\_-  
        REMOVING\_OWNED\_FILES, 23

    GLOBUS\_GSI\_SYSCONFIG\_ERROR\_-  
        SETTING\_PERMS, 23

    GLOBUS\_GSI\_SYSCONFIG\_ERROR\_-  
        SUCCESS, 23

    globus\_gsi\_sysconfig\_error\_t, 23

    GLOBUS\_GSI\_SYSCONFIG\_INVALID\_-  
        ARG, 23

    GLOBUS\_PROXY\_FILE\_INPUT, 24

    GLOBUS\_PROXY\_FILE\_OUTPUT, 24

GLOBUS\_GSI\_SYSCONFIG\_DIR\_EXISTS

    globus\_gsi\_system\_config\_defines, 2

globus\_gsi\_sysconfig\_dir\_exists\_unix

    globus\_gsi\_sysconfig\_unix, 9

globus\_gsi\_sysconfig\_dir\_exists\_win32

    globus\_gsi\_sysconfig\_win32, 16

GLOBUS\_GSI\_SYSCONFIG\_ERROR\_-  
    CHECKING\_FILE\_EXISTS

    globus\_gsi\_sysconfig\_datatypes, 23

GLOBUS\_GSI\_SYSCONFIG\_ERROR\_-  
    CHECKING\_SUPERUSER

    globus\_gsi\_sysconfig\_datatypes, 23

GLOBUS\_GSI\_SYSCONFIG\_ERROR\_ERRNO  
     globus\_gsi\_sysconfig\_datatypes, 23  
 GLOBUS\_GSI\_SYSCONFIG\_ERROR\_FILE\_-  
     BAD\_PERMISSIONS  
     globus\_gsi\_sysconfig\_datatypes, 23  
 GLOBUS\_GSI\_SYSCONFIG\_ERROR\_FILE\_-  
     DOES\_NOT\_EXIST  
     globus\_gsi\_sysconfig\_datatypes, 23  
 GLOBUS\_GSI\_SYSCONFIG\_ERROR\_FILE\_-  
     HAS\_CHANGED  
     globus\_gsi\_sysconfig\_datatypes, 24  
 GLOBUS\_GSI\_SYSCONFIG\_ERROR\_FILE\_-  
     HAS\_LINKS  
     globus\_gsi\_sysconfig\_datatypes, 23  
 GLOBUS\_GSI\_SYSCONFIG\_ERROR\_FILE\_IS\_-  
     DIR  
     globus\_gsi\_sysconfig\_datatypes, 23  
 GLOBUS\_GSI\_SYSCONFIG\_ERROR\_FILE\_-  
     NOT\_DIR  
     globus\_gsi\_sysconfig\_datatypes, 24  
 GLOBUS\_GSI\_SYSCONFIG\_ERROR\_FILE\_-  
     NOT\_OWNED  
     globus\_gsi\_sysconfig\_datatypes, 23  
 GLOBUS\_GSI\_SYSCONFIG\_ERROR\_FILE\_-  
     NOT\_REGULAR  
     globus\_gsi\_sysconfig\_datatypes, 23  
 GLOBUS\_GSI\_SYSCONFIG\_ERROR\_FILE\_-  
     ZERO\_LENGTH  
     globus\_gsi\_sysconfig\_datatypes, 23  
 GLOBUS\_GSI\_SYSCONFIG\_ERROR\_-  
     GETTING\_AUTHZ\_FILENAME  
     globus\_gsi\_sysconfig\_datatypes, 23  
 GLOBUS\_GSI\_SYSCONFIG\_ERROR\_-  
     GETTING\_AUTHZ\_LIB\_FILENAME  
     globus\_gsi\_sysconfig\_datatypes, 24  
 GLOBUS\_GSI\_SYSCONFIG\_ERROR\_-  
     GETTING\_CA\_CERT\_FILENAMES  
     globus\_gsi\_sysconfig\_datatypes, 23  
 GLOBUS\_GSI\_SYSCONFIG\_ERROR\_-  
     GETTING\_CERT\_DIR  
     globus\_gsi\_sysconfig\_datatypes, 23  
 GLOBUS\_GSI\_SYSCONFIG\_ERROR\_-  
     GETTING\_CERT\_FILENAME  
     globus\_gsi\_sysconfig\_datatypes, 23  
 GLOBUS\_GSI\_SYSCONFIG\_ERROR\_-  
     GETTING\_CERT\_STRING  
     globus\_gsi\_sysconfig\_datatypes, 23  
 GLOBUS\_GSI\_SYSCONFIG\_ERROR\_-  
     GETTING\_CWD  
     globus\_gsi\_sysconfig\_datatypes, 23  
 GLOBUS\_GSI\_SYSCONFIG\_ERROR\_-  
     GETTING\_DELEG\_FILENAME  
     globus\_gsi\_sysconfig\_datatypes, 23  
 GLOBUS\_GSI\_SYSCONFIG\_ERROR\_-  
     GETTING\_GAA\_FILENAME  
     globus\_gsi\_sysconfig\_datatypes, 24

GLOBUS\_GSI\_SYSCONFIG\_ERROR\_-  
     GETTING\_GRIDMAP\_FILENAME  
     globus\_gsi\_sysconfig\_datatypes, 23  
 GLOBUS\_GSI\_SYSCONFIG\_ERROR\_-  
     GETTING\_HOME\_DIR  
     globus\_gsi\_sysconfig\_datatypes, 23  
 GLOBUS\_GSI\_SYSCONFIG\_ERROR\_-  
     GETTING\_KEY\_STRING  
     globus\_gsi\_sysconfig\_datatypes, 23  
 GLOBUS\_GSI\_SYSCONFIG\_ERROR\_-  
     GETTING\_PROXY\_FILENAME  
     globus\_gsi\_sysconfig\_datatypes, 23  
 GLOBUS\_GSI\_SYSCONFIG\_ERROR\_-  
     GETTING\_PW\_ENTRY  
     globus\_gsi\_sysconfig\_datatypes, 23  
 GLOBUS\_GSI\_SYSCONFIG\_ERROR\_-  
     GETTING\_SIGNING\_POLICY  
     globus\_gsi\_sysconfig\_datatypes, 23  
 GLOBUS\_GSI\_SYSCONFIG\_ERROR\_LAST  
     globus\_gsi\_sysconfig\_datatypes, 24  
 GLOBUS\_GSI\_SYSCONFIG\_ERROR\_-  
     REMOVING\_OWNED\_FILES  
     globus\_gsi\_sysconfig\_datatypes, 23  
 GLOBUS\_GSI\_SYSCONFIG\_ERROR\_-  
     SETTING\_PERMS  
     globus\_gsi\_sysconfig\_datatypes, 23  
 GLOBUS\_GSI\_SYSCONFIG\_ERROR\_SUCCESS  
     globus\_gsi\_sysconfig\_datatypes, 23  
 globus\_gsi\_sysconfig\_error\_t  
     globus\_gsi\_sysconfig\_datatypes, 23  
 GLOBUS\_GSI\_SYSCONFIG\_FILE\_EXISTS  
     globus\_gsi\_system\_config\_defines, 2  
 globus\_gsi\_sysconfig\_file\_exists\_unix  
     globus\_gsi\_sysconfig\_unix, 9  
 globus\_gsi\_sysconfig\_file\_exists\_win32  
     globus\_gsi\_sysconfig\_win32, 15  
 GLOBUS\_GSI\_SYSCONFIG\_GET\_AUTHZ\_-  
     CONF\_FILENAME  
     globus\_gsi\_system\_config\_defines, 4  
 globus\_gsi\_sysconfig\_get\_authz\_conf\_filename\_-  
     unix  
     globus\_gsi\_sysconfig\_unix, 13  
 globus\_gsi\_sysconfig\_get\_authz\_conf\_filename\_-  
     win32  
     globus\_gsi\_sysconfig\_win32, 19  
 globus\_gsi\_sysconfig\_get\_authz\_lib\_conf\_-  
     filename\_unix  
     globus\_gsi\_sysconfig\_unix, 13  
 GLOBUS\_GSI\_SYSCONFIG\_GET\_CA\_CERT\_-  
     FILES  
     globus\_gsi\_system\_config\_defines, 3  
 globus\_gsi\_sysconfig\_get\_ca\_cert\_files\_unix  
     globus\_gsi\_sysconfig\_unix, 12  
 globus\_gsi\_sysconfig\_get\_ca\_cert\_files\_win32  
     globus\_gsi\_sysconfig\_win32, 19  
 GLOBUS\_GSI\_SYSCONFIG\_GET\_CERT\_DIR

- globus\_gsi\_system\_config\_defines, 3
- globus\_gsi\_sysconfig\_get\_cert\_dir\_unix
  - globus\_gsi\_sysconfig\_unix, 10
- globus\_gsi\_sysconfig\_get\_cert\_dir\_win32
  - globus\_gsi\_sysconfig\_win32, 16
- GLOBUS\_GSI\_SYSCONFIG\_GET\_CURRENT\_-  
WORKING\_DIR
  - globus\_gsi\_system\_config\_defines, 3
- globus\_gsi\_sysconfig\_get\_current\_working\_dir\_-  
unix
  - globus\_gsi\_sysconfig\_unix, 8
- globus\_gsi\_sysconfig\_get\_current\_working\_dir\_-  
win32
  - globus\_gsi\_sysconfig\_win32, 16
- GLOBUS\_GSI\_SYSCONFIG\_GET\_GAA\_-  
CONF\_FILENAME
  - globus\_gsi\_system\_config\_defines, 4
- globus\_gsi\_sysconfig\_get\_gaa\_conf\_filename\_unix
  - globus\_gsi\_sysconfig\_unix, 13
- globus\_gsi\_sysconfig\_get\_gaa\_conf\_filename\_-  
win32
  - globus\_gsi\_sysconfig\_win32, 20
- GLOBUS\_GSI\_SYSCONFIG\_GET\_GRIDMAP\_-  
FILENAME
  - globus\_gsi\_system\_config\_defines, 4
- globus\_gsi\_sysconfig\_get\_gridmap\_filename\_unix
  - globus\_gsi\_sysconfig\_unix, 13
- globus\_gsi\_sysconfig\_get\_gridmap\_filename\_-  
win32
  - globus\_gsi\_sysconfig\_win32, 19
- GLOBUS\_GSI\_SYSCONFIG\_GET\_HOME\_DIR
  - globus\_gsi\_system\_config\_defines, 2
- globus\_gsi\_sysconfig\_get\_home\_dir\_unix
  - globus\_gsi\_sysconfig\_unix, 9
- GLOBUS\_GSI\_SYSCONFIG\_GET\_HOST\_-  
CERT\_FILENAME
  - globus\_gsi\_system\_config\_defines, 3
- globus\_gsi\_sysconfig\_get\_host\_cert\_filename\_unix
  - globus\_gsi\_sysconfig\_unix, 10
- globus\_gsi\_sysconfig\_get\_host\_cert\_filename\_-  
win32
  - globus\_gsi\_sysconfig\_win32, 17
- GLOBUS\_GSI\_SYSCONFIG\_GET\_PROC\_ID\_-  
STRING
  - globus\_gsi\_system\_config\_defines, 4
- globus\_gsi\_sysconfig\_get\_proc\_id\_string\_unix
  - globus\_gsi\_sysconfig\_unix, 8
- GLOBUS\_GSI\_SYSCONFIG\_GET\_PROXY\_-  
FILENAME
  - globus\_gsi\_system\_config\_defines, 3
- globus\_gsi\_sysconfig\_get\_proxy\_filename\_unix
  - globus\_gsi\_sysconfig\_unix, 11
- globus\_gsi\_sysconfig\_get\_proxy\_filename\_win32
  - globus\_gsi\_sysconfig\_win32, 18
- GLOBUS\_GSI\_SYSCONFIG\_GET\_SERVICE\_-  
CERT\_FILENAME

- globus\_gsi\_system\_config\_defines, 3
- globus\_gsi\_sysconfig\_get\_service\_cert\_filename\_-  
unix
  - globus\_gsi\_sysconfig\_unix, 11
- globus\_gsi\_sysconfig\_get\_service\_cert\_filename\_-  
win32
  - globus\_gsi\_sysconfig\_win32, 18
- GLOBUS\_GSI\_SYSCONFIG\_GET\_SIGNING\_-  
POLICY\_FILENAME
  - globus\_gsi\_system\_config\_defines, 3
- globus\_gsi\_sysconfig\_get\_signing\_policy\_-  
filename\_unix
  - globus\_gsi\_sysconfig\_unix, 12
- globus\_gsi\_sysconfig\_get\_signing\_policy\_-  
filename\_win32
  - globus\_gsi\_sysconfig\_win32, 20
- GLOBUS\_GSI\_SYSCONFIG\_GET\_UNIQUE\_-  
PROXY\_FILENAME
  - globus\_gsi\_system\_config\_defines, 5
- globus\_gsi\_sysconfig\_get\_unique\_proxy\_filename
  - globus\_gsi\_sysconfig\_shared, 21
- GLOBUS\_GSI\_SYSCONFIG\_GET\_USER\_-  
CERT\_FILENAME
  - globus\_gsi\_system\_config\_defines, 3
- globus\_gsi\_sysconfig\_get\_user\_cert\_filename\_unix
  - globus\_gsi\_sysconfig\_unix, 10
- globus\_gsi\_sysconfig\_get\_user\_cert\_filename\_-  
win32
  - globus\_gsi\_sysconfig\_win32, 17
- GLOBUS\_GSI\_SYSCONFIG\_GET\_USER\_ID\_-  
STRING
  - globus\_gsi\_system\_config\_defines, 4
- globus\_gsi\_sysconfig\_get\_user\_id\_string\_unix
  - globus\_gsi\_sysconfig\_unix, 7
- GLOBUS\_GSI\_SYSCONFIG\_GET\_USERNAME
  - globus\_gsi\_system\_config\_defines, 4
- globus\_gsi\_sysconfig\_get\_username\_unix
  - globus\_gsi\_sysconfig\_unix, 7
- GLOBUS\_GSI\_SYSCONFIG\_INVALID\_ARG
  - globus\_gsi\_sysconfig\_datatypes, 23
- GLOBUS\_GSI\_SYSCONFIG\_IS\_SUPERUSER
  - globus\_gsi\_system\_config\_defines, 4
- globus\_gsi\_sysconfig\_is\_superuser\_unix
  - globus\_gsi\_sysconfig\_unix, 12
- globus\_gsi\_sysconfig\_is\_superuser\_win32
  - globus\_gsi\_sysconfig\_win32, 20
- GLOBUS\_GSI\_SYSCONFIG\_MAKE\_-  
ABSOLUTE\_PATH\_FOR\_FILENAME
  - globus\_gsi\_system\_config\_defines, 3
- globus\_gsi\_sysconfig\_make\_absolute\_path\_for\_-  
filename\_unix
  - globus\_gsi\_sysconfig\_unix, 8
- globus\_gsi\_sysconfig\_make\_absolute\_path\_for\_-  
filename\_win32
  - globus\_gsi\_sysconfig\_win32, 16
- GLOBUS\_GSI\_SYSCONFIG\_MODULE

- globus\_gsi\_sysconfig\_activation, 21
- GLOBAL\_GSI\_SYSCONFIG\_REMOVE\_ALL\_-  
OWNED\_FILES
- globus\_gsi\_system\_config\_defines, 4
- globus\_gsi\_sysconfig\_remove\_all\_owned\_files\_-  
unix
- globus\_gsi\_sysconfig\_unix, 12
- globus\_gsi\_sysconfig\_remove\_all\_owned\_files\_-  
win32
- globus\_gsi\_sysconfig\_win32, 19
- GLOBAL\_GSI\_SYSCONFIG\_SET\_KEY\_-  
PERMISSIONS
- globus\_gsi\_system\_config\_defines, 2
- globus\_gsi\_sysconfig\_set\_key\_permissions\_unix
- globus\_gsi\_sysconfig\_unix, 7
- globus\_gsi\_sysconfig\_set\_key\_permissions\_win32
- globus\_gsi\_sysconfig\_win32, 15
- globus\_gsi\_sysconfig\_shared
- globus\_gsi\_sysconfig\_get\_unique\_proxy\_-  
filename, 21
- GLOBAL\_GSI\_SYSCONFIG\_SPLIT\_DIR\_-  
AND\_FILENAME
- globus\_gsi\_system\_config\_defines, 4
- globus\_gsi\_sysconfig\_split\_dir\_and\_filename\_unix
- globus\_gsi\_sysconfig\_unix, 8
- globus\_gsi\_sysconfig\_split\_dir\_and\_filename\_-  
win32
- globus\_gsi\_sysconfig\_win32, 16
- globus\_gsi\_sysconfig\_unix
- globus\_gsi\_sysconfig\_check\_certfile\_unix, 9
- globus\_gsi\_sysconfig\_check\_keyfile\_unix, 9
- globus\_gsi\_sysconfig\_dir\_exists\_unix, 9
- globus\_gsi\_sysconfig\_file\_exists\_unix, 9
- globus\_gsi\_sysconfig\_get\_authz\_conf\_-  
filename\_unix, 13
- globus\_gsi\_sysconfig\_get\_authz\_lib\_conf\_-  
filename\_unix, 13
- globus\_gsi\_sysconfig\_get\_ca\_cert\_files\_unix,  
12
- globus\_gsi\_sysconfig\_get\_cert\_dir\_unix, 10
- globus\_gsi\_sysconfig\_get\_current\_working\_-  
dir\_unix, 8
- globus\_gsi\_sysconfig\_get\_gaa\_conf\_-  
filename\_unix, 13
- globus\_gsi\_sysconfig\_get\_gridmap\_-  
filename\_unix, 13
- globus\_gsi\_sysconfig\_get\_home\_dir\_unix, 9
- globus\_gsi\_sysconfig\_get\_host\_cert\_-  
filename\_unix, 10
- globus\_gsi\_sysconfig\_get\_proc\_id\_string\_-  
unix, 8
- globus\_gsi\_sysconfig\_get\_proxy\_filename\_-  
unix, 11
- globus\_gsi\_sysconfig\_get\_service\_cert\_-  
filename\_unix, 11

- globus\_gsi\_sysconfig\_get\_signing\_policy\_-  
filename\_unix, 12
- globus\_gsi\_sysconfig\_get\_user\_cert\_-  
filename\_unix, 10
- globus\_gsi\_sysconfig\_get\_user\_id\_string\_-  
unix, 7
- globus\_gsi\_sysconfig\_get\_username\_unix, 7
- globus\_gsi\_sysconfig\_is\_superuser\_unix, 12
- globus\_gsi\_sysconfig\_make\_absolute\_path\_-  
for\_filename\_unix, 8
- globus\_gsi\_sysconfig\_remove\_all\_owned\_-  
files\_unix, 12
- globus\_gsi\_sysconfig\_set\_key\_permissions\_-  
unix, 7
- globus\_gsi\_sysconfig\_split\_dir\_and\_-  
filename\_unix, 8
- globus\_gsi\_sysconfig\_win32
- globus\_gsi\_sysconfig\_dir\_exists\_win32, 16
- globus\_gsi\_sysconfig\_file\_exists\_win32, 15
- globus\_gsi\_sysconfig\_get\_authz\_conf\_-  
filename\_win32, 19
- globus\_gsi\_sysconfig\_get\_ca\_cert\_files\_-  
win32, 19
- globus\_gsi\_sysconfig\_get\_cert\_dir\_win32, 16
- globus\_gsi\_sysconfig\_get\_current\_working\_-  
dir\_win32, 16
- globus\_gsi\_sysconfig\_get\_gaa\_conf\_-  
filename\_win32, 20
- globus\_gsi\_sysconfig\_get\_gridmap\_-  
filename\_win32, 19
- globus\_gsi\_sysconfig\_get\_host\_cert\_-  
filename\_win32, 17
- globus\_gsi\_sysconfig\_get\_proxy\_filename\_-  
win32, 18
- globus\_gsi\_sysconfig\_get\_service\_cert\_-  
filename\_win32, 18
- globus\_gsi\_sysconfig\_get\_signing\_policy\_-  
filename\_win32, 20
- globus\_gsi\_sysconfig\_get\_user\_cert\_-  
filename\_win32, 17
- globus\_gsi\_sysconfig\_is\_superuser\_win32, 20
- globus\_gsi\_sysconfig\_make\_absolute\_path\_-  
for\_filename\_win32, 16
- globus\_gsi\_sysconfig\_remove\_all\_owned\_-  
files\_win32, 19
- globus\_gsi\_sysconfig\_set\_key\_permissions\_-  
win32, 15
- globus\_gsi\_sysconfig\_split\_dir\_and\_-  
filename\_win32, 16
- globus\_gsi\_system\_config\_defines
- GLOBAL\_GSI\_SYSCONFIG\_CHECK\_-  
CERTFILE, 2
- GLOBAL\_GSI\_SYSCONFIG\_CHECK\_-  
KEYFILE, 2
- GLOBAL\_GSI\_SYSCONFIG\_DIR\_EXISTS,

GLOBUS\_GSI\_SYSCONFIG\_FILE\_-  
     EXISTS, 2  
 GLOBUS\_GSI\_SYSCONFIG\_GET\_-  
     AUTHZ\_CONF\_FILENAME, 4  
 GLOBUS\_GSI\_SYSCONFIG\_GET\_CA\_-  
     CERT\_FILES, 3  
 GLOBUS\_GSI\_SYSCONFIG\_GET\_CERT\_-  
     DIR, 3  
 GLOBUS\_GSI\_SYSCONFIG\_GET\_-  
     CURRENT\_WORKING\_DIR, 3  
 GLOBUS\_GSI\_SYSCONFIG\_GET\_GAA\_-  
     CONF\_FILENAME, 4  
 GLOBUS\_GSI\_SYSCONFIG\_GET\_-  
     GRIDMAP\_FILENAME, 4  
 GLOBUS\_GSI\_SYSCONFIG\_GET\_HOME\_-  
     DIR, 2  
 GLOBUS\_GSI\_SYSCONFIG\_GET\_HOST\_-  
     CERT\_FILENAME, 3  
 GLOBUS\_GSI\_SYSCONFIG\_GET\_PROC\_-  
     ID\_STRING, 4  
 GLOBUS\_GSI\_SYSCONFIG\_GET\_-  
     PROXY\_FILENAME, 3  
 GLOBUS\_GSI\_SYSCONFIG\_GET\_-  
     SERVICE\_CERT\_FILENAME, 3  
 GLOBUS\_GSI\_SYSCONFIG\_GET\_-  
     SIGNING\_POLICY\_FILENAME,  
     3  
 GLOBUS\_GSI\_SYSCONFIG\_GET\_-  
     UNIQUE\_PROXY\_FILENAME, 5  
 GLOBUS\_GSI\_SYSCONFIG\_GET\_USER\_-  
     CERT\_FILENAME, 3  
 GLOBUS\_GSI\_SYSCONFIG\_GET\_USER\_-  
     ID\_STRING, 4  
 GLOBUS\_GSI\_SYSCONFIG\_GET\_-  
     USERNAME, 4  
 GLOBUS\_GSI\_SYSCONFIG\_IS\_-  
     SUPERUSER, 4  
 GLOBUS\_GSI\_SYSCONFIG\_MAKE\_-  
     ABSOLUTE\_PATH\_FOR\_FILENAME,  
     3  
 GLOBUS\_GSI\_SYSCONFIG\_REMOVE\_-  
     ALL\_OWNED\_FILES, 4  
 GLOBUS\_GSI\_SYSCONFIG\_SET\_KEY\_-  
     PERMISSIONS, 2  
 GLOBUS\_GSI\_SYSCONFIG\_SPLIT\_DIR\_-  
     AND\_FILENAME, 4  
 GLOBUS\_PROXY\_FILE\_INPUT  
     globus\_gsi\_sysconfig\_datatypes, 24  
 GLOBUS\_PROXY\_FILE\_OUTPUT  
     globus\_gsi\_sysconfig\_datatypes, 24