

globus gssapi error

2.5

Generated by Doxygen 1.7.3

Tue Jul 5 2011 08:27:12

Contents

1	Module Index	1
1.1	Modules	1
2	Module Documentation	2
2.1	Globus GSSAPI Error API	2
2.1.1	Detailed Description	2
2.2	Error Construction	2
2.2.1	Detailed Description	3
2.2.2	Define Documentation	3
2.2.3	Function Documentation	3
2.3	Error Data Accessors and Modifiers	4
2.3.1	Detailed Description	4
2.3.2	Function Documentation	5
2.4	Error Handling Helpers	5
2.4.1	Detailed Description	6
2.4.2	Function Documentation	6

1 Module Index

1.1 Modules


Here is a list of all modules:

Globus GSSAPI Error API	2
Error Construction	2
Error Data Accessors and Modifiers	4
Error Handling Helpers	5

2 Module Documentation

2.1 Globus GSSAPI Error API

Collaboration diagram for Globus GSSAPI Error API:



Modules

- [Error Construction](#)
- [Error Data Accessors and Modifiers](#)
- [Error Handling Helpers](#)

2.1.1 Detailed Description

These `globus_error` functions are motivated by the desire to provide a easier way of generating new error types, while at the same time preserving all features (e.g. memory management, chaining) of the current error handling framework. The functions in this API are auxiliary to the function in the Globus Generic Error API in the sense that they provide a wrapper for representing GSSAPI errors in terms of a `globus_error_t`.

Any program that uses Globus GSSAPI Error functions must include "`globus_error_gssapi.h`".

2.2 Error Construction

Create and initialize a Globus GSSAPI Error object.

Collaboration diagram for Error Construction:



Defines

- #define [GLOBUS_ERROR_TYPE_GSSAPI](#)

Construct Error

- globus_object_t * [globus_error_construct_gssapi_error](#) (globus_module_descriptor_t *base_source, globus_object_t *base_cause, const OM_uint32 major_status, const OM_uint32 minor_status)

Initialize Error

- globus_object_t * [globus_error_initialize_gssapi_error](#) (globus_object_t *error, globus_module_descriptor_t *base_source, globus_object_t *base_cause, const OM_uint32 major_status, const OM_uint32 minor_status)

2.2.1 Detailed Description

Create and initialize a Globus GSSAPI Error object. This section defines operations to create and initialize Globus GSSAPI Error objects.

2.2.2 Define Documentation

2.2.2.1 #define GLOBUS_ERROR_TYPE_GSSAPI

Error type definition.

2.2.3 Function Documentation

2.2.3.1 globus_object_t* globus_error_construct_gssapi_error (globus_module_descriptor_t * base_source, globus_object_t * base_cause, const OM_uint32 major_status, const OM_uint32 minor_status)

Allocate and initialize an error of type GLOBUS_ERROR_TYPE_GSSAPI.

Parameters

<i>base_source</i>	Pointer to the originating module.
<i>base_cause</i>	The error object causing the error. If this is the original error, this parameter may be NULL.
<i>major_status</i>	The GSSAPI major status
<i>minor_status</i>	The GSSAPI minor status

Returns

The resulting error object. It is the user's responsibility to eventually free this object using globus_object_free(). A globus_result_t may be obtained by calling globus_error_put() on this object.

2.2.3.2 `globus_object_t* globus_error_initialize_gssapi_error (globus_object_t * error,
globus_module_descriptor_t * base_source, globus_object_t * base_cause, const OM_uint32
major_status, const OM_uint32 minor_status)`

Initialize a previously allocated error of type GLOBUS_ERROR_TYPE_GSSAPI.

Parameters

<i>error</i>	The previously allocated error object.
<i>base_source</i>	Pointer to the originating module.
<i>base_cause</i>	The error object causing the error. If this is the original error this paramater may be NULL.
<i>major_status</i>	The GSSAPI major status
<i>minor_status</i>	The GSSAPI minor status

Returns

The resulting error object. You may have to call `globus_error_put()` on this object before passing it on.

2.3 Error Data Accessors and Modifiers

Get and set data in a Globus GSSAPI Error object.

Collaboration diagram for Error Data Accessors and Modifiers:



Get Major Status

- OM_uint32 [globus_error_gssapi_get_major_status](#) (globus_object_t *error)

Set Major Status

- void [globus_error_gssapi_set_major_status](#) (globus_object_t *error, const OM_uint32 major_status)

Get Minor Status

- OM_uint32 [globus_error_gssapi_get_minor_status](#) (globus_object_t *error)

2.3.1 Detailed Description

Get and set data in a Globus GSSAPI Error object. This section defines operations for accessing and modifying data in a Globus GSSAPI Error object.

2.3.2 Function Documentation

2.3.2.1 OM_uint32 globus_error_gssapi_get_major_status (globus_object_t * *error*)

Retrieve the major status from a gssapi error object.

Parameters

<i>error</i>	The error from which to retrieve the major status
--------------	---

Returns

The major status stored in the object

2.3.2.2 void globus_error_gssapi_set_major_status (globus_object_t * *error*, const OM_uint32 *major_status*)

Set the major status in a gssapi error object.

Parameters

<i>error</i>	The error object for which to set the major status
<i>major_status</i>	The major status

Returns

void

2.3.2.3 OM_uint32 globus_error_gssapi_get_minor_status (globus_object_t * *error*)

Retrieve the minor status from a gssapi error object.

Parameters

<i>error</i>	The error from which to retrieve the minor status
--------------	---

Returns

The minor status stored in the object

2.4 Error Handling Helpers

Helper functions for dealing with Globus GSSAPI Error objects.

Collaboration diagram for Error Handling Helpers:



Error Match

- globus_bool_t [globus_error_gssapi_match](#) (globus_object_t *error, globus_module_descriptor_t *module, const OM_uint32 major_status)

Wrap GSSAPI Error

- globus_object_t * [globus_error_wrap_gssapi_error](#) (globus_module_descriptor_t *base_source, OM_uint32 major_status, OM_uint32 minor_status, int type, const char *source_file, const char *source_func, int source_line, const char *short_desc_format,...)

2.4.1 Detailed Description

Helper functions for dealing with Globus GSSAPI Error objects. This section defines utility functions for dealing with Globus GSSAPI Error objects.

2.4.2 Function Documentation

2.4.2.1 globus_bool_t globus_error_gssapi_match (globus_object_t *error, globus_module_descriptor_t * module, const OM_uint32 major_status)

Check whether the error originated from a specific module and match a specific major status.

This function checks whether the error or any of it's causative errors originated from a specific module and contains a specific major status. If the module descriptor is left unspecified this function will check for any error of the specified major_status and vice versa.

Parameters

<i>error</i>	The error object for which to perform the check
<i>module</i>	The module descriptor to check for
<i>major_status</i>	The major status to check for

Returns

GLOBUS_TRUE - the error matched the module and major status GLOBUS_FALSE - the error failed to match the module and major status

2.4.2.2 `globus_object_t* globus_error_wrap_gssapi_error (globus_module_descriptor_t * base_source, OM_uint32 major_status, OM_uint32 minor_status, int type, const char * source_file, const char * source_func, int source_line, const char * short_desc_format, ...)`

Allocate and initialize an error of type GLOBUS_ERROR_TYPE_GLOBUS which contains a causal error of type GLOBUS_ERROR_TYPE_GSSAPI.

Parameters

<i>base_source</i>	Pointer to the originating module.
<i>major_status</i>	The major status to use when generating the causal error.
<i>minor_status</i>	The minor status to use when generating the causal error.
<i>type</i>	The error type. We may reserve part of this namespace for common errors. Errors not in this space are assumed to be local to the originating module.
<i>source_file</i>	Name of file. Use __FILE__
<i>source_func</i>	Name of function. Use _globus_func_name and declare your func with GlobusFuncName(<name>)
<i>source_line</i>	Line number. Use __LINE__
<i>short_desc_format</i>	Short format string giving a succinct description of the error. To be passed on to the user.
...	Arguments for the format string.

Returns

The resulting error object. It is the user's responsibility to eventually free this object using `globus_object_free()`. A `globus_result_t` may be obtained by calling `globus_error_put()` on this object.

Index

Error Construction, [2](#)

Error Data Accessors and Modifiers, [3](#)

Error Handling Helpers, [5](#)

Globus GSSAPI Error API, [1](#)

globus_error_construct_gssapi_error

 globus_gssapi_error_object, [2](#)

globus_error_gssapi_get_major_status

 globus_gssapi_error_accessor, [4](#)

globus_error_gssapi_get_minor_status

 globus_gssapi_error_accessor, [4](#)

globus_error_gssapi_match

 globus_gssapi_error_utility, [5](#)

globus_error_gssapi_set_major_status

 globus_gssapi_error_accessor, [4](#)

globus_error_initialize_gssapi_error

 globus_gssapi_error_object, [3](#)

GLOBAL_ERROR_TYPE_GSSAPI

 globus_gssapi_error_object, [2](#)

globus_error_wrap_gssapi_error

 globus_gssapi_error_utility, [6](#)

globus_gssapi_error_accessor

 globus_error_gssapi_get_major_status, [4](#)

 globus_error_gssapi_get_minor_status, [4](#)

 globus_error_gssapi_set_major_status, [4](#)

globus_gssapi_error_object

 globus_error_construct_gssapi_error, [2](#)

 globus_error_initialize_gssapi_error, [3](#)

 GLOBAL_ERROR_TYPE_GSSAPI, [2](#)

globus_gssapi_error_utility

 globus_error_gssapi_match, [5](#)

 globus_error_wrap_gssapi_error, [6](#)