

globus authz

0.7

Generated by Doxygen 1.7.3

Sat Feb 26 2011 11:18:06

# Contents

<b>1</b>	<b>Module Index</b>	<b>1</b>
1.1	Modules . . . . .	1
<b>2</b>	<b>Module Documentation</b>	<b>1</b>
2.1	GSI Authorization API . . . . .	1
2.1.1	Function Documentation . . . . .	2
2.2	GSI Credential Constants . . . . .	3
2.2.1	Enumeration Type Documentation . . . . .	3

## 1 Module Index

### 1.1 Modules

Here is a list of all modules:

<b>GSI Authorization API</b>	<b>1</b>
<b>GSI Credential Constants</b>	<b>3</b>

## 2 Module Documentation

### 2.1 GSI Authorization API

#### Initialize Handle

- globus\_result\_t [globus\\_gsi\\_authz\\_handle\\_init](#) (globus\_gsi\_authz\_handle\_t \*handle, const char \*service\_name, const gss\_ctx\_id\_t context, globus\_gsi\_authz\_cb\_t callback, void \*callback\_arg)

#### Authorization decision made here

- globus\_result\_t [globus\\_gsi\\_authorize](#) (globus\_gsi\_authz\_handle\_t handle, const void \*action, const void \*object, globus\_gsi\_authz\_cb\_t callback, void \*callback\_arg)

#### Destroy Handle

- globus\_result\_t [globus\\_gsi\\_authz\\_handle\\_destroy](#) (globus\_gsi\_authz\_handle\_t handle, globus\_gsi\_authz\_cb\_t callback, void \*callback\_arg)

#### Query for authorization identity

- globus\_result\_t [globus\\_gsi\\_authz\\_get\\_authorization\\_identity](#) (globus\_gsi\_authz\_handle\_t handle, char \*\*identity\_ptr, globus\_gsi\_authz\_cb\_t callback, void \*callback\_arg)

## 2.1.1 Function Documentation

**2.1.1.1** `globus_result_t globus_gsi_authz_handle_init ( globus_gsi_authz_handle_t * handle, const char * service_name, const gss_ctx_id_t context, globus_gsi_authz_cb_t callback, void * callback_arg )`

Initializes a handle.

### Parameters

<i>handle</i>	Pointer to the handle that is to be initialized
<i>service_name</i>	Service to authorize access to
<i>context</i>	Security context used to contact the service
<i>callback</i>	Callback function to call when authz handle init completes
<i>callback_arg</i>	Argument to callback function

### Returns

GLOBUS\_SUCCESS if successful A Globus error object on failure:

**2.1.1.2** `globus_result_t globus_gsi_authorize ( globus_gsi_authz_handle_t handle, const void * action, const void * object, globus_gsi_authz_cb_t callback, void * callback_arg )`

Authorization decision made here.

### Parameters

<i>handle</i>	Pointer to the handle that is to be initialized
<i>action</i>	Action to authorize
<i>object</i>	Object that the action pertains to.
<i>callback</i>	Callback function to call when authorization completes
<i>callback_arg</i>	Argument to callback function

### Returns

GLOBUS\_SUCCESS if successful A Globus error object on failure:

**2.1.1.3** `globus_result_t globus_gsi_authz_handle_destroy ( globus_gsi_authz_handle_t handle, globus_gsi_authz_cb_t callback, void * callback_arg )`

Destroy a Globus GSI authz handle.

### Parameters

<i>handle</i>	The handle that is to be destroyed
<i>callback</i>	Callback function to call when handle is destroyed
<i>callback_arg</i>	Argument to callback function

### Returns

GLOBUS\_SUCCESS

#### 2.1.1.4 globus\_result\_t globus\_gsi\_authz\_get\_authorization\_identity ( globus\_gsi\_authz\_handle\_t handle, char \*\* identity\_ptr, globus\_gsi\_authz\_cb\_t callback, void \* callback\_arg )

Query for authorization identity.

##### Parameters

<i>handle</i>	The handle that is to be used for the identity check.
<i>identity_ptr</i>	The authorization identity determined by the authorization handle. This is must be freed by the caller. If the value is NULL (and this function returned GLOBUS_SUCCESS), the caller should use the authenticated identity.
<i>callback</i>	Callback function to call when identity is determined.
<i>callback_arg</i>	Argument to callback function.

##### Returns

GLOBUS\_SUCCESS

## 2.2 GSI Credential Constants

##### Enumerations

- enum globus\_gsi\_authz\_error\_t {  
GLOBUS\_GSI\_AUTHZ\_ERROR\_SUCCESS = 0,  
GLOBUS\_GSI\_AUTHZ\_ERROR\_ERRNO = 1,  
GLOBUS\_GSI\_AUTHZ\_ERROR\_BAD\_PARAMETER = 2,  
GLOBUS\_GSI\_AUTHZ\_ERROR\_CALLOUT = 3 }

#### 2.2.1 Enumeration Type Documentation

##### 2.2.1.1 enum globus\_gsi\_authz\_error\_t

GSI Authz Error codes.

##### Enumerator:

**GLOBUS\_GSI\_AUTHZ\_ERROR\_SUCCESS** Success.  
**GLOBUS\_GSI\_AUTHZ\_ERROR\_ERRNO** Error with system call.  
**GLOBUS\_GSI\_AUTHZ\_ERROR\_BAD\_PARAMETER** Invalid parameter.  
**GLOBUS\_GSI\_AUTHZ\_ERROR\_CALLOUT** Callout returned an error.

## Index

- globus\_gsi\_authz\_constants
  - GLOBUS\_GSI\_AUTHZ\_ERROR\_BAD\_PARAMETER,  
[3](#)
  - GLOBUS\_GSI\_AUTHZ\_ERROR\_CALLOUT, [3](#)
  - GLOBUS\_GSI\_AUTHZ\_ERROR\_ERRNO, [3](#)
  - GLOBUS\_GSI\_AUTHZ\_ERROR\_SUCCESS, [3](#)
- GLOBUS\_GSI\_AUTHZ\_ERROR\_BAD\_PARAMETER
  - globus\_gsi\_authz\_constants, [3](#)
- GLOBUS\_GSI\_AUTHZ\_ERROR\_CALLOUT
  - globus\_gsi\_authz\_constants, [3](#)
- GLOBUS\_GSI\_AUTHZ\_ERROR\_ERRNO
  - globus\_gsi\_authz\_constants, [3](#)
- GLOBUS\_GSI\_AUTHZ\_ERROR\_SUCCESS
  - globus\_gsi\_authz\_constants, [3](#)
- globus\_gsi\_authorize
  - globus\_gsi\_authz, [2](#)
- globus\_gsi\_authz
  - globus\_gsi\_authorize, [2](#)
  - globus\_gsi\_authz\_get\_authorization\_identity, [2](#)
  - globus\_gsi\_authz\_handle\_destroy, [2](#)
  - globus\_gsi\_authz\_handle\_init, [1](#)
- globus\_gsi\_authz\_constants
  - globus\_gsi\_authz\_error\_t, [3](#)
- globus\_gsi\_authz\_error\_t
  - globus\_gsi\_authz\_constants, [3](#)
- globus\_gsi\_authz\_get\_authorization\_identity
  - globus\_gsi\_authz, [2](#)
- globus\_gsi\_authz\_handle\_destroy
  - globus\_gsi\_authz, [2](#)
- globus\_gsi\_authz\_handle\_init
  - globus\_gsi\_authz, [1](#)
- GSI Authorization API, [1](#)
- GSI Credential Constants, [3](#)