

globus gssapi gsi  
10.7

Generated by Doxygen 1.8.4

Mon Aug 26 2013 12:47:52

## Contents

<b>1</b>	<b>Deprecated List</b>	<b>1</b>
<b>2</b>	<b>Module Index</b>	<b>1</b>
2.1	Modules . . . . .	1
<b>3</b>	<b>Module Documentation</b>	<b>1</b>
3.1	Functions for manipulating a buffer set . . . . .	1
3.2	GSI GSS-API Constants . . . . .	2
3.3	Activation . . . . .	3
3.3.1	Detailed Description . . . . .	3
3.3.2	Macro Definition Documentation . . . . .	3
3.4	GSS Req Flags . . . . .	4
3.4.1	Detailed Description . . . . .	4
3.4.2	Macro Definition Documentation . . . . .	4
3.5	GSS Ret Flags . . . . .	5
3.5.1	Detailed Description . . . . .	5
3.5.2	Macro Definition Documentation . . . . .	5
	<b>Index</b>	<b>6</b>

## 1 Deprecated List

### Global GSS\_C\_GLOBUS\_ACCEPT\_PROXY\_SIGNED\_BY\_LIMITED\_PROXY\_FLAG (p. 4)

We now accept proxies signed by limited proxies if they are limited or independent.

## 2 Module Index

### 2.1 Modules

Here is a list of all modules:

<b>Functions for manipulating a buffer set</b>	<b>1</b>
<b>GSI GSS-API Constants</b>	<b>2</b>
<b>Activation</b>	<b>3</b>
<b>GSS Req Flags</b>	<b>4</b>
<b>GSS Ret Flags</b>	<b>5</b>

## **3 Module Documentation**

### **3.1 Functions for manipulating a buffer set**

## 3.2 GSI GSS-API Constants

## 3.3 Activation

### Macros

- **#define GLOBUS\_GSI\_GSSAPI\_MODULE**

#### 3.3.1 Detailed Description

Globus GSI GSSAPI uses standard Globus module activation and deactivation. Before any Globus GSI GSSAPI functions are called, the following function should be called:

```
globus_module_activate(GLOBUS_GSI_GSSAPI_MODULE)
```

This function returns GLOBUS\_SUCCESS if Globus GSI GSSAPI was successfully initialized, and you are therefore allowed to subsequently call Globus GSI GSSAPI functions. Otherwise, an error code is returned, and Globus GSI GSSAPI functions should not subsequently be called. This function may be called multiple times.

To deactivate Globus GSI GSSAPI, the following function should be called:

```
globus_module_deactivate(GLOBUS_GSI_GSSAPI_MODULE)
```

This function should be called once for each time Globus GSI GSSAPI was activated.

Note that it is not mandatory to call the above functions.

#### 3.3.2 Macro Definition Documentation

##### 3.3.2.1 #define GLOBUS\_GSI\_GSSAPI\_MODULE

Module descriptor.

## 3.4 GSS Req Flags

### Macros

- `#define GSS_C_GLOBUS_DONT_ACCEPT_LIMITED_PROXY_FLAG 8192`
- `#define GSS_C_GLOBUS_DELEGATE_LIMITED_PROXY_FLAG 4096`
- `#define GSS_C_GLOBUS_ACCEPT_PROXY_SIGNED_BY_LIMITED_PROXY_FLAG 32768`
- `#define GSS_C_GLOBUS_ALLOW_MISSING_SIGNING_POLICY 65536`
- `#define GSS_C_GLOBUS_FORCE_SSL3 131072`

#### 3.4.1 Detailed Description

These macros set the REQUESTED type of context - these should be set (or not) in the context's req\_flags (or in the context's ret\_flags if accept\_sec\_context is being called)

#### 3.4.2 Macro Definition Documentation

##### 3.4.2.1 `#define GSS_C_GLOBUS_DONT_ACCEPT_LIMITED_PROXY_FLAG 8192`

Set if you don't want a context to accept a limited proxy.

If this flag is set, and a limited proxy is received, the call will not be successful and the context will not be set up

##### 3.4.2.2 `#define GSS_C_GLOBUS_DELEGATE_LIMITED_PROXY_FLAG 4096`

Set if you want the delegated proxy to be a limited proxy.

##### 3.4.2.3 `#define GSS_C_GLOBUS_ACCEPT_PROXY_SIGNED_BY_LIMITED_PROXY_FLAG 32768`

Set if you want to accept proxies signed by limited proxies.

**Deprecated** We now accept proxies signed by limited proxies if they are limited or independent.

##### 3.4.2.4 `#define GSS_C_GLOBUS_ALLOW_MISSING_SIGNING_POLICY 65536`

Set if you want to allow CA certs without a signing policy to verify.

##### 3.4.2.5 `#define GSS_C_GLOBUS_FORCE_SSL3 131072`

Set if you want to force SSLv3 instead of negotiating TLSv1 or SSLv3.

## 3.5 GSS Ret Flags

### Macros

- `#define GSS_C_GLOBUS_RECEIVED_LIMITED_PROXY_FLAG` 8192
- `#define GSS_C_GLOBUS_RECEIVED_LIMITED_PROXY_DURING_DELEGATION_FLAG` 4096

#### 3.5.1 Detailed Description

These macros set the RETURNED context type - these will be set (or not) in the context's `ret_flags`.

#### 3.5.2 Macro Definition Documentation

##### 3.5.2.1 `#define GSS_C_GLOBUS_RECEIVED_LIMITED_PROXY_FLAG` 8192

If the proxy received is a limited proxy, this flag will be set in the returned context flags (`ret_flags`)

##### 3.5.2.2 `#define GSS_C_GLOBUS_RECEIVED_LIMITED_PROXY_DURING_DELEGATION_FLAG` 4096

If the proxy received is a limited proxy received during delegation, this flag is set in the returned flags.

## Index

Activation, 3

    GLOBUS\_GSI\_GSSAPI\_MODULE, 3

Functions for manipulating a buffer set, 1

GLOBUS\_GSI\_GSSAPI\_MODULE

    Activation, 3

GSI GSS-API Constants, 2

GSS Req Flags, 4

    GSS\_C\_GLOBUS\_ACCEPT\_PROXY\_SIGNED\_BY\_LIMITED\_PROXY\_FLAG, 4

    GSS\_C\_GLOBUS\_ALLOW\_MISSING\_SIGNING\_POLICY, 4

    GSS\_C\_GLOBUS\_DELEGATE\_LIMITED\_PROXY\_FLAG, 4

    GSS\_C\_GLOBUS\_DONT\_ACCEPT\_LIMITED\_PROXY\_FLAG, 4

    GSS\_C\_GLOBUS\_FORCE\_SSL3, 4

GSS Ret Flags, 5

    GSS\_C\_GLOBUS\_RECEIVED\_LIMITED\_PROXY\_DURING\_DELEGATION\_FLAG, 5

    GSS\_C\_GLOBUS\_RECEIVED\_LIMITED\_PROXY\_FLAG, 5

GSS\_C\_GLOBUS\_ACCEPT\_PROXY\_SIGNED\_BY\_LIMITED\_PROXY\_FLAG

    GSS Req Flags, 4

GSS\_C\_GLOBUS\_ALLOW\_MISSING\_SIGNING\_POLICY

    GSS Req Flags, 4

GSS\_C\_GLOBUS\_DELEGATE\_LIMITED\_PROXY\_FLAG

    GSS Req Flags, 4

GSS\_C\_GLOBUS\_DONT\_ACCEPT\_LIMITED\_PROXY\_FLAG

    GSS Req Flags, 4

GSS\_C\_GLOBUS\_FORCE\_SSL3

    GSS Req Flags, 4

GSS\_C\_GLOBUS\_RECEIVED\_LIMITED\_PROXY\_DURING\_DELEGATION\_FLAG

    GSS Ret Flags, 5

GSS\_C\_GLOBUS\_RECEIVED\_LIMITED\_PROXY\_FLAG

    GSS Ret Flags, 5