

NASM – The Netwide Assembler

version 2.13.03



© 1996-2017 The NASM Development Team - All Rights Reserved

This document is distributed under the license given in the file LICENSE distributed in the NASM archive.

Contents

Chapter 1: Introduction	17
1.1 What Is NASM?	17
1.1.1 License Conditions.....	17
Chapter 2: Running NASM	19
2.1 NASM Command-Line Syntax	19
2.1.1 The -o Option: Specifying the Output File Name.....	19
2.1.2 The -f Option: Specifying the Output File Format	20
2.1.3 The -l Option: Generating a Listing File	20
2.1.4 The -M Option: Generate Makefile Dependencies	20
2.1.5 The -MG Option: Generate Makefile Dependencies.....	20
2.1.6 The -MF Option: Set Makefile Dependency File	20
2.1.7 The -MD Option: Assemble and Generate Dependencies.....	20
2.1.8 The -MT Option: Dependency Target Name.....	21
2.1.9 The -MQ Option: Dependency Target Name (Quoted)	21
2.1.10 The -MP Option: Emit phony targets.....	21
2.1.11 The -MW Option: Watcom Make quoting style.....	21
2.1.12 The -F Option: Selecting a Debug Information Format	21
2.1.13 The -g Option: Enabling Debug Information.....	21
2.1.14 The -X Option: Selecting an Error Reporting Format	21
2.1.15 The -Z Option: Send Errors to a File	22
2.1.16 The -s Option: Send Errors to stdout	22
2.1.17 The -i Option: Include File Search Directories.....	22
2.1.18 The -p Option: Pre-Include a File.....	22
2.1.19 The -d Option: Pre-Define a Macro.....	23
2.1.20 The -u Option: Undefine a Macro	23
2.1.21 The -E Option: Preprocess Only.....	23
2.1.22 The -a Option: Don't Preprocess At All.....	23
2.1.23 The -O Option: Specifying Multipass Optimization	23
2.1.24 The -t Option: Enable TASM Compatibility Mode.....	24
2.1.25 The -w and -W Options: Enable or Disable Assembly Warnings.	24
2.1.26 The -v Option: Display Version Info	25
2.1.27 The -y Option: Display Available Debug Info Formats	25
2.1.28 The --prefix and --postfix Options.....	26

2.1.29 The NASMENV Environment Variable	26
2.2 Quick Start for MASM Users.....	26
2.2.1 NASM Is Case-Sensitive.....	26
2.2.2 NASM Requires Square Brackets For Memory References.....	26
2.2.3 NASM Doesn't Store Variable Types	27
2.2.4 NASM Doesn't ASSUME.....	27
2.2.5 NASM Doesn't Support Memory Models.....	27
2.2.6 Floating-Point Differences.....	27
2.2.7 Other Differences	27
Chapter 3: The NASM Language.....	29
3.1 Layout of a NASM Source Line	29
3.2 Pseudo-Instructions.....	30
3.2.1 DB and Friends: Declaring Initialized Data.....	30
3.2.2 RESB and Friends: Declaring Uninitialized Data.....	30
3.2.3 INCBIN: Including External Binary Files.....	30
3.2.4 EQU: Defining Constants.....	31
3.2.5 TIMES: Repeating Instructions or Data	31
3.3 Effective Addresses.....	31
3.4 Constants	33
3.4.1 Numeric Constants	33
3.4.2 Character Strings	33
3.4.3 Character Constants.....	34
3.4.4 String Constants	34
3.4.5 Unicode Strings.....	35
3.4.6 Floating-Point Constants	35
3.4.7 Packed BCD Constants	36
3.5 Expressions.....	36
3.5.1 : Bitwise OR Operator.....	36
3.5.2 ^: Bitwise XOR Operator.....	37
3.5.3 &: Bitwise AND Operator.....	37
3.5.4 << and >>: Bit Shift Operators.....	37
3.5.5 + and -: Addition and Subtraction Operators.....	37
3.5.6 *, /, //, % and %: Multiplication and Division.....	37
3.5.7 Unary Operators.....	37
3.6 SEG and WRT.....	37
3.7 STRICT: Inhibiting Optimization.....	38

3.8 Critical Expressions	38
3.9 Local Labels	39
Chapter 4: The NASM Preprocessor.....	41
4.1 Single-Line Macros.....	41
4.1.1 The Normal Way: %define.....	41
4.1.2 Resolving %define: %xdefine.....	42
4.1.3 Macro Indirection: %[...]	43
4.1.4 Concatenating Single Line Macro Tokens: %+.....	43
4.1.5 The Macro Name Itself: %? and %??	43
4.1.6 Undefining Single-Line Macros: %undef	44
4.1.7 Preprocessor Variables: %assign.....	44
4.1.8 Defining Strings: %defstr	45
4.1.9 Defining Tokens: %deftok	45
4.2 String Manipulation in Macros	45
4.2.1 Concatenating Strings: %strcat.....	45
4.2.2 String Length: %strlen.....	45
4.2.3 Extracting Substrings: %substr.....	46
4.3 Multi-Line Macros: %macro	46
4.3.1 Overloading Multi-Line Macros	47
4.3.2 Macro-Local Labels.....	47
4.3.3 Greedy Macro Parameters.....	48
4.3.4 Macro Parameters Range.....	48
4.3.5 Default Macro Parameters	49
4.3.6 %0: Macro Parameter Counter.....	50
4.3.7 %00: Label Preceding Macro.....	50
4.3.8 %rotate: Rotating Macro Parameters.....	50
4.3.9 Concatenating Macro Parameters.....	51
4.3.10 Condition Codes as Macro Parameters	52
4.3.11 Disabling Listing Expansion	52
4.3.12 Undefining Multi-Line Macros: %unmacro.....	53
4.4 Conditional Assembly	53
4.4.1 %ifdef: Testing Single-Line Macro Existence.....	53
4.4.2 %ifmacro: Testing Multi-Line Macro Existence	54
4.4.3 %ifctx: Testing the Context Stack	54
4.4.4 %if: Testing Arbitrary Numeric Expressions.....	54
4.4.5 %ifidn and %ifidni: Testing Exact Text Identity.....	55

4.4.6	%ifid, %ifnum, %ifstr: Testing Token Types.....	55
4.4.7	%iftoken: Test for a Single Token	56
4.4.8	%ifempty: Test for Empty Expansion.....	56
4.4.9	%ifenv: Test If Environment Variable Exists.....	56
4.5	Preprocessor Loops: %rep	56
4.6	Source Files and Dependencies	57
4.6.1	%include: Including Other Files.....	57
4.6.2	%pathsearch: Search the Include Path	58
4.6.3	%depend: Add Dependent Files	58
4.6.4	%use: Include Standard Macro Package	58
4.7	The Context Stack	58
4.7.1	%push and %pop: Creating and Removing Contexts.....	59
4.7.2	Context-Local Labels	59
4.7.3	Context-Local Single-Line Macros	59
4.7.4	Context Fall-Through Lookup (<i>deprecated</i>)	60
4.7.5	%repl: Renaming a Context	60
4.7.6	Example Use of the Context Stack: Block IFs.....	61
4.8	Stack Relative Preprocessor Directives.....	62
4.8.1	%arg Directive.....	62
4.8.2	%stacksize Directive	63
4.8.3	%local Directive	63
4.9	Reporting User-Defined Errors: %error, %warning, %fatal.....	64
4.10	Other Preprocessor Directives.....	64
4.10.1	%line Directive	65
4.10.2	%! <i>variable</i> : Read an Environment Variable.	65
4.11	Standard Macros	65
4.11.1	NASM Version Macros	65
4.11.2	__NASM_VERSION_ID__: NASM Version ID	66
4.11.3	__NASM_VER__: NASM Version string.....	66
4.11.4	__FILE__ and __LINE__: File Name and Line Number	66
4.11.5	__BITS__: Current BITS Mode	66
4.11.6	__OUTPUT_FORMAT__: Current Output Format	66
4.11.7	Assembly Date and Time Macros.....	67
4.11.8	__USE_ <i>package</i> __: Package Include Test	67
4.11.9	__PASS__: Assembly Pass	67
4.11.10	STRUC and ENDSTRUC: Declaring Structure Data Types	68

4.11.11	ISTRUC, AT and IEND: Declaring Instances of Structures . . .	69
4.11.12	ALIGN and ALIGNB: Data Alignment	69
4.11.13	SECTALIGN: Section Alignment	70
Chapter 5:	Standard Macro Packages	71
5.1	altreg: Alternate Register Names	71
5.2	smartalign: Smart ALIGN Macro	71
5.3	fp: Floating-point macros	72
5.4	ifunc: Integer functions	72
5.4.1	Integer logarithms	72
Chapter 6:	Assembler Directives	73
6.1	BITS: Specifying Target Processor Mode	73
6.1.1	USE16 & USE32: Aliases for BITS	74
6.2	DEFAULT: Change the assembler defaults	74
6.2.1	REL & ABS: RIP-relative addressing	74
6.2.2	BND & NOBND: BND prefix	74
6.3	SECTION or SEGMENT: Changing and Defining Sections	74
6.3.1	The __SECT__ Macro	74
6.4	ABSOLUTE: Defining Absolute Labels	75
6.5	EXTERN: Importing Symbols from Other Modules	76
6.6	GLOBAL: Exporting Symbols to Other Modules	76
6.7	COMMON: Defining Common Data Areas	77
6.8	CPU: Defining CPU Dependencies	77
6.9	FLOAT: Handling of floating-point constants	78
6.10	[WARNING]: Enable or disable warnings	78
Chapter 7:	Output Formats	79
7.1	bin: Flat-Form Binary Output	79
7.1.1	ORG: Binary File Program Origin	79
7.1.2	bin Extensions to the SECTION Directive	79
7.1.3	Multisection Support for the bin Format	80
7.1.4	Map Files	80
7.2	ith: Intel Hex Output	80
7.3	srec: Motorola S-Records Output	80
7.4	obj: Microsoft OMF Object Files	81
7.4.1	obj Extensions to the SEGMENT Directive	81
7.4.2	GROUP: Defining Groups of Segments	82
7.4.3	UPPERCASE: Disabling Case Sensitivity in Output	83

7.4.4	IMPORT: Importing DLL Symbols	83
7.4.5	EXPORT: Exporting DLL Symbols	83
7.4.6	..start: Defining the Program Entry Point	84
7.4.7	obj Extensions to the EXTERN Directive.....	84
7.4.8	obj Extensions to the COMMON Directive.....	84
7.4.9	Embedded File Dependency Information	85
7.5	win32: Microsoft Win32 Object Files.....	85
7.5.1	win32 Extensions to the SECTION Directive	85
7.5.2	win32: Safe Structured Exception Handling	86
7.5.3	Debugging formats for Windows	87
7.6	win64: Microsoft Win64 Object Files.....	87
7.6.1	win64: Writing Position-Independent Code	87
7.6.2	win64: Structured Exception Handling	88
7.7	coff: Common Object File Format.....	91
7.8	macho32 and macho64: Mach Object File Format	91
7.8.1	macho extensions to the SECTION Directive	91
7.8.2	Thread Local Storage in Mach-O: macho special symbols and WRD	92
7.8.3	macho specific directive subsections_via_symbols.....	92
7.8.4	macho specific directive no_dead_strip	92
7.9	elf32, elf64, elfx32: Executable and Linkable Format Object File	92
7.9.1	ELF specific directive osabi	92
7.9.2	elf extensions to the SECTION Directive	93
7.9.3	Position-Independent Code: macho Special Symbols and WRT ..	93
7.9.4	Thread Local Storage in ELF: elf Special Symbols and WRT ..	94
7.9.5	elf Extensions to the GLOBAL Directive.....	94
7.9.6	elf Extensions to the COMMON Directive	95
7.9.7	16-bit code and ELF	95
7.9.8	Debug formats and ELF	95
7.10	aout: Linux a.out Object Files.....	95
7.11	aoutb: NetBSD/FreeBSD/OpenBSD a.out Object Files	95
7.12	as86: Minix/Linux as86 Object Files	96
7.13	rdf: Relocatable Dynamic Object File Format	96
7.13.1	Requiring a Library: The LIBRARY Directive.....	96
7.13.2	Specifying a Module Name: The MODULE Directive.....	96
7.13.3	rdf Extensions to the GLOBAL Directive.....	96
7.13.4	rdf Extensions to the EXTERN Directive.....	97

7.14 dbg: Debugging Format.....	97
Chapter 8: Writing 16-bit Code (DOS, Windows 3/3.1)	99
8.1 Producing .EXE Files	99
8.1.1 Using the obj Format To Generate .EXE Files.....	99
8.1.2 Using the bin Format To Generate .EXE Files.....	100
8.2 Producing .COM Files	101
8.2.1 Using the bin Format To Generate .COM Files.....	101
8.2.2 Using the obj Format To Generate .COM Files.....	101
8.3 Producing .SYS Files	102
8.4 Interfacing to 16-bit C Programs	102
8.4.1 External Symbol Names	102
8.4.2 Memory Models	103
8.4.3 Function Definitions and Function Calls.....	104
8.4.4 Accessing Data Items	106
8.4.5 c16.mac: Helper Macros for the 16-bit C Interface	106
8.5 Interfacing to Borland Pascal Programs.....	107
8.5.1 The Pascal Calling Convention	108
8.5.2 Borland Pascal Segment Name Restrictions	109
8.5.3 Using c16.mac With Pascal Programs.....	109
Chapter 9: Writing 32-bit Code (Unix, Win32, DJGPP)	111
9.1 Interfacing to 32-bit C Programs	111
9.1.1 External Symbol Names	111
9.1.2 Function Definitions and Function Calls.....	111
9.1.3 Accessing Data Items	113
9.1.4 c32.mac: Helper Macros for the 32-bit C Interface	113
9.2 Writing NetBSD/FreeBSD/OpenBSD and Linux/ELF Shared Libraries ..	114
9.2.1 Obtaining the Address of the GOT	114
9.2.2 Finding Your Local Data Items	115
9.2.3 Finding External and Common Data Items.....	115
9.2.4 Exporting Symbols to the Library User	116
9.2.5 Calling Procedures Outside the Library.....	117
9.2.6 Generating the Library File.....	117
Chapter 10: Mixing 16 and 32 Bit Code.....	119
10.1 Mixed-Size Jumps	119
10.2 Addressing Between Different-Size Segments.....	119
10.3 Other Mixed-Size Instructions.....	120

Chapter 11: Writing 64-bit Code (Unix, Win64)	123
11.1 Register Names in 64-bit Mode	123
11.2 Immediates and Displacements in 64-bit Mode	123
11.3 Interfacing to 64-bit C Programs (Unix)	124
11.4 Interfacing to 64-bit C Programs (Win64)	125
Chapter 12: Troubleshooting	127
12.1 Common Problems	127
12.1.1 NASM Generates Inefficient Code	127
12.1.2 My Jumps are Out of Range	127
12.1.3 ORG Doesn't Work	127
12.1.4 TIMES Doesn't Work	128
Appendix A: Ndisasm	129
A.1 Introduction	129
A.2 Running NDISASM	129
A.2.1 COM Files: Specifying an Origin	129
A.2.2 Code Following Data: Synchronisation	129
A.2.3 Mixed Code and Data: Automatic (Intelligent) Synchronisation	130
A.2.4 Other Options	130
Appendix B: Instruction List	133
B.1 Introduction	133
B.1.1 Special instructions	133
B.1.2 Conventional instructions	133
B.1.3 Katmai Streaming SIMD instructions (SSE -- a.k.a. KNI, XMM, MMX2)	160
B.1.4 Introduced in Deschutes but necessary for SSE support	161
B.1.5 XSAVE group (AVX and extended state)	161
B.1.6 Generic memory operations	162
B.1.7 New MMX instructions introduced in Katmai	162
B.1.8 AMD Enhanced 3DNow! (Athlon) instructions	162
B.1.9 Willamette SSE2 Cacheability Instructions	162
B.1.10 Willamette MMX instructions (SSE2 SIMD Integer Instructions)	162
B.1.11 Willamette Streaming SIMD instructions (SSE2)	164
B.1.12 Prescott New Instructions (SSE3)	166
B.1.13 VMX/SVM Instructions	166
B.1.14 Extended Page Tables VMX instructions	167
B.1.15 Tejas New Instructions (SSSE3)	167
B.1.16 AMD SSE4A	167

B.1.17	New instructions in Barcelona.....	167
B.1.18	Penryn New Instructions (SSE4.1)	168
B.1.19	Nehalem New Instructions (SSE4.2).....	169
B.1.20	Intel SMX.....	169
B.1.21	Geode (Cyrix) 3DNow! additions.....	169
B.1.22	Intel new instructions in ???.....	169
B.1.23	Intel AES instructions.....	169
B.1.24	Intel AVX AES instructions.....	169
B.1.25	Intel instruction extension based on pub number 319433-0301760 dated October 1, 2009.....	169
B.1.26	Intel AVX instructions.....	170
B.1.27	Intel Carry-Less Multiplication instructions (CLMUL)	183
B.1.28	Intel AVX Carry-Less Multiplication instructions (CLMUL) .	183
B.1.29	Intel Fused Multiply-Add instructions (FMA)	183
B.1.30	Intel post-32 nm processor instructions	187
B.1.31	VIA (Centaur) security instructions	187
B.1.32	AMD Lightweight Profiling (LWP) instructions	188
B.1.33	AMD XOP and FMA4 instructions (SSE5)	188
B.1.34	Intel AVX2 instructions	190
B.1.35	Intel Transactional Synchronization Extensions (TSX)	194
B.1.36	Intel BMI1 and BMI2 instructions, AMD TBM instructions...	194
B.1.37	Intel Memory Protection Extensions (MPX)	195
B.1.38	Intel SHA acceleration instructions	196
B.1.39	AVX-512 mask register instructions.....	196
B.1.40	AVX-512 instructions	197
B.1.41	Intel memory protection keys for userspace (PKU aka PKEYs)	225
B.1.42	Read Processor ID.....	225
B.1.43	New memory instructions	225
B.1.44	Systematic names for the hinting nop instructions.....	225
Appendix C: NASM Version History.....		231
C.1	NASM 2 Series	231
C.1.1	Version 2.13.03.....	231
C.1.2	Version 2.13.02.....	231
C.1.3	Version 2.13.01.....	231
C.1.4	Version 2.13	231
C.1.5	Version 2.12.02.....	233
C.1.6	Version 2.12.01.....	233

C.1.7 Version 2.12	233
C.1.8 Version 2.11.09	233
C.1.9 Version 2.11.08	234
C.1.10 Version 2.11.07	234
C.1.11 Version 2.11.06	234
C.1.12 Version 2.11.05	234
C.1.13 Version 2.11.04	234
C.1.14 Version 2.11.03	234
C.1.15 Version 2.11.02	234
C.1.16 Version 2.11.01	235
C.1.17 Version 2.11	235
C.1.18 Version 2.10.09	236
C.1.19 Version 2.10.08	236
C.1.20 Version 2.10.07	236
C.1.21 Version 2.10.06	236
C.1.22 Version 2.10.05	236
C.1.23 Version 2.10.04	236
C.1.24 Version 2.10.03	237
C.1.25 Version 2.10.02	237
C.1.26 Version 2.10.01	237
C.1.27 Version 2.10	237
C.1.28 Version 2.09.10	237
C.1.29 Version 2.09.09	237
C.1.30 Version 2.09.08	237
C.1.31 Version 2.09.07	237
C.1.32 Version 2.09.06	238
C.1.33 Version 2.09.05	238
C.1.34 Version 2.09.04	238
C.1.35 Version 2.09.03	238
C.1.36 Version 2.09.02	238
C.1.37 Version 2.09.01	238
C.1.38 Version 2.09	238
C.1.39 Version 2.08.02	239
C.1.40 Version 2.08.01	239
C.1.41 Version 2.08	239
C.1.42 Version 2.07	240

C.1.43	Version 2.06	240
C.1.44	Version 2.05.01	241
C.1.45	Version 2.05	241
C.1.46	Version 2.04	241
C.1.47	Version 2.03.01	242
C.1.48	Version 2.03	242
C.1.49	Version 2.02	243
C.1.50	Version 2.01	243
C.1.51	Version 2.00	244
C.2	NASM 0.98 Series	244
C.2.1	Version 0.98.39	245
C.2.2	Version 0.98.38	245
C.2.3	Version 0.98.37	245
C.2.4	Version 0.98.36	245
C.2.5	Version 0.98.35	246
C.2.6	Version 0.98.34	246
C.2.7	Version 0.98.33	246
C.2.8	Version 0.98.32	246
C.2.9	Version 0.98.31	247
C.2.10	Version 0.98.30	247
C.2.11	Version 0.98.28	247
C.2.12	Version 0.98.26	247
C.2.13	Version 0.98.25alt	247
C.2.14	Version 0.98.25	247
C.2.15	Version 0.98.24p1	248
C.2.16	Version 0.98.24	248
C.2.17	Version 0.98.23	248
C.2.18	Version 0.98.22	248
C.2.19	Version 0.98.21	248
C.2.20	Version 0.98.20	248
C.2.21	Version 0.98.19	248
C.2.22	Version 0.98.18	248
C.2.23	Version 0.98.17	248
C.2.24	Version 0.98.16	248
C.2.25	Version 0.98.15	248
C.2.26	Version 0.98.14	248

C.2.27	Version 0.98.13	248
C.2.28	Version 0.98.12	248
C.2.29	Version 0.98.11	248
C.2.30	Version 0.98.10	249
C.2.31	Version 0.98.09	249
C.2.32	Version 0.98.08	249
C.2.33	Version 0.98.09b with John Coffman patches released 28-Oct-2001	249
C.2.34	Version 0.98.07 released 01/28/01.....	250
C.2.35	Version 0.98.06f released 01/18/01.....	250
C.2.36	Version 0.98.06e released 01/09/01.....	250
C.2.37	Version 0.98p1.....	250
C.2.38	Version 0.98bf (bug-fixed).....	250
C.2.39	Version 0.98.03 with John Coffman's changes released 27-Jul-2000	250
C.2.40	Version 0.98.03	251
C.2.41	Version 0.98	254
C.2.42	Version 0.98p9.....	254
C.2.43	Version 0.98p8.....	254
C.2.44	Version 0.98p7.....	255
C.2.45	Version 0.98p6.....	255
C.2.46	Version 0.98p3.7	255
C.2.47	Version 0.98p3.6	255
C.2.48	Version 0.98p3.5	255
C.2.49	Version 0.98p3.4	256
C.2.50	Version 0.98p3.3	256
C.2.51	Version 0.98p3.2	256
C.2.52	Version 0.98p3-hpa.....	257
C.2.53	Version 0.98 pre-release 3.....	257
C.2.54	Version 0.98 pre-release 2.....	257
C.2.55	Version 0.98 pre-release 1.....	257
C.3	NASM 0.9 Series.....	258
C.3.1	Version 0.97 released December 1997.....	258
C.3.2	Version 0.96 released November 1997.....	259
C.3.3	Version 0.95 released July 1997.....	261
C.3.4	Version 0.94 released April 1997	262
C.3.5	Version 0.93 released January 1997.....	263
C.3.6	Version 0.92 released January 1997.....	263

C.3.7 Version 0.91 released November 1996.....	263
C.3.8 Version 0.90 released October 1996.....	264
Appendix D: Building NASM from Source.....	265
D.1 Building from a Source Archive.....	265
D.2 Building from the git Repository	265
Appendix E: Contact Information	267
E.1 Website.....	267
E.1.1 User Forums.....	267
E.1.2 Development Community	267
E.2 Reporting Bugs.....	267

Chapter 1: Introduction

1.1 What Is NASM?

The Netwide Assembler, NASM, is an 80x86 and x86-64 assembler designed for portability and modularity. It supports a range of object file formats, including Linux and BSD a.out, ELF, COFF, Mach-O, 16-bit and 32-bit OBJOMF format, Win32 and Win64. It will also output plain binary files, Intel hex, and Motorola S-Record formats. Its syntax is designed to be simple and easy to understand, similar to the syntax in the *Intel Software Developer's Manual*, with minimal complexity. It supports all currently known x86 architectural extensions, and has strong support for macros.

NASM also comes with a set of utilities for handling the RDOFF custom object-file format.

1.1.1 License Conditions

Please see the file `LICENSE`, supplied as part of any NASM distribution archive, for the license conditions under which you may use NASM. NASM is now under the so-called 2-clause BSD license, also known as the simplified BSD license.

Copyright 1996–2017 the NASM Authors – All rights reserved.

Redistribution and use in source and binary forms, with or without modification, are permitted provided that the following conditions are met:

- Redistribution of source code must retain the above copyright notice, this list of conditions, and the following disclaimer.
- Redistribution in binary form must reproduce the above copyright notice, this list of conditions, and the following disclaimer in the documentation and/or other materials provided with the distribution.

THIS SOFTWARE IS PROVIDED BY THE COPYRIGHT HOLDERS AND CONTRIBUTORS "AS IS" AND ANY EXPRESS OR IMPLIED WARRANTIES, INCLUDING, BUT NOT LIMITED TO, THE IMPLIED WARRANTIES OF MERCHANTABILITY AND FITNESS FOR A PARTICULAR PURPOSE ARE DISCLAIMED. IN NO EVENT SHALL THE COPYRIGHT OWNER OR CONTRIBUTORS BE LIABLE FOR ANY DIRECT, INDIRECT, INCIDENTAL, SPECIAL, EXEMPLARY, OR CONSEQUENTIAL DAMAGES (INCLUDING, BUT NOT LIMITED TO, PROCUREMENT OF SUBSTITUTE GOODS OR SERVICES; LOSS OF USE, DATA, OR PROFITS; OR BUSINESS INTERRUPTION) HOWEVER CAUSED AND ON ANY THEORY OF LIABILITY, WHETHER IN CONTRACT, STRICT LIABILITY, OR TORT (INCLUDING NEGLIGENCE OR OTHERWISE) ARISING IN ANY WAY OUT OF THE USE OF THIS SOFTWARE, EVEN IF ADVISED OF THE POSSIBILITY OF SUCH DAMAGE.

Chapter 2: Running NASM

2.1 NASM Command-Line Syntax

To assemble a file, you issue a command of the form

```
nasm -f <format> <filename> [-o <output>]
```

For example,

```
nasm -f elf myfile.asm
```

will assemble myfile.asm into an ELF object file myfile.o. And

```
nasm -f bin myfile.asm -o myfile.com
```

will assemble myfile.asm into a raw binary file myfile.com.

To produce a listing file, with the hex codes output from NASM displayed on the left of the original sources, use the -l option to give a listing file name, for example:

```
nasm -f coff myfile.asm -l myfile.lst
```

To get further usage instructions from NASM, try typing

```
nasm -h
```

As -hf, this will also list the available output file formats, and what they are.

If you use Linux but aren't sure whether your system is a.out or ELF, type

```
file nasm
```

(in the directory in which you put the NASM binary when you installed it). If it says

```
nasm: ELF 32-bit LSB executable i386 (386 and up) Version 1
```

then your system is ELF, and you should use the option -f elf when you want NASM to produce Linux object files. If it says

```
nasm: Linux/i386 demand-paged executable (QMAGIC)
```

or something similar, your system is a.out, and you should use -f aout instead (Linux a.out systems have long been obsolete, and are rare these days.)

Like Unix compilers and assemblers, NASM is silent unless it goes wrong or you won't see any output at all, unless it gives error messages.

2.1.1 The -o Option: Specifying the Output File Name

NASM will normally choose the name of your output file for you precisely how it does this is dependent on the object file format. For Microsoft object file formats (obj, win32 and win64) it will remove the .asm extension (or whatever extension you like to use NASM doesn't care) from your source file name and substitute obj. For Unix object file formats (a.out, as86, coff, elf32, elf64, elfx32, ieee, macho32 and macho64) it will substitute .o. For dbg, rdf, it handles rec, it will use .dbg, .rdf, .it and srec, respectively, and for the info format it will simply remove the extension, so that myfile.asm produces the output file myfile.

If the output file already exists NASM will overwrite it, unless it has the same name as the input file in which case it will give a warning and use nasm.out as the output file name instead.

For situations in which this behaviour is unacceptable, NASM provides the command-line option, which allows you to specify your desired output file name. You invoke it by following it with the name you wish for the output file, either with or without an intervening space. For example:

```
nasm -f bin program.asm -o program.com
nasm -f bin driver.asm -o driver.sys
```

Note that this is `small`, and is different from `capitalQ`, which is used to specify the number of optimisation passes required. See section 2.1.23.

2.1.2 The `-f` Option: Specifying the Output File Format

If you do not supply the `-f` option to NASM, it will choose an output file format for you itself. In the distribution versions of NASM, the default is always `bin`; if you've compiled your own copy of NASM, you can redefine `OF_DEFAULT` at compile time and choose what you want the default to be.

Like `-o`, the intervening space between `-f` and the output file format is optional; so `-f elf` and `-felf` are both valid.

A complete list of the available output file formats can be given by issuing the command:

2.1.3 The `-l` Option: Generating a Listing File

If you supply the `-l` option to NASM, followed (with the usual optional space) by a filename, NASM will generate a source-listing file for you, which addresses and generated code are listed on the left and the actual source code with expansions of multi-line macros (except those which specifically request no expansion in source listings: see section 4.3.11) on the right. For example:

```
nasm -f elf myfile.asm -l myfile.lst
```

If a listing file is selected, you may turn off listing for a section of your source with `[list-]` and turn it back on with `[list+]`, (the default, obviously) There is a `#` use form (without the brackets) This can be used to list only sections of interest, avoiding excessively long listings.

2.1.4 The `-M` Option: Generate Makefile Dependencies

This option causes NASM to generate makefile dependencies and send them to stdout. This can be redirected to a file for further processing. For example:

```
nasm -M myfile.asm > myfile.dep
```

2.1.5 The `-MG` Option: Generate Makefile Dependencies

This option causes NASM to generate makefile dependencies and send them to stdout. This differs from the `-M` option in that if a non-existing file is encountered, it is assumed to be a generated file and is added to the dependency list without a prefix.

2.1.6 The `-MF` Option: Set Makefile Dependency File

This option can be used with the `-M` or `-MG` options to send the output to a file, rather than to stdout. For example:

```
nasm -M -MF myfile.dep myfile.asm
```

2.1.7 The `-MD` Option: Assemble and Generate Dependencies

The `-MD` option acts as the combination of the `-M` and `-MG` options (i.e. a filename has to be specified.) However, unlike the `-M` or `-MG` options, `-MD` does *not* inhibit the normal operation of the assembler. Use this to automatically generate updated dependencies with every assembly session.

```
nasm -f elf -o myfile.o -MD myfile.dep myfile.asm
```

2.1.8 The -MT Option: Dependency Target Name

The `-MT` option can be used to override the default name of the dependency target. This is normally the same as the output filename, specified by the `-o` option.

2.1.9 The -MQ Option: Dependency Target Name (Quoted)

The `-MQ` option acts as the `-MT` option, except it tries to quote characters that have special meaning in Makefile syntax. This is so foolproof that a single character with special meaning is quotable in Make. The default output (if no `-MT` or `-MQ` option is specified) is automatically quoted.

2.1.10 The -MP Option: Emit phony targets

When used with any of the dependency generation options, the `-MP` option causes NASM to emit a phony target without dependencies for each header file. This prevents Make from complaining if a header file has been removed.

2.1.11 The -MW Option: Watcom Make quoting style

This option causes NASM to attempt to quote dependencies according to Watcom Make conventions rather than POSIX Make conventions (also used by most other Make variants.) This quotes `#a$#` rather than `#,use$` rather than for continuation lines, and encloses filenames containing whitespace in double quotes.

2.1.12 The -F Option: Selecting a Debug Information Format

This option is used to select the format of the debug information emitted into the output file, based by debugger (*or will be*). Prior to version 2.03.01, this switch did *not* enable output of the selected debug info format. Use `g` (see section 2.1.13) to enable output. Version 2.03.0 and later automatically enable `-g` if `-F` is specified.

A complete list of the available debug file formats for an output format can be seen by issuing the command `asm -f <format> -y`. Not all output formats currently support debugging output. See section 2.1.27.

This should not be confused with the `-f dbg` output format option, see section 7.14.

2.1.13 The -g Option: Enabling Debug Information.

This option enables generation of debugging information in the specified format (see section 2.1.12). Using `g` without `-F` results in emitting debug info in the default format, if any, for the selected output format. If debug information is currently implemented in the selected output format, `-g` *silently ignored*.

2.1.14 The -X Option: Selecting an Error Reporting Format

This option can be used to select an error reporting format for any error messages that might be produced by NASM.

Currently, two error reporting formats may be selected. They are the `-Xv` option and the `-Xgnu` option. The GNU format is the default and looks like this:

```
filename.asm:65: error: specific error message
```

where `filename.asm` is the name of the source file in which the error was detected, `65` is the source file line number on which the error was detected, `error` is the severity of the error (this could be warning), and `specific error message` is a more detailed text message which should help pinpoint the exact problem.

The other format, specified by `-Xv`, is the style used by Microsoft Visual C++ and some other programs. It looks like this:

filename.asm(65) : error: specific error message

where the only difference is that the line number is in parentheses instead of being

See also the Visual C++ output format, section 7.5.

2.1.15 The **-Z** Option: Send Errors to a File

Under MS-DOS it can be difficult (though there are ways) to redirect the standard-error output of a program to a file. Since NASM usually produces its warning and error messages on stderr, this can make it hard to capture the errors if (for example) you want to load them into an editor.

NASM therefore provides the **-Z** option, taking a filename argument which causes errors to be sent to the specified files rather than standard error. Therefore you can redirect the error

```
nasm -Z myfile.err -f obj myfile.asm
```

In earlier versions of NASM, this option was called **-E**, but it was changed since **-E** is an option conventionally used for preprocessing only, with disastrous results. See section 2.1.

2.1.16 The **-s** Option: Send Errors to stdout

The option to redirect error messages to stdout rather than stderr, so it can be redirected under MS-DOS. To assemble the file myfile.asm and pipe its output to the more program, you

```
nasm -s -f obj myfile.asm | more
```

See also the **-Z** option, section 2.1.15.

2.1.17 The **-i** Option: Include File Search Directories

When NASM sees the **%include** path search directive in a source file (see section 4.6.1, section 4.6.2, section 3.2.3), it will search for the given file not only in the current directory but also in any directories specified on the command line by use of the option. Therefore you can include files from a macro library, for example, by typing

```
nasm -ic:\macrolib\ -f obj myfile.asm
```

(As usual, a space between **-i** and the path name is allowed, and optional).

NASM, in its interest for complete source-code portability, does not understand the file naming conventions of the OS it is running on; the string you provide as an argument to the option will be prepended exactly as written to the name of the include file. Therefore the trailing backslash in the above example is necessary. Under Unix, a trailing forward slash is similarly necessary.

(You can use this to your advantage, if you're really perverse, by noting that the option **-i** will cause **%include "bar.i"** to search for the file foobar.i....)

If you want to define a standard include search path, similar to **/usr/include** on Unix systems, you should place one or more **-i** directives in the **NASMENV** environment variable (see section 2.1).

For Makefile compatibility with many C compilers, this option can also be specified as

2.1.18 The **-p** Option: Pre-Include a File

NASM allows you to specify files to be *pre-included* into your source file by use of the option. So running

```
nasm myfile.asm -p myinc.inc
```

is equivalent to running `nasm myfile.asm` and placing the directive `%include "myinc.inc"` at the start of the file.

For consistency with the **-I**, **-D** and **-U** options, this option can also be specified as

2.1.19 The -d Option: Pre-Define a Macro

Just as the option gives an alternative to placing an include directive at the start of a source file, the -d option gives an alternative to placing a %define directive. You could code

```
nasm myfile.asm -dFOO=100
```

as an alternative to placing the directive

```
%define FOO 100
```

at the start of the file. You can miss off the macro value, as well the option -dFOO, equivalent to coding %define FOO. This form of the directive may be useful for selecting assembly-time options which are then tested using %ifdef, for example -dDEBUG.

For Makefile compatibility with many C compilers, this option can also be specified as

2.1.20 The -u Option: Undefine a Macro

The option undefines a macro that would otherwise have been pre-defined, either automatically or by a -p or -d option specified earlier on the command lines.

For example, the following command line:

```
nasm myfile.asm -dFOO=100 -uFOO
```

would result in FOO not being a predefined macro in the program. This is useful to override options specified at a different point in a Makefile.

For Makefile compatibility with many C compilers, this option can also be specified as

2.1.21 The -E Option: Preprocess Only

NASM allows the preprocessor to be run on its own, up to a point. Using the -E option (which requires no arguments) will cause NASM to preprocess its input file, expand all the macro references, remove all the comment and preprocessor directives, and print the resulting file to standard output (or save it to a file, if the -o option is also used).

This option cannot be applied to programs which require the preprocessor to evaluate expressions which depend on the values of symbols: so code such as

```
%assign tablesize ($-tablestart)
```

will cause an error in preprocess-only mode.

For compatibility with older versions of NASM, this option can also be written as -E. Older versions of NASM was the equivalent of the current -Z option, section 2.1.15.

2.1.22 The -a Option: Don't Preprocess At All

If NASM is being used as the backend compiler, it might be desirable to suppress preprocessing completely and assume the compiler has already done it, to save time and increase compilation speeds. The option, requiring no argument, instructs NASM to replace the powerful preprocessor with a stub preprocessor which does nothing.

2.1.23 The -O Option: Specifying Multipass Optimization

Using the -O option, you can tell NASM to carry out different levels of optimization

- -O0 No optimization. All operands take the full long form, if short form is not specified, except conditional jumps. This is intended to match NASM 0.98 behavior.
- -O1 Minimal optimization. Above, but immediate operands which will fit in a signed byte are optimized, unless the long form is specified. Conditional jumps default to the long form unless otherwise specified.

- `-Ox` (where `x` is the actual letter) Multipass optimization Minimize branch offset and signed immediate bytes, overriding size specification unless the `strict` keyword has been used (see section 3.7) For compatibility with earlier releases, the letter `x` may also be any number greater than one. This number has no effect on the actual number of passes.

The `-Ox` mode is recommended for most uses, and is the default since NASM 2.09.

Note that this is `s`capital `O`, and is different from `m`small `b`, which is used to specify the output file name. See section 2.1.1.

2.1.24 The `-t` Option: Enable TASM Compatibility Mode

NASM includes limited form of compatibility with Borland's TASM when NASM's `-t` option is used, the following changes are made:

- local labels may be prefixed with `@@` instead of `.`
- `size` override supported with `hi` brackets. In TASM compatibility mode, `size` override inside square brackets changes the size of the operand, and not the address type of the operand as it does in NASM syntax. E.g. `moveax, [DWORDval]` is valid syntax in TASM compatibility mode. Note that you lose the ability to override the default address type for the instruction.
- unprefixed forms of some directives supported (`arg`, `elif`, `else`, `endif`, `if`, `ifdef`, `ifdif`, `ifndef`, `include`, `local`)

2.1.25 The `-w` and `-W` Options: Enable or Disable Assembly Warnings

NASM can observe many conditions during the course of assembly which are worth mentioning to the user, but not sufficiently severe to justify NASM refusing to generate an output file. These conditions are reported like errors but come up with the word `warning` before the message. Warnings do not prevent NASM from generating an output file and returning success status to the operating system.

Some conditions are even less severe than that they are only sometimes worth mentioning to the user. Therefore NASM supports the command-line option which enables or disables certain classes of assembly warning. Such warning classes are described by name, for example `orphan-labels`, you can enable warnings of this class by the command-line option `-w+orphan-labels` and disable by `-w-orphan-labels`.

The current warning classes are:

- `other` specifies any warning not otherwise specified in any class. Enabled by default.
- `macro-params` covers warnings about multi-line macro being invoked with the wrong number of parameters. Enabled by default; see section 4.3.1 for an example of why you might want to disable it.
- `macro-selfref` warns if a macro references itself. Disabled by default.
- `macro-default` warns when a macro has no default parameter than optional parameters. Enabled by default; see section 4.3.5 for why you might want to disable it.
- `orphan-labels` covers warnings about source lines which contain an instruction but define a label without a trailing colon. NASM warns about this somewhat obscure condition by default; see section 3.1 for more information.
- `number-overflow` covers warning about numeric constant which don't fit in 64 bits. Enabled by default.
- `gnu-elf-extensions` warns if 8-bit or 16-bit relocations are used in `elf` format. The GNU extensions allow this. Disabled by default.
- `float-overflow` warns about floating point overflow. Enabled by default.

- float-denorm warns about floating point denormals. Disabled by default.
- float-underflow warns about floating point underflow. Disabled by default.
- float-toolong warns about too many digits in floating-point numbers. Enabled by default.
- user controls %warning directives (see section 4.9). Enabled by default.
- lock warns about LOCK prefixes on unlockable instructions. Enabled by default.
- hle warns about invalid use of the HLE XACQUIRE or XRELEASE prefixes. Enabled by default.
- bnd warns about ineffective use of the BND prefix when a relaxed form of jmp instruction becomes jmp short form. Enabled by default.
- zext-reloc warns that a relocation has been zero-extended due to limitations in the output format. Enabled by default.
- pt warns about keywords used in the assembler that might indicate a mistake in the source code. Currently only the MASM PTR keyword is recognized. Enabled by default.
- bad-pragm warns about a malformed or otherwise unparseable pragma directive. Disabled by default.
- unknown-pragm warns about an unknown %pragma directive. This is not yet implemented. Disabled by default.
- not-my-pragm warns about a %pragma directive which is not applicable to this particular assembly session. This is not yet implemented. Disabled by default.
- unknown-warning warns about a -w or -W option or a [WARNING] directive that contains an unknown warning name or is otherwise not possible to process. Disabled by default.
- alias alias for -all suppressible warning classes. Thus, -w+all enables all available warnings, and -w-all disables warnings entirely (since NASM 2.13).

Since version 2.00, NASM has also supported the gcc-like syntax -Wwarning-class and -Wno-warning-class instead of -w+warning-class and -w-warning-class, respectively; both syntaxes work identically.

The option -w+error or -Werror can be used to treat warnings as errors. This can be controlled on a per-warning class basis (-w+error=warning-class or -Werror=warning-class); if warning-class is specified NASM treats it as -w+error=all; the same applies to -w-error or -Wno-error, of course.

In addition you can control warnings in the source code itself using the %WARNING directive. See section 6.10.

2.1.26 The -v Option: Display Version Info

Typing `NASM-w` will display the version of NASM which you are using, and the date on which it was compiled.

You will need the version number if you report a bug.

For command-line compatibility with Yasm, the form `-v` is also accepted for this option starting in NASM version 2.11.05.

2.1.27 The -y Option: Display Available Debug Info Formats

Typing `nasm -f <option>` will display a list of the available debug info formats for the given output format. The default format is indicated by an asterisk. For example:

```
nasm -f elf -y
```

valid debug formats for 'elf32' output format are
 ('*' denotes default):

* stabs	ELF32 (i386) stabs debug format for Linux
dwarf	elf32 (i386) dwarf debug format for Linux

2.1.28 The --prefix and --postfix Options.

The `--prefix` and `--postfix` options prepend or append (respectively) the given argument to all global or extern variables. E.g., `--prefix_` will prepend the underscore to all global and external variables, as C requires it in some, but not all, system calling convention.

2.1.29 The NASMENV Environment Variable

If you define an environment variable called `NASMENV`, the program will interpret it as a list of extra command-line options which are processed before the real command line. You can use this to define standard search directories for include files, by putting `-i` options in the `NASMENV`.

The value of the variable is split up at whitespace, so that the value `-s -ic:\nasmlib\` will be treated as two separate options. However, that means that the value `-dNAME="my name"` won't do what you might want, because it will be split at the space and the NASM command-line processing will get confused by the two nonsensical words `-dNAME="my and name"`.

To get around this, NASM provides a feature whereby, if you begin the `NASMENV` environment variable with some character that isn't a minus sign, then NASM will treat this character as the separator character for options. So setting the `NASMENV` variable to the value `!-s -ic:\nasmlib\` is equivalent to setting it to `-s -ic:\nasmlib\`, but `!-dNAME="my name"` will work.

This environment variable was previously called `NASM`. This was changed with version

2.2 Quick Start for MASM Users

If you're used to writing programs with MASM, or with TASM, MASM-compatible (non-Ideal) mode, or with 86, this section attempts to outline the major differences between MASM's syntax and NASM's. If you're not already used to MASM, it's probably worth skipping this section.

2.2.1 NASM Is Case-Sensitive

One simple difference is that NASM is case-sensitive. It makes a difference whether you call a label `foo`, `Foo` or `FOO`. If you're reassembling to DOS or OS/2 OBJ files, you can invoke the `UPPERCASE` directive (documented in section 7.4) to ensure that all symbols exported to other modules are forced to uppercase, but even then, within a single module, NASM will distinguish between labels differing only in case.

2.2.2 NASM Requires Square Brackets For Memory References

NASM was designed with simplicity of syntax in mind. One of the design goals of NASM is that it should be possible, as far as is practical, for the user to look at a single line of NASM code and tell what opcodes are generated by it. You can't do this in MASM: if you declare, for example,

```
foo    equ    1
bar    dw     2
```

then the two lines of code

```
mov     ax, foo
mov     ax, bar
```

generate completely different opcodes, despite having identical-looking syntaxes.

NASM avoids this undesirable situation by having much simpler syntax for memory references. The rule is simply that any access to the contents of a memory location requires square brackets around the

address, and any access to the *address* of a variable doesn't. So an instruction of the form `mov ax, foo` will *always* refer to a compile-time constant, whether it's an EQU or the address of a variable; and to access the *contents* of the variable `bar`, you must code `mov ax, [bar]`.

This also means that NASM has no need for MASM's OFFSET keyword, since the MASM code `mov ax, offset bar` means exactly the same thing as NASM's `mov ax, bar`. If you're retrying to get large amounts of MASM code to assemble sensibly under NASM, you can always code `%define offset` to make the preprocessor treat the OFFSET keyword as a no-op.

This issue is even more confusing in x86, where declaring a label with a trailing colon defines it as a 'label' as opposed to a 'variable' and causes x86 to adopt NASM-style semantics; so in x86, `mov ax, var` has different behaviour depending on whether `var` was declared as `var dw 0` (a label) or `var dw 0` (a word-size variable). NASM is very simple by comparison: *everything*

NASM, with the interest of simplicity, also does not support the hybrid syntaxes supported by MASM and its clones, such as `mov ax, table[bx]`, where a memory reference is denoted by one portion outside square brackets and another portion inside. The correct syntax for the above is `mov ax, [table+bx]`. Likewise, `mov ax, es:[di]` is wrong and `mov ax, [es:di]` is right.

2.2.3 NASM Doesn't Store Variable Types

NASM, by design, chooses not to remember the types of variables you declare. Whereas MASM will remember, or see in `var dw 0`, that you declared `var` as a word-size variable, and will then be able to fill in the ambiguity in the size of the instruction `mov ax, var`, NASM will deliberately remember nothing about the symbol `var` except where it begins, and so you must explicitly code `mov word [var], 2`.

For this reason, NASM doesn't support the LODS, MOVS, STOS, SCAS, CMPS, INS, or OUTS instructions, but only supports the forms such as `LODSB`, `MOVSW`, and `CASD`, which explicitly specify the size of the components of the strings being manipulated.

2.2.4 NASM Doesn't ASSUME

As part of NASM's drive for simplicity, it also does not support the ASSUME directive. NASM will not keep track of what values you choose to put in your segment registers, and will never *automatically* generate a segment override prefix.

2.2.5 NASM Doesn't Support Memory Models

NASM does not have any directives to support different 16-bit memory models. The programmer has to keep track of which functions are supposed to be called with `far call` and which with `near call`, and is responsible for putting the correct form of RET instruction (RET or RETF). NASM accepts RET itself as an alternate form for RETN; in addition, the programmer is responsible for coding CLEARE instructions where necessary when calling *external* functions, and must also keep track of which external variable definitions are far and which are near.

2.2.6 Floating-Point Differences

NASM uses different names to refer to floating-point registers from MASM, where MASM would call them ST(0), ST(1) and so on, and x86 would call them simply 0, 1 and so on; NASM chooses to call them `st0`, `st1` etc.

As of version 0.96, NASM now treats the instructions with 'nowait' forms in the same way as MASM-compatible assemblers. The idiosyncratic treatment employed by 0.95 and earlier was based on a misunderstanding by the authors.

2.2.7 Other Differences

For historical reasons, NASM uses the keyword `TWORD` where MASM and compatible assemblers use `TBYTE`.

NASM does not declare uninitialized storage in the same way as MASM: where a MASM programmer might use `stack db 64 dup (?)`, NASM requires `stack resb 64`, intended to be read as 'reserve 64 bytes'. For a limited amount of compatibility, since NASM treats a valid character in symbol names, you can code `?equ 0` and then writing `dw ?` will at least do something vaguely useful. DUP is still not a supported syntax, however.

In addition, `lbf` macro and directives work completely differently. NASM See chapter 4 and chapter 6 for further details.

Chapter 3: The NASM Language

3.1 Layout of a NASM Source Line

Like most assemblers, each NASM source line contains (unless it is a macro preprocessor directive or an assembler directive: see chapter 4 and chapter 6) some combination of the four fields:

```
label:      instruction operands      ; comment
```

As usual, most of these fields are optional; the presence or absence of any combination of a label, an instruction, and a comment is allowed. Of course, the operand field is either required or forbidden by the presence and nature of the instruction field.

NASM uses backslash (\) as the line continuation character; a line ends with backslash; the next line is considered to be a part of the backslash-ended line.

NASM places no restrictions on whitespace within a line; labels may have whitespace before them; instructions may have space before them; anything that follows a colon after a label is also optional. (Note that this means that if you intend to code a label on a line, and type it by accident, then that's still a valid source line which does nothing but define a label. Running NASM with the command-line option `-w orphan-labels` will cause it to warn you if you define a label alone on a line without a trailing colon.)

Valid characters in labels are letters, numbers, `_`, `$`, `#`, `@`, `~`, `.`, and `?`. The only characters which may be used as the first character in identifiers are letters, `_` (with special meanings in section 3.9) and `?`. An identifier may also be prefixed with `__` to indicate that it is intended to be read as an identifier and not a reserved word; thus, if some other module you are linking with defines a symbol called `eax`, you can refer to `__eax` in NASM code to distinguish the symbol from the register. Maximum length of an identifier is 4095 characters.

The instruction field may contain any machine instruction. Pentium and P6 instructions, FPU instructions, MMX instructions, and even documented instructions not supported by the instruction may be prefixed by `LOCK`, `REP`, `REPE/REPZ`, `REPNE/REPNZ`, `XACQUIRE/XRELEASE` or `BND/NOBND`, in the usual way. Explicit address-size and operand-size prefixes `A16`, `A32`, `A64`, `O16`, and `O32`, `O64` are provided; one example of their use is given in chapter 10. You can also use the name of a segment register as an instruction prefix: coding `es mov [bx], ax` is equivalent to coding `mov[es:bx], ax`. We recommend the latter syntax, since it is consistent with other syntactic features of the language, but for instructions such as `LODSB`, which has no operands and yet can require a segment override, there is no clean syntactic way to proceed apart from `es`.

An instruction is not required to use a prefix; prefixes such as `CS`, `A32`, `LOCK`, `REPE` can appear on a line by themselves, and NASM will just generate the prefix bytes.

In addition to actual machine instructions, NASM also supports a number of pseudo-instructions, described in section 3.2.

Instruction operands may take a number of forms: they can be registers, described simply by the register name (e.g. `eax`, `ebx`, `cr0`). NASM does not use the gas-style syntax in which register names must be prefixed by `%` (signifying that they are effective addresses) (see section 3.3), constants (section 3.4) or expressions (section 3.5).

For x87 floating-point instructions, NASM accepts a wide range of syntaxes; you can use two-operand forms like `FMASKMOVQ`, or you can use NASM's native single-operand forms in most cases. For example, you can code:

```
fadd    st1                ; this sets st0 := st0 + st1
fadd    st0,st1            ; so does this
```

```

fadd    st1,st0          ; this sets st1 := st1 + st0
fadd    to st1           ; so does this

```

Almost any x87 floating-point instruction that references memory must use one of the prefixes BWORD, QWORD or TWORD to indicate what size of memory operand it refers to.

3.2 Pseudo-Instructions

Pseudo-instructions are things which, though not real x86 machine instructions, are used in the instruction field anyway because that's the most convenient place to put them. The current pseudo-instructions are `DB`, `DW`, `DD`, `DQ`, `DT`, `DO`, `DY` and `DZ`; the uninitialized counterpart `RESB`, `RESW`, `RESQ`, `REST`, `RESO`, `RESY` and `RESZ`; the `INCbin` command, the `EQU` command, and the `TIMES` prefix.

3.2.1 DB and Friends: Declaring Initialized Data

`DB`, `DW`, `DD`, `DQ`, `DT`, `DO`, `DY` and `DZ` are used, much as in MASM, to declare initialized data in the output file. They can be invoked in a wide range of ways:

```

db      0x55              ; just the byte 0x55
db      0x55,0x56,0x57    ; three bytes in succession
db      'a',0x55          ; character constants are OK
db      'hello',13,10,'$' ; so are string constants
dw      0x1234            ; 0x34 0x12
dw      'a'               ; 0x61 0x00 (it's just a number)
dw      'ab'              ; 0x61 0x62 (character constant)
dw      'abc'             ; 0x61 0x62 0x63 0x00 (string)
dd      0x12345678        ; 0x78 0x56 0x34 0x12
dd      1.234567e20       ; floating-point constant
dq      0x123456789abcdef0 ; eight byte constant
dq      1.234567e20       ; double-precision float
dt      1.234567e20       ; extended-precision float

```

`DT`, `DO`, `DY` and `DZ` do not accept numeric constants as operands.

3.2.2 RESB and Friends: Declaring Uninitialized Data

`RESB`, `RESW`, `RESQ`, `REST`, `RESO`, `RESY` and `RESZ` are designed to be used in the BSS section of a module to declare *uninitialized* storage space. Each takes a single operand, which is the number of bytes, words, double words, whatever, to reserve. As stated in section 2.2.7, NASM does not support the MASM/TASM syntax of reserving uninitialized space by writing `0`. For similar things, this is what it does instead. The operand to a `RESB`-type pseudo-instruction is a *critical expression*: see

For example:

```

buffer:      resb    64          ; reserve 64 bytes
wordvar:     resw    1           ; reserve a word
realarray    resq    10          ; array of ten reals
ymmval:      resy    1           ; one YMM register
zmmvals:     resz    32          ; 32 ZMM registers

```

3.2.3 INCBIN: Including External Binary Files

`INCbin` is borrowed from the old Amiga assembler DevPac: it includes a binary file verbatim into the output file. This can be handy for (for example) including graphics and sound data directly into a game executable file. It can be called in one of these three ways:

```

incbin "file.dat"          ; include the whole file
incbin "file.dat",1024     ; skip the first 1024 bytes

```

```
incbin "file.dat",1024,512    ; skip the first 1024, and
                             ; actually include at most 512
```

INCBIN is both a directive and a standard macro; the standard macro version searches for the file in the include file search path and adds the file to the dependency lists. This macro can be overridden if desired.

3.2.4 EQU: Defining Constants

EQU defines symbols to given constant value when EQU is used, the source line must contain a label. The action of EQU is to define the given label to have the value of its (only) operand. This definition is absolute, and cannot change later. So, for example,

```
message      db      'hello, world'
msglen       equ     $-message
```

defines msglen to be the constant 12. msglen may not then be redefined later. This is not a preprocessor definition either; the value of msglen is evaluated *once*, using the value of \$ (see section 3.5 for an explanation of \$) at the point of definition, rather than being evaluated where it is referenced and using the value of \$ at the point of reference.

3.2.5 TIMES: Repeating Instructions or Data

The TIMES prefix causes the instruction to be assembled multiple times. This is partly presented as NASM's equivalent of the DUP syntax supported by MASM-compatible assemblers, in that

```
zerobuf:      times 64 db 0
```

is similar things, but TIMES is more versatile than that. The argument to TIMES is not just a numeric constant, but a numeric *expression*, so you can do things like

```
buffer: db      'hello, world'
          times 64-$+buffer db ' '
```

which will store exactly enough space to make the total length of buffer 64. Finally, TIMES can be applied to ordinary instructions, so you can code trivial unrolled loops in i

```
          times 100 movsb
```

Note that there is no effective difference between times 100 resb and resb 100, except that the latter will be assembled about 100 times faster due to the internal structure of

The operand to TIMES is a critical expression (section 3.8).

Note also that TIMES can't be applied to macros; the reason for this is that TIMES is processed after the macro phase, which allows the argument to TIMES to contain expressions such as 64-\$+buffer as above. To repeat more than one line of code, or a complex macro, use the preprocessor %rep directive.

3.3 Effective Addresses

An effective address is any operand in an instruction which references memory. Effective addresses in NASM have a very simple syntax: they consist of an expression evaluating to the desired address, enclosed in square brackets. For example:

```
wordvar dw      123
          mov     ax,[wordvar]
          mov     ax,[wordvar+1]
          mov     ax,[es:wordvar+bx]
```

Anything not conforming to this simple system is not a valid memory reference in NASM, for example es:wordvar[bx].

More complicated effective addresses, such as those involving more than one register, work exactly the same way:

```
mov     eax,[ebx*2+ecx+offset]
mov     ax,[bp+di+8]
```

NASM is capable of doing all these effective addresses, so that things which don't necessarily look legal are perfectly all right:

```
mov     eax,[ebx*5]           ; assembles as [ebx*4+ebx]
mov     eax,[label1*2-label2] ; ie [label1+(label1-label2)]
```

Some forms of effective address have more than one assembled form; in most such cases NASM will generate the smallest form it can. For example, there are distinct assembled forms for the 32-bit effective addresses `[eax*2+0]` and `[eax+eax]`, and NASM will generally generate the latter on the grounds that the former requires four bytes to store a zero offset.

NASM has a hinting mechanism which will cause `[eax+ebx]` and `[ebx+eax]` to generate different opcodes; this is occasionally useful because `[esi+ebp]` and `[ebp+esi]` have different default segment registers.

However, you can force NASM to generate an effective address in particular form by the use of the keywords `BYTE`, `WORD`, `DWORD` and `NOSPLIT`. If you need `[eax+3]` to be assembled using a double-word offset field instead of the one byte NASM will normally generate, you can code `[dword eax+3]`. Similarly, you can force NASM to use a byte offset for a small value which it has not seen on the first pass (see section 3.8 for an example of such a code fragment) by using `[byte eax+offset]`. As special cases, `[byte eax]` will code `[eax+0]` with a byte offset of zero, and `[dword eax]` will code it with a double-word offset of zero. The normal form, `[eax]`, will be coded with no offset field.

The forms described in the previous paragraph are also useful if you are trying to access data in a 32-bit segment from within 16-bit code. For more information on this see the section on mixed-size addressing (section 10.2). In particular, if one needs access to data with an offset that is larger than will fit in a 6-bit value, if you don't specify that it is a double-word offset, NASM will cause the high word of the offset to be lost.

Similarly NASM will split `[eax*2]` into `[eax+eax]` because that allows the offset field to be absent and space to be saved; in fact, it will also split `[eax*2+offset]` into `[eax+eax+offset]`. You can combat this behaviour by the use of the `NOSPLIT` keyword: `[nosplit eax*2]` will force `[eax*2+0]` to be generated literally. `[nosplit eax*1]` also has the same effect. In another way, a split EA form `[0, eax*2]` can be used, too. However, `NOSPLIT` in `[nosplit eax+eax]` will be ignored because user's intention here is considered as `[eax+eax]`.

In 64-bit mode, NASM will by default generate absolute addresses. The `REL` keyword makes it produce RIP-relative addresses. Since this is frequently the normal desired behaviour, see the `DEFAULT` directive (section 6.2). The keyword `ABS` overrides `REL`.

A new form of split effective address syntax is also supported. This is mainly intended for `mib` operands as used by `MPX` instructions, but can be used for any memory reference. The basic concept of this form is splitting base and index.

```
mov eax,[ebx+8,ecx*4] ; ebx=base, ecx=index, 4=scale, 8=disp
```

For `mib` operands, there are several ways of writing effective addresses depending on the tools NASM supports all currently possible ways of `mib` syntax:

```
; bndstx
; next 5 lines are parsed same
; base=rbx, index=rbx, scale=1, displacement=3
bndstx [rax+0x3,rbx], bnd0 ; NASM - split EA
```



```

bndstx [rbx*1+rax+0x3], bnd0    ; GAS - '*1' indicates an index reg
bndstx [rax+rbx+3], bnd0        ; GAS - without hints
bndstx [rax+0x3], bnd0, rbx     ; ICC-1
bndstx [rax+0x3], rbx, bnd0     ; ICC-2

```

When broadcasting decorator is used, the opsize keyword should match the size of each operand.

```

VDIVPS zmm4, zmm5, dword [rbx]{1to16}    ; single-precision float
VDIVPS zmm4, zmm5, zword [rbx]             ; packed 512 bit memory

```

3.4 Constants

NASM understands four different types of constant: numeric, character, string and floating point.

3.4.1 Numeric Constants

A numeric constant is simply a number. NASM allows you to specify numbers in a variety of number bases, in a variety of ways: you can suffix with `X`, `D`, `T`, `Q`, or `O`, and `B` or `Y` for hexadecimal, decimal, octal and binary respectively, or you can prefix with `0x` for hexadecimal in the style of C, or you can prefix with `$` for hexadecimal in the style of Borland and Asca. Motorola Assemblers. Note though, that the `$` prefix does double duty as a prefix on identifiers (see section 3.1), so a number prefixed with `$` must have a digit after the `$` rather than a letter. In addition, current versions of NASM accept the prefix `0h` for hexadecimal, `0d` or `0t` for decimal, `0o` or `0q` for octal, and `0b` or `0y` for binary. Please note that unlike C, a `0` prefix by itself does *not* imply an octal constant!

Numeric constants can have underscores (`_`) interspersed to break up long strings.

Some examples (all producing exactly the same code):

```

mov     ax,200                ; decimal
mov     ax,0200               ; still decimal
mov     ax,0200d              ; explicitly decimal
mov     ax,0d200              ; also decimal
mov     ax,0c8h               ; hex
mov     ax,$0c8               ; hex again: the 0 is required
mov     ax,0xc8               ; hex yet again
mov     ax,0hc8               ; still hex
mov     ax,310q               ; octal
mov     ax,310o               ; octal again
mov     ax,0o310              ; octal yet again
mov     ax,0q310              ; octal yet again
mov     ax,11001000b          ; binary
mov     ax,1100_1000b         ; same binary constant
mov     ax,1100_1000y         ; same binary constant once more
mov     ax,0b1100_1000        ; same binary constant yet again
mov     ax,0y1100_1000        ; same binary constant yet again

```

3.4.2 Character Strings

A character string consists of up to 255 characters enclosed in either single quotes (`'...'`) or double quotes (`"..."`) or backquotes (``...``). Single or double quotes are equivalent to NASM except for course that surrounding the constant with single quotes allows double quotes to appear within and vice versa; the contents of those are represented verbatim. Strings enclosed in backquotes support C-style `\`-escapes for special characters.

The following escape sequences are recognized by backquoted strings:

```

\'      single quote (')
\"      double quote (")

```

<code>\'</code>	backquote (<code>`</code>)
<code>\\</code>	backslash (<code>\</code>)
<code>\?</code>	question mark (<code>?</code>)
<code>\a</code>	BEL (ASCII 7)
<code>\b</code>	BS (ASCII 8)
<code>\t</code>	TAB (ASCII 9)
<code>\n</code>	LF (ASCII 10)
<code>\v</code>	VT (ASCII 11)
<code>\f</code>	FF (ASCII 12)
<code>\r</code>	CR (ASCII 13)
<code>\e</code>	ESC (ASCII 27)
<code>\377</code>	Up to 3 octal digits - literal byte
<code>\xFF</code>	Up to 2 hexadecimal digits - literal byte
<code>\u1234</code>	4 hexadecimal digits - Unicode character
<code>\U12345678</code>	8 hexadecimal digits - Unicode character

All the escape sequences are reserved. Note that `\0`, meaning a NUL character (ASCII 0), is a special case of the octal escape sequence.

Unicode characters specified with `\u` are converted to UTF-8. For example, the following lines are all equivalent:

```
db '\u263a'           ; UTF-8 smiley face
db '\xe2\x98\xba'    ; UTF-8 smiley face
db 0E2h, 098h, 0BAh  ; UTF-8 smiley face
```

3.4.3 Character Constants

A character constant consists of a string of one byte long, used in an expression context. It is treated as if it was an integer.

A character constant with more than one byte will be arranged with little-endian order in mind if you code

```
mov eax, 'abcd'
```

then the constant generated is not `0x61626364`, but `0x64636261`, so that if you were to store the value in memory, it would read `abcd` rather than `dcba`. This is also the sense of character constants understood by the Pentium's `CPUID` instruction.

3.4.4 String Constants

String constants are character strings used in the context of some pseudo-instructions, namely the `DB` family and `INCBIN` (where it represents a filename). They are also used in certain preprocessor directives.

A string constant looks like a character constant, only longer. It is created as a concatenation of maximum-size character constants for the conditions. So the following are equivalent

```
db 'hello'           ; string constant
db 'h','e','l','l','o' ; equivalent character constants
```

And the following are also equivalent:

```
dd 'ninechars'       ; doubleword string constant
dd 'nine','char','s'  ; becomes three doublewords
db 'ninechars',0,0,0  ; and really looks like this
```

Note that when used in string-supporting context, quoted strings are created as string constants even if they are short enough to be a character constant, because otherwise `db 'ab'` would have the

same effect as `db a'`, which would be silly. Similarly, three-character or four-character constants are treated as strings when they are operands to `DW`, and so forth.

3.4.5 Unicode Strings

The special operators `__utf16__`, `__utf16le__`, `__utf16be__`, `__utf32__`, `__utf32le__` and `__utf32be__` allow definition of Unicode strings. They take a string in UTF-8 format and convert it to UTF-16 or UTF-32, respectively. Unless the `be` form is specified, the output is little-endian.

For example:

```
%define u(x) __utf16__(x)
%define w(x) __utf32__(x)

        dw u('C:\WINDOWS'), 0      ; Pathname in UTF-16
        dd w('A + B = \u206a'), 0   ; String in UTF-32
```

The `UTF` operators can be applied either to strings passed to the `DB` family instructions, or to character constants in an expression context.

3.4.6 Floating-Point Constants

Floating-point constants are acceptable only as arguments to `DB`, `DW`, `DD`, `DQ`, `DT`, and `DO`, or as arguments to the special operators `__float8__`, `__float16__`, `__float32__`, `__float64__`, `__float80m__`, `__float80e__`, `__float128l__`, and `__float128h__`.

Floating-point constants are expressed in the traditional form: digits, the period, the optional more digits, the optional `+` or `-` exponent. The period is mandatory, so that NASM can distinguish between `ddl`, which declares an integer constant, and `ddl.0` which declares a floating-point constant.

NASM supports C99-style hexadecimal floating-point: 0x, hexadecimal digits, period, optionally more hexadecimal digits, the optional `+` or `-` exponent. The period is mandatory, so that NASM can distinguish between `ddl`, which declares an integer constant, and `ddl.0` which declares a floating-point constant.

Underscores to break up groups of digits are permitted in floating-point constants as well.

Some examples:

```
db      -0.2                      ; "Quarter precision"
dw      -0.5                      ; IEEE 754r/SSE5 half precision
dd      1.2                      ; an easy one
dd      1.222_222_222            ; underscores are permitted
dd      0x1p+2                   ; 1.0x2^2 = 4.0
dq      0x1p+32                  ; 1.0x2^32 = 4 294 967 296.0
dq      1.e10                    ; 10 000 000 000.0
dq      1.e+10                   ; synonymous with 1.e10
dq      1.e-10                   ; 0.000 000 000 1
dt      3.141592653589793238462 ; pi
do      1.e+4000                 ; IEEE 754r quad precision
```

The `__float8__` operator produces a floating-point number in the format: sign:exponent:mantissa, with an exponent bias of 7. This appears to be the most frequently used 8-bit floating-point format, although it is not covered by any formal standard. This is sometimes called a "minifloat."

The special operators are used to produce floating-point numbers in other contexts. They produce the binary representation of a specific floating-point number as an integer, and can be used anywhere integer constants are used in an expression. `__float80m__` and `__float80e__` produce the 64-bit

mantissa and 16-bit exponent to form an 80-bit floating-point number, and `__float128l__` and `__float128h__` produce the lower and upper 64-bit halves of a 128-bit floating-point number, respectively.

For example:

```
mov    rax, __float64__(3.141592653589793238462)
```

.. would assign the binary representation of a 64-bit floating-point number into RAX. This is exactly equivalent to:

```
mov    rax, 0x400921fb54442d18
```

NASM cannot compile-time arithmetic or floating-point constants. This is because NASM is designed to be portable, although it always generates code to run on x86 processors; the assembler itself runs on many systems with an ANSI C compiler. Therefore, the assembler cannot guarantee the presence of floating-point units capable of handling the number formats, and for NASM to be able to do floating-point arithmetic would have to include a complete set of floating-point routines, which would significantly increase the size of the assembler for very little benefit.

The special tokens `__Infinity__`, `__QNaN__` (or `__NaN__`) and `__SNaN__` can be used to generate infinities, quiet NaNs, and signalling NaNs, respectively. These are normal

```
%define Inf __Infinity__
```

```
%define NaN __QNaN__
```

```
dq      +1.5, -Inf, NaN          ; Double-precision constants
```

The `%use fp` standard macro package contains a set of convenience macros. See section

3.4.7 Packed BCD Constants

x87-style packed BCD constants are based in the same context as 80-bit floating-point numbers.

They are suffixed with `p` or prefixed with `0p`, and can include up to 18 decimal digits.

As with other numeric constants, underscores can be used to separate digits.

For example:

```
dt 12_345_678_901_245_678p
dt -12_345_678_901_245_678p
dt +0p33
dt 33p
```

3.5 Expressions

Expressions in NASM are similar in syntax to those in C. Expressions are evaluated as 64-bit integers which are then adjusted to the appropriate size.

NASM supports special tokens in expressions, allowing calculations to involve the current assembly position: the `%` and `$$` tokens. `%` evaluates to the assembly position at the beginning of the line containing the expression; you can code an infinite loop using `jmp %`. `$$` evaluates to the beginning of the current section; so you can tell how far into the section you are by using `($$ - %)`.

The arithmetic operators provided by NASM are listed here, in increasing order of precedence.

3.5.1 |: Bitwise OR Operator

The `|` operator gives a bitwise OR, exactly as performed by the `OR` machine instruction. Bitwise OR is the lowest-priority arithmetic operator supported by NASM.

3.5.2 ^: Bitwise XOR Operator

`^` provides the bitwise XOR operation.

3.5.3 &: Bitwise AND Operator

`&` provides the bitwise AND operation.

3.5.4 << and >>: Bit Shift Operators

`<<` gives a bit-shift to the left, just as it does in C. So `<<3` evaluates to times 8, or 40. `>>` gives a bit-shift to the right; in NASM, such shifts are *always* unsigned, so that the bits shifted in from the left-hand end are filled with zero rather than a sign-extension of the previous high

3.5.5 + and -: Addition and Subtraction Operators

The `+` and `-` operators do perfectly ordinary addition and subtraction.

3.5.6 *, /, //, % and %%: Multiplication and Division

`*` is the multiplication operator and `/` is the division operator. `/` is unsigned division and `//` is signed division. Similarly, `%` and `%%` provide unsigned and signed modulo operators respectively. NASM, like ANSI C, provides no guarantees about the sensible operation of the signed modulo operators. Since the character is used extensively by the macro preprocessor, you should ensure that both the signed and unsigned modulo operators are followed by white space wherever they appear.

3.5.7 Unary Operators

The highest-priority operators in NASM's expression grammar are those which only apply to one argument. These are `+`, `-`, `~`, `!`, `SEG`, and the integer functions operators.

`-` negates its operand, `~` does nothing (it's provided for symmetry with `-`), `!` computes the one's complement of its operand, `!` is the logical negation operator.

`SEG` provides the segment address of its operand (explained in more detail in section 5.4).

As an additional operator with leading and trailing double underscores, `__` complements the integer functions of the `ifunc` macro package, see section 5.4.

3.6 SEG and WRT

When writing large 6-bit programs which must be split into multiple segments, it is often necessary to be able to refer to the segment part of the address of a symbol. NASM supports the `SEG` operator to perform this function.

The `SEG` operator returns the *preferred* segment base of a symbol, defined as the segment base relative to which the offset of the symbol makes sense. So the code

```
mov     ax, seg symbol
mov     es, ax
mov     bx, symbol
```

will load `ES:BX` with a valid pointer to the symbol `symbol`.

Things can be more complex than this: since 16-bit segments and groups may overlap, you might occasionally want to refer to some symbol using a different segment base from the preferred one. NASM lets you do this, by the use of the `WRT` (With Reference To) keyword. So you can

```
mov     ax, weird_seg      ; weird_seg is a segment base
mov     es, ax
mov     bx, symbol wrt weird_seg
```

to load ES:BX with a different, but functionally equivalent, pointer to the symbol segment. NASM supports far (inter-segment) calls and jumps by means of the syntax call segment:offset, where segment and offset both represent immediate values. So to call a far procedure, you could code either of

```
call    (seg procedure):procedure
call    weird_seg:(procedure wrt weird_seg)
```

(The parentheses are included for clarity, to show the intended parsing of the above instructions. They are not necessary in practice.)

NASM supports the syntax call far procedure as a synonym for the first of the above usages. JMP works identically to CALL in these examples.

To declare a far pointer to a data item in a data segment, you must code

```
dw      symbol, seg symbol
```

NASM supports an inconvenient synonym for this, though you can always invent one using the macro processor.

3.7 STRICT: Inhibiting Optimization

When assembling with the optimizer set to level 2 or higher (see section 2.1.23), NASM will use size specifiers (BYTE, WORD, DWORD, QWORD, TWORD, OWORD, YWORD or ZWORD), but will give them the smallest possible size. The keyword **STRICT** is used to inhibit optimization and force a particular operand to be emitted in the specified size. For example, with the optimizer on, and

```
push dword 33
```

is encoded in three bytes 66 6A 21, whereas

```
push strict dword 33
```

is encoded in six bytes, with a full dword immediate operand 66 68 21 00 00 00.

With the optimizer off, the same code (six bytes) is generated whether the **STRICT** keyword is used or not.

3.8 Critical Expressions

Although NASM has an optional multi-pass optimizer, there are some expressions which must be resolvable on the first pass. These are called *Critical Expressions*.

The first pass is used to determine the size of all the assembled code and data, so that the second pass, when generating all the code, knows all the symbol addresses the code refers to. So anything NASM can't handle is code whose size depends on the value of a symbol declared after the code in question. For example,

```
times (label-$) db 0
label: db      'Where am I?'
```

The argument **TIMES** in this case could equally legally evaluate anything at all. NASM will reject this example because it cannot tell the size of the **TIMES** line when it first sees it. It will just as firmly reject the slightly paradoxical code

```
times (label-$(+1)) db 0
label: db      'NOW where am I?'
```

in which *any* value for the **TIMES** argument is by definition wrong!

NASM rejects these examples by means of a concept called *critical expression*, which is defined to be an expression whose value is required to be computable in the first pass, and which must therefore depend only on symbols defined before it. The argument to the TIMES prefix is a critical

3.9 Local Labels

NASM gives special treatment to symbols beginning with a period. A label beginning with a single period is treated as a *local* label, which means that it is associated with the previous non-local label. So, for example:

```
label1 ; some code

.loop
    ; some more code

    jne .loop
    ret

label2 ; some code

.loop
    ; some more code

    jne .loop
    ret
```

In the above code fragment, each JNE instruction jumps to the line immediately before it because the two definitions of .loop are kept separate by virtue of each being associated with the previous non-local label.

This form of local label handling is borrowed from the old Amiga assembler DevPac; however, NASM goes one step further, allowing access to local labels from the parts of the code. This is achieved by means of *defining* local labels in terms of the previous non-local label: the first definition of loop above is really defining a symbol called label1.loop, and the second defines a symbol called label2.loop. So, if you really needed to, you could write

```
label3 ; some more code
    ; and some more

    jmp label1.loop
```

Sometimes it is useful in a macro, for instance, to be able to define a label which can be referenced from anywhere, but which doesn't interfere with the normal local-label mechanism. Such a label can't be non-local because it would interfere with subsequent definitions and references to local labels; and it can't be local because the macro that defined it wouldn't know the label's full name. NASM therefore introduces a third type of label, which is probably only useful for macro definitions. If a label begins with the special prefix `..@`, then it does nothing to the local label mechanism.

```
label1: ; a non-local label
.local: ; this is really label1.local
..@foo: ; this is a special symbol
label2: ; another non-local label
.local: ; this is really label2.local

    jmp ..@foo ; this will jump three lines up
```

NASM has the capacity to define other special symbols beginning with a double period. For example, `..start` is used to specify the entry point in the object output format (see section 7.4.6),

..imagebase is used to find but the offset from base address of the current image in the win64
output format (see section 7.6.1) So just keep in mind that symbols beginning with double period are
special.

Chapter 4: The NASM Preprocessor

NASM contains a powerful macro processor which supports conditional assembly, multi-level file inclusion, `%macro` (single-line and multi-line) and context stack mechanisms for extra macro power. Preprocessor directives all begin with a `%` sign.

The preprocessor collapses all lines which end with a backslash (`\`) character into a

```
%define THIS_VERY_LONG_MACRO_NAME_IS_DEFINED_TO \
    THIS_VALUE
```

will work like a single-line macro without the backslash-newline sequence.

4.1 Single-Line Macros

4.1.1 The Normal Way: `%define`

Single-line macros are defined using the `%define` preprocessor directive. The definition works a similar way to C; so you can do things like

```
%define ctrl    0x1F &
%define param(a,b) ((a)+(a)*(b))

    mov     byte [param(2,ebx)], ctrl 'D'
```

which will expand to

```
    mov     byte [(2)+(2)*(ebx)], 0x1F & 'D'
```

When the expansion of a single-line macro contains tokens which invoke another macro, the expansion is performed at invocation time, not at definition time. Thus the code

```
%define a(x)    1+b(x)
%define b(x)    2*x
```

```
    mov     ax,a(8)
```

will evaluate in the expected way to `mov ax,1+2*8`, even though the macro wasn't defined at the time of definition of `a`.

Macros defined with `%define` are case sensitive: after `%define foobar`, only `foo` will expand to `bar`. `Foo`, `FOO` will not. By using `%define` instead of `%DEFIN` (the 'i' stands for 'insensitive') you can define all the case variants of a macro at once, so that `%define foobar` would cause `foo`, `Foo`, `FOO`, `f00` and so on all to expand to `bar`.

There is a mechanism which detects when a macro call has occurred as a result of a previous expansion of the same macro, to guard against circular references and infinite loops. If this happens, the preprocessor will only expand the first occurrence of the macro. Hence, if you code

```
%define a(x)    1+a(x)

    mov     ax,a(3)
```

the macro `a(3)` will expand once becoming `1+a(3)` and will then expand no further. This behaviour can be useful: see section 9.1 for an example of its use.

You can overload single-line macros: if you write

```
%define foo(x)    1+x
%define foo(x,y)  1+x*y
```

the preprocessor will be able to handle both types of macro call by counting the parameters you pass; so `foo(3)` will become `1+3` whereas `foo(ebx,2)` will become `1+ebx*2`. However, if you do

```
%define foo bar
```

then no other definition of `foo` will be accepted, a macro with parameters prohibits the definition of the same name as a macro *with* parameters, and vice versa.

This doesn't prevent single-line macros being *redefined*: you can perfectly well define

```
%define foo bar
```

and then re-define it later in the same source file with

```
%define foo baz
```

Then everywhere the macro `foo` is invoked, it will be expanded according to the most recent definition. This is particularly useful when defining single-line macros with assignments (see section 4.1.7).

You can pre-define single-line macros using the `-d` option of the NASM command line (see section 2.1.19).

4.1.2 Resolving %define: %xdefine

When a reference to an embedded single-line macro is resolved at the time that the embedding macro is *defined*, as opposed to when the embedding macro is *expanded*, you need a different mechanism to the one offered by `%define`. The solution is to use `%xdefine`, its case-insensitive counterpart `%ixdefine`.

Suppose you have the following code:

```
%define  isTrue  1
%define  isFalse isTrue
%define  isTrue  0

val1:    db      isFalse

%define  isTrue  1

val2:    db      isFalse
```

In this case, `val1` is equal to 0, and `val2` is equal to 1. This is because, when a single-line macro is defined using `%define`, it is expanded only when it is called. As `isFalse` expands to `isTrue`, the expansion will be the current value of `isTrue`. The first time it is called that is 0, and the second time it is 1.

If you wanted `isFalse` to expand to the value assigned to the embedded macro `isTrue` at the time that `isFalse` was defined, you need to change the above code to use `%xdefine`.

```
%xdefine isTrue  1
%xdefine isFalse isTrue
%xdefine isTrue  0

val1:    db      isFalse

%xdefine isTrue  1

val2:    db      isFalse
```

Now, each time that `isFalse` is called, it expands to `1`, as that is what the embedded macro `isTrue` expanded to at the time that `isFalse` was defined.

4.1.3 Macro Indirection: %[...]

The `%[...]` construct can be used to expand macros in contexts where macro expansion would otherwise not occur, including in the names of other macros. For example, if you have set of macros named `Foo16`, `Foo32` and `Foo64`, you could write:

```
mov ax, Foo%[__BITS__]    ; The Foo value
```

to use the built-in macro `__BITS__` (see section 4.11.5) to automatically select between them. Similarly, the two statements:

```
%xdefine Bar            Quux    ; Expands due to %xdefine
#define Bar              %[Quux] ; Expands due to %[...]
```

have, in fact, exactly the same effect.

`%[...]` concatenates adjacent tokens in the same way that multi-line macro parameters do, see section 4.3.9 for details.

4.1.4 Concatenating Single Line Macro Tokens: %+

Individual tokens in single-line macros can be concatenated to produce longer tokens for later processing. This can be useful if there are several similar macros that perform similar operations.

Please note that a space is required after `+`, in order to disambiguate it from the syntax `++` used in multiline macros.

As an example, consider the following:

```
%define BDASTART 400h                ; Start of BIOS data area

struc    tBIOSDA                      ; its structure
    .COM1addr    RESW    1
    .COM2addr    RESW    1
    ; ..and so on
endstruc
```

Now, if we need to access the elements of `tBIOSDA` in different places, we can end up with:

```
mov     ax, BDASTART + tBIOSDA.COM1addr
mov     bx, BDASTART + tBIOSDA.COM2addr
```

This will become pretty ugly (and tedious) if used in many places, and can be reduced in size significantly by using the following macro:

```
; Macro to access BIOS variables by their names (from tBDA):
```

```
%define BDA(x)  BDASTART + tBIOSDA. %+ x
```

Now the above code can be written as:

```
mov     ax, BDA(COM1addr)
mov     bx, BDA(COM2addr)
```

Using this feature, we can simplify references to a lot of macros (and, in turn, reduce code size).

4.1.5 The Macro Name Itself: %? and %??

The special symbols `%?` and `%??` can be used to reference the macro name itself inside a macro expansion; this is supported for both single- and multi-line macros. `%?` refers to the macro as

invoked, whereas `??` refers to the macro name as *declared*. The two are always the same for case-sensitive macros, but for case-insensitive macros, they can differ.

For example:

```
%define Foo mov %?,%??
```

```
foo
FOO
```

will expand to:

```
mov foo,Foo
mov FOO,Foo
```

The sequence:

```
%define keyword $%?
```

can be used to make a keyword "disappear", for example in case a new instruction has been used as a label in older code. For example:

```
%define pause $%? ; Hide the PAUSE instruction
```

4.1.6 Undefining Single-Line Macros: %undef

Single-line macros can be removed with the `%undef` directive. For example, the following

```
%define foo bar
%undef foo
```

```
mov eax, foo
```

will expand to the instruction `moveax,foo`, since after `%undef` the macro `foo` is no longer defined.

Macro that would otherwise be pre-defined can be undefined on the command-line using the `'-u'` option on the NASM command line: see section 2.1.20.

4.1.7 Preprocessor Variables: %assign

An alternative way to define single-line macros is by means of the `%assign` command (and its case-insensitive counterpart `%iassign`, which differs from `%assign` exactly the same way that `%ifdef` differs from `%define`).

`%assign` is used to define single-line macros which take parameters and have a numeric value. This value can be specified in the form of an expression, and it will be evaluated once, when the `%assign` directive is processed.

Like `%define`, macros defined using `%assign` can be re-defined later, so you can do the

```
%assign i i+1
```

to increment the numeric value of a macro.

`%assign` is useful for controlling the termination of preprocessor loops (see section 4.5 for an example of this). Another use for `%assign` is given in section 8.4 and section 9.1.

The expression passed to `%assign` is a critical expression (see section 3.8) and must also evaluate to a pure number (rather than a relocatable reference such as a code address, anything involving a register).

4.1.8 Defining Strings: %defstr

`%defstr` and its case-insensitive counterpart `%idefstr` define or redefine a single-line macro without a parameter but convert the entire right-hand side after macro expansion to a quoted string before definition.

For example:

```
%defstr test TEST
```

is equivalent to

```
%define test 'TEST'
```

This can be used, for example, with the `%! construct` (see section 4.10.2):

```
%defstr PATH %!PATH ; The operating system PATH variable
```

4.1.9 Defining Tokens: %deftok

`%deftok` and its case-insensitive counterpart `%ideftok` define or redefine a single-line macro without a parameter but convert the second parameter after string conversion to a sequence of tokens.

For example:

```
%deftok test 'TEST'
```

is equivalent to

```
%define test TEST
```

4.2 String Manipulation in Macros

It's often useful to be able to handle strings in macros. NASM supports a few simple string handling macro operators from which more complex operations can be constructed.

All the string operators define or redefine a value (either a string or a numerical value) as a single-line macro. When producing a string value, it may change the style of quoting of the input string strings, and possibly use `\`-escapes inside ```-quoted strings.

4.2.1 Concatenating Strings: %strcat

The `%strcat` operator concatenates quoted strings and assign them to a single-line macro.

For example:

```
%strcat alpha "Alpha: ", '12" screen'
```

... would assign the value `'Alpha: 12" screen'` to `alpha`. Similarly:

```
%strcat beta '"foo"\', "'bar"'
```

... would assign the value `'"foo"\\'bar''` to `beta`.

The use of commas to separate strings is permitted but optional.

4.2.2 String Length: %strlen

The `%strlen` operator assigns the length of a string to a macro. For example:

```
%strlen charcnt 'my string'
```

In this example, `charcnt` would receive the value 9, just as if `%assign` had been used. In this example, `'mystring'` was a literal string but it could also have been a single-line macro that expands to a string, as in the following example:

```
%define sometext 'my string'
%strlen charcnt sometext
```

As in the first case, this would result in charcnt being assigned the value of 9.

4.2.3 Extracting Substrings: %substr

Individual letters or substrings of strings can be extracted using the %substr operator. An example of its use is probably more useful than the description:

```
%substr mychar 'xyzw' 1      ; equivalent to %define mychar 'x'
%substr mychar 'xyzw' 2      ; equivalent to %define mychar 'y'
%substr mychar 'xyzw' 3      ; equivalent to %define mychar 'z'
%substr mychar 'xyzw' 2,2    ; equivalent to %define mychar 'yz'
%substr mychar 'xyzw' 2,-1    ; equivalent to %define mychar 'yzw'
%substr mychar 'xyzw' 2,-2    ; equivalent to %define mychar 'yz'
```

With %strlen (see section 4.2.2), the first parameter is the single-line macro to be created and the second is the string. The third parameter specifies the first character to be selected and the optional fourth parameter (preceded by comma) is the length. Note that the first index is 1, not 0, and the last index is equal to the value that %strlen would assign given the same string. Index values out of range result in an empty string. A negative length means "until N-character before end of string", i.e. -1 means until end of string, -2 until one character before, etc.

4.3 Multi-Line Macros: %macro

Multi-line macros are much more like the type of macro seen in NASM and TASM: a multi-line macro definition in NASM looks something like this.

```
%macro prologue 1

    push    ebp
    mov     ebp,esp
    sub     esp,%1

%endmacro
```

This defines a C-like function prologue as a macro: so you would invoke the macro with

```
myfunc: prologue 12
```

which would expand to the three lines of code

```
myfunc: push    ebp
        mov     ebp,esp
        sub     esp,12
```

The number 1 after the macro name in the %macro line defines the number of parameters the macro prologue expects to receive. These 0-1 inside the macro definition refers to the first parameter to the macro call. With a macro taking more than one parameter, subsequent parameters would be referred to as %2, %3 and so on.

Multi-line macros, like single-line macros, are case-sensitive unless you define them using the alternative directive %imacro.

If you need to pass a comma-separated parameter to a multi-line macro, you can do that by enclosing the entire parameter in braces. So you could code things like

```
%macro silly 2

    %2: db    %1
```

```
%endmacro
```

```
        silly 'a', letter_a           ; letter_a:  db 'a'
        silly 'ab', string_ab         ; string_ab: db 'ab'
        silly {13,10}, crlf           ; crlf:      db 13,10
```

4.3.1 Overloading Multi-Line Macros

As with single-line macros, multi-line macros can be overloaded by defining the same macro name several times with different numbers of parameters. This time, exceptions are made for macros with no parameters at all. So you could define

```
%macro  prologue 0
```

```
        push     ebp
        mov      ebp,esp
```

```
%endmacro
```

to define an alternative form of the function prologue which allocates no local stack.

Sometimes, however, you might want to overload a machine instruction. For example, you might want to define

```
%macro  push 2
```

```
        push     %1
        push     %2
```

```
%endmacro
```

so that you could code

```
        push     ebx           ; this line is not a macro call
        push     eax,ecx       ; but this one is
```

Ordinarily, NASM will give a warning for the first of the above two lines, since `push` is now defined to be a macro, and being invoked with a number of parameters for which no definition has been given. The correct code will still be generated, but the assembler will give a warning. This warning can be disabled by the use of the `-w-macro-params` command-line option (see section 2.1.25).

4.3.2 Macro-Local Labels

NASM allows you to define labels within a multi-line macro definition in such a way as to make them local to the macro call. Calling the same macro multiple times will use different labels each time. You do this by prefixing `%` to the label name. So you can invent an instruction which executes `RET` if the Z flag is set by doing this:

```
%macro  retz 0
```

```
        jnz      %%skip
        ret
%%skip:
```

```
%endmacro
```

You can call this macro as many times as you want, and every time you call it NASM will make up a different 'real' name to substitute for the label `%%skip`. The names NASM invents are of the form `..@2345.skip`, where the number 2345 changes with every macro call. The `..@` prefix prevents

macro-local labels from interfering with the local label mechanism as described in section 6.9. You should avoid defining your own labels in this form (the .@ prefix, the number, then another period) in case they interfere with macro-local labels.

4.3.3 Greedy Macro Parameters

Occasionally it is useful to define a macro which lumps its entire command into one parameter definition, possibly after extracting one or two smaller parameters from the front. An example might be a macro to write a text string to a file in MS-DOS, where you might want to be able to

```
writefile [filehandle], "hello, world", 13, 10
```

NASM allows you to define the last parameter of a macro to be *greedy*, meaning that if you invoke the macro with more parameters than it expects, all the spare parameters get lumped into the last defined one along with the separating commas. So if you code:

```
%macro writefile 2+
```

```
    jmp     %%endstr
%%str:    db     %2
%%endstr:
    mov     dx, %%str
    mov     cx, %%endstr-%%str
    mov     bx, %1
    mov     ah, 0x40
    int     0x21
```

```
%endmacro
```

then the example call to writefile above will work as expected: the text before the first comma, [filehandle], is used as the first macro parameter and expanded where %1 is referred to, and all the subsequent text is lumped into %2 and placed after the db.

The greedy nature of the macro is indicated in NASM by the use of the sign after the parameter count on the %macro line.

If you define a greedy macro, you are effectively telling NASM how it should expand the macro given *any* number of parameters from the actual number specified up to infinity; in this case, for example, NASM now knows what to do when it sees a call to writefile with 2, 3, 4 or more parameters. NASM will take this into account when overloading macros and will not allow you to define another form of writefile taking 4 parameters (for example).

Of course, the above macro could have been implemented as a non-greedy macro, in which case the call to it would have had to look like

```
writefile [filehandle], {"hello, world", 13, 10}
```

NASM provides both mechanisms for putting commas in macro parameters, and you choose which one you prefer for each macro definition.

See section 6.3.1 for a better way to write the above macro.

4.3.4 Macro Parameters Range

NASM allows you to expand parameters via a special construction {x:y} where x is the first parameter index and y is the last. Any index can be either negative or positive but must never

For example

```
%macro mpar 1-*
    db %{3:5}
```



```
%endmacro
```

```
mpar 1,2,3,4,5,6
```

expands to 3,4,5 range.

Even more, the parameters can be reversed so that

```
%macro mpar 1-*
```

```
    db %{5:3}
```

```
%endmacro
```

```
mpar 1,2,3,4,5,6
```

expands to 5,4,3 range.

But even this is not the last. The parameters can be addressed via negative indices. NASM will count them reversed. The ones who know Python may see the analogue here.

```
%macro mpar 1-*
```

```
    db %{-1:-3}
```

```
%endmacro
```

```
mpar 1,2,3,4,5,6
```

expands to 6,5,4 range.

Note that NASM uses comma to separate parameters being expanded.

By the way, here is a trick you might use: the index %{-1:-1} which gives you the last argument passed to a macro.

4.3.5 Default Macro Parameters

NASM also allows you to define a multi-line macro with a *range* of allowable parameter counts. If you do this, you can specify defaults for omitted parameters. So, for example:

```
%macro die 0-1 "Painful program death has occurred."
```

```
    writefile 2,%1
```

```
    mov     ax,0x4c01
```

```
    int     0x21
```

```
%endmacro
```

This macro (which makes use of the `writefile` macro defined in section 4.3.3) can be called with an explicit error message which will display the error output stream before exiting, or it can be called with no parameters, in which case it will use the default error message supplied in `stderr`.

In general, you supply a minimum and maximum number of parameters for a macro of this type; the minimum number of parameters are then required in the macro call, and they you provide defaults for the optional ones. So if a macro definition began with the line

```
%macro foobar 1-3 eax,[ebx+2]
```

then it could be called with between one and three parameters, and `%1` would always be taken from the macro call. `%2`, if not specified by the macro call, would default to `eax`, and `%3` if not specified would default to `[ebx+2]`.

You can provide extra information to a macro by providing too many default parameters.

```
%macro quux 1 something
```

This will trigger a warning by default, see section 2.1.2 for more information. When `quux` is invoked it receives not one but two parameters, something can be referred to as `%2`. The difference between passing something this way and writing something in the macro body is that with this way something is evaluated when the macro is defined, not when it is expanded.

You may omit parameter defaults from the macro definition, in which case the parameter default is taken to be blank. This can be useful for a macro which takes a variable number of parameters, since the `%0` token (see section 4.3.6) allows you to determine how many parameters were really passed to the macro call.

This defaulting mechanism can be combined with the greedy-parameter mechanism; so the `die` macro above could be made more powerful and more useful by changing the first line of the definition to

```
%macro die 0-1+ "Painful program death has occurred.",13,10
```

The maximum parameter count can be infinite, denoted by `*`. In this case, of course, it is impossible to provide a *full* set of default parameters. Examples of this usage are shown in section

4.3.6 `%0`: Macro Parameter Counter

The parameter reference `%0` will return a numeric constant giving the number of parameters received, that is, if `%0` is the first or the last parameter `%0` is mostly useful for a macro that takes a variable number of parameters. It can be used as an argument to `%rep` (see section 4.5) in order to iterate through all the parameters of a macro. Examples are given in section 4.3.8.

4.3.7 `%00`: Label Preceding Macro

`%00` will return the label preceding the macro invocation, if any. The label must be on the same line as the macro invocation, may be a local label (see section 3.9), and need not end in a

4.3.8 `%rotate`: Rotating Macro Parameters

Unix shell programmers will be familiar with the `shift` shell command, which allows the arguments passed to a shell script (referred to as `$1`, `$2` and so on) to be moved left by one place, so that the argument previously referenced as `$2` becomes available as `$1`, and the argument previously referenced as `$1` is no longer available at all.

NASM provides a similar mechanism, in the form of `%rotate`. As its name suggests, it differs from the Unix `shift` in that no parameters are lost: parameters rotated off the left end of the argument list reappear on the right, and vice versa.

`%rotate` is invoked with a single numeric argument (which may be an expression). The macro parameters are rotated to the left by that many places. If the argument to `%rotate` is negative, the macro parameters are rotated to the right.

So a pair of macros to save and restore a set of registers might work as follows:

```
%macro multipush 1-*
```

```
    %rep    %0
        push    %1
    %rotate 1
%endrep
```

```
%endmacro
```

This macro invokes the `USH` instruction on each of its arguments in turn, from left to right. It begins by pushing its first argument, `%1`, then invokes `%rotate` to move all the arguments one place to the left, so that the original second argument is now available as `$1`. Repeating this procedure as many times as

there were arguments (achieved by supplying `%0` as the argument to `%rep`) causes each argument in turn to be pushed.

Note also the use of `%a` as the maximum parameter count, indicating that there is no upper limit to the number of parameters you may supply to the `multipush` macro.

It would be convenient, when using this macro, to have a POP equivalent, which *didn't* require the arguments to be given in reverse order. Ideally, you would write the `multipush` macro call, then cut-and-paste the line to where the pop needed to be done, and change the name of the called macro to `multipop`, and the macro would take care of popping the registers in the opposite order from the one in which they were pushed.

This can be done by the following definition:

```
%macro multipop 1-*

    %rep %0
    %rotate -1
        pop    %1
    %endrep

%endmacro
```

This macro begins by rotating its arguments one place to the *right*, so that the original *last* argument appears as `%1`. This is the popped argument, and the arguments are rotated right again, so the second-to-last argument becomes `%1`. Thus the arguments are iterated through in reverse order.

4.3.9 Concatenating Macro Parameters

NASM can concatenate macro parameters and macro indirect instruction constructs onto other text surrounding them. This allows you to declare a family of symbols, for example, in a macro definition. If, for example, you wanted to generate a table of key codes along with offsets into the table, you could code something like

```
%macro keytab_entry 2

    keypos%1    equ    $-keytab
                db     %2

%endmacro

keytab:
    keytab_entry F1,128+1
    keytab_entry F2,128+2
    keytab_entry Return,13
```

which would expand to

```
keytab:
keyposF1      equ    $-keytab
              db     128+1
keyposF2      equ    $-keytab
              db     128+2
keyposReturn  equ    $-keytab
              db     13
```

You can just as easily concatenate text on to the other end of a macro parameter, by

If you need to append a *digit* macro parameter, for example defining labels `foo` and `foo2` when passed the parameter `foo`, you can't code `%1` because that would be taken as the eleventh macro parameter. Instead, you must code `&{1}1`, which will separate the first (giving the number of the macro parameter) from the second (literal text to be concatenated to the parameter).

This concatenation can also be applied to the preprocessor in-line objects, such as macro-local label (section 4.3.2) and context-local label (section 4.7.2). To avoid ambiguities, syntax can be resolved by enclosing everything after the sign and before the literal text in braces: `&{%foo}bar` concatenates the text `bar` to the end of the real name of the macro-local label `%foo`. (This is unnecessary, since the form `NASM` uses for the real names of macro-local labels means that the two usages `&{%foo}bar` and `%foo`bar would both expand to the same thing anyway, nevertheless, the capability is there.)

The in-line macro `direction` construct `%[...]` (section 4.1.3) behaves the same way as macro parameters for the purpose of concatenation.

See also the `%+` operator, section 4.1.4.

4.3.10 Condition Codes as Macro Parameters

`NASM` may give special treatment to a macro parameter which contains a condition code. For a start, you can refer to the macro parameter by means of the alternative syntax `%+1`, which informs `NASM` that this macro parameter is supposed to contain a condition code, and will cause the preprocessor to report an error message if the macro is called with a parameter which is *not* a valid

For more usefully, though, you can refer to the macro parameter by means of `%-1`, which `NASM` will expand to the *inverse* condition code. So the `ret` macro defined in section 4.3.2 can be replaced by a general conditional-return macro like this:

```
%macro    retc 1

            j%-1    %%skip
            ret
%%skip:

%endmacro
```

This macro can now be invoked using calls like `retc je`, which will cause the conditional-jump instruction in the macro expansion to come out as `JE`, or `retc po` which will make the

The `+macro-parameter` reference is quite happy to interpret the arguments `$X` and `!CX` as valid condition codes, however, `%-` will report an error if passed either of these, because an inverse condition code exists.

4.3.11 Disabling Listing Expansion

When `NASM` is generating a listing file from your program, it will generally expand multi-line macros by means of writing the macro call and then the listing of the expansion. This allows you to see which instructions in the macro expansion are generating what code, however for some macros this clutters the listing up unnecessarily.

`NASM` therefore provides the `nolist` qualifier which you can include in a macro definition to inhibit the expansion of the macro in the listing file. The `nolist` qualifier comes directly after the number of parameters, like this:

```
%macro foo 1.nolist
```

Or like this:

```
%macro bar 1-5+.nolist a,b,c,d,e,f,g,h
```

4.3.12 Undefined Multi-Line Macros: %unmacro

Multi-line macros can be removed with the %unmacro directive. Unlike the %undef directive, however, %unmacro takes an argument specification and will only remove exact matches with that argument specification.

For example:

```
%macro foo 1-3
    ; Do something
%endmacro
%unmacro foo 1-3
```

removes the previously defined macro foo, but

```
%macro bar 1-3
    ; Do something
%endmacro
%unmacro bar 1
```

does *not* remove the macro bar, since the argument specification does not match exactly.

4.4 Conditional Assembly

Similarly to the preprocessor, NASM allows sections of source files to be assembled only if certain conditions are met. The general syntax of this feature looks like this:

```
%if<condition>
    ; some code which only appears if <condition> is met
%elif<condition2>
    ; only appears if <condition> is not met but <condition2> is
%else
    ; this appears if neither <condition> nor <condition2> was met
%endif
```

The inverse forms %ifn and %elifn are also supported.

The %else clause is optional, as is the %elif clause. You can have more than one %elif clause as well.

There are a number of variants of the %if directive. Each has its corresponding %elif, %ifn, and %elifn directives; for example, the equivalent to the %if directive is %elifdef, %ifndef, and %elifndef.

4.4.1 %ifdef: Testing Single-Line Macro Existence

Beginning a conditional-assembly block with the %ifdef MACRO will assemble the subsequent code if, and only if, a single-line macro called MACRO is defined. If not, then the %elif and %else blocks (if any) will be processed instead.

For example, when debugging a program, you might want to write code such as

```
    ; perform some function
%ifdef DEBUG
    writefile 2, "Function performed successfully", 13, 10
%endif
    ; go and do something else
```

Then you could use the command-line option -dDEBUG to create a version of the program which produced debugging messages, and remove the option to generate the final release version of the program.

You can test for a macro *not* being defined by using `%ifndef` instead of `%ifndef`. You can also test for macro definitions in `%elif` blocks by using `%elifdef` and `%elifndef`.

4.4.2 %ifmacro: Testing Multi-Line Macro Existence

The `%ifmacro` directive operates in the same way as the `%ifdef` directive, except that it checks for the existence of a multi-line macro.

For example, you may be working with a large project and not have control over the macro library. You may want to create a macro with a name it doesn't already exist, and another name if one with that name does exist.

The `%ifmacro` is considered true if defining a macro with the given name and number of arguments would cause a definitions conflict. For example:

```
%ifmacro MyMacro 1-3

    %error "MyMacro 1-3" causes a conflict with an existing macro.

%else

    %macro MyMacro 1-3

        ; insert code to define the macro

    %endmacro

%endif
```

This will create the macro "MyMacro 1-3" if a macro already exists which would conflict with it and emits a warning if there would be a definition conflict.

You can test for the macro not existing by using the `%ifnmacro` instead of `%ifmacro`. Additional tests can be performed in `%elif` blocks by using `%elifmacro` and `%elifnmacro`.

4.4.3 %ifctx: Testing the Context Stack

The conditional-assembly construct `%ifctx` will cause the subsequent code to be assembled and only if the context of the preprocessor's context stack has the same name as one of the arguments. As with `%ifdef`, the inverse and `%elif` forms `%ifnctx`, `%elifctx` and `%elifnctx` are also supported.

For more details of the context stack, see section 4.7. For a sample use of `%ifctx`,

4.4.4 %if: Testing Arbitrary Numeric Expressions

The conditional-assembly construct `%if` will cause the subsequent code to be assembled and only if the value of the numeric expression is non-zero. An example of the use of this feature is in deciding when to break out of a `%rep` preprocessor loop: see section 4.5 for a detailed example.

The expression given to `%if`, and its counterpart `%elif`, is a critical expression (see

`%if` extends the normal NASM expressions syntax by providing a set of relational operators which are not normally available in expressions. The operators `<`, `>`, `<=`, `>=` and `=` test equality, less-than, greater-than, less-or-equal, greater-or-equal and not-equal respectively. The like forms `and` are supported as alternative forms `and`. In addition, low-priority logical operators `&`, `^` and `|` are provided, supplying logical AND, logical XOR and logical OR. These work like the logical operators (although the logical XOR), in that they always return either 0 or 1, and treat any non-zero input as 1 (so that `1^1`, for example, returns 0 if exactly one of its inputs is zero, and 1 otherwise). The relational operators also return 1 for true and 0 for false.

Like other `%if` constructs, `%if` has a counterpart `%elif`, and negative forms `%ifn` and

4.4.5 `%ifidn` and `%ifidni`: Testing Exact Text Identity

The construct `%ifidn text1, text2` will cause the subsequent code to be assembled ~~and only if~~ `text1` and `text2`, after expanding single-line macros, are identical pieces of text. Difference in white space are not counted.

`%ifidni` is similar to `%ifidn`, but is case-insensitive.

For example, the following macro pushes a register number on the stack and allows you to treat IP as a real register:

```
%macro pushparam 1

    %ifidni %1, ip
        call    %%label
    %%label:
    %else
        push    %1
    %endif

%endmacro
```

Like other `%if` constructs, `%ifidn` has counterpart `%elifidn`, and negative forms `%ifnidn` and `%elifnidn`. Similarly, `%ifidni` has counterparts `%elifidni`, `%ifnidni` and `%elifnidni`.

4.4.6 `%ifid`, `%ifnum`, `%ifstr`: Testing Token Types

Some macros will want to perform different tasks depending on whether they are passed a number, a string, or an identifier. For example, a string output macro might want to be able to cope with being passed either a string constant or a pointer to an existing string.

The conditional assembly construct `%ifid` taking one parameter (which may be blank) assembles the subsequent code ~~and only if~~ the first token in the parameter exists and is an identifier. `%ifnum` works similarly, but tests for the token being a numeric constant; `%ifstr` tests for

For example, the `writefile` macro defined in section 4.3.3 can be extended to take advantage of `%ifstr` in the following fashion:

```
%macro writefile 2-3+

    %ifstr %2
        jmp    %%endstr
    %if %0 = 3
        %%str:  db    %2,%3
    %else
        %%str:  db    %2
    %endif
    %%endstr:  mov    dx, %%str
               mov    cx, %%endstr-%%str
    %else
               mov    dx, %2
               mov    cx, %3
    %endif

               mov    bx, %1
               mov    ah, 0x40
               int     0x21
```

```
%endmacro
```

Then the `writefile` macro can cope with being called in either of the following two ways:

```
writefile [file], strpointer, length
writefile [file], "hello", 13, 10
```

In the first, `strpointer` is used as the address of a already-declared string, and `length` is used as its length; in the second, a string is given to the macro, which therefore declares itself and works out the address and length for itself.

Note the use of `%if` inside the `%ifstr`: this is to detect whether the macro was passed two arguments (so the string would be a single string constant, and `db %2` would be adequate) or more (in which case, all but the first two would be lumped together into `%3`, and `db %2,%3` would be required).

The usual `%elif...`, `%ifn...`, and `%elifn...` versions exist for each of `%ifid`, `%ifnum`, and `%ifstr`.

4.4.7 %iftoken: Test for a Single Token

Some macros will want to do different things depending on if it's passed a single token (e.g. `past` to something else using `+`) versus a multi-token sequence.

The conditional assembly construct `%iftoken` assembles the subsequent code if and only if the expanded parameters consist of exactly one token, possibly surrounded by whitespace.

For example:

```
%iftoken 1
```

will assemble the subsequent code, but

```
%iftoken -1
```

will not, since `-1` contains two tokens: the unary minus operator `-`, and the number `1`.

The usual `%eliftoken`, `%ifntoken`, and `%elifntoken` variants are also provided.

4.4.8 %ifempty: Test for Empty Expansion

The conditional assembly construct `%ifempty` assembles the subsequent code if and only if the expanded parameters do not contain any tokens at all, whitespace excepted.

The usual `%elifempty`, `%ifnempty`, and `%elifnempty` variants are also provided.

4.4.9 %ifenv: Test If Environment Variable Exists

The conditional assembly construct `%ifenv` assembles the subsequent code if and only if the environment variable referenced by the `!variable` directive exists.

The usual `%elifenv`, `%ifnenv`, and `%elifnenv` variants are also provided.

Just as for `!variable`, the arguments should be written as a string if it contains characters that would not be legal in an identifier. See section 4.10.2.

4.5 Preprocessor Loops: %rep

NASM's `$` prefix, though useful, cannot be used to invoke a multi-line macro multiple times, because it's processed by NASM after macros have already been expanded. Therefore NASM provides another form of loop, this time at the preprocessor level: `%rep`.

The directives `%rep` and `%endrep` (`%rep` takes a numeric argument, which can be an expression; `%endrep` takes no arguments) can be used to enclose a chunk of code, which is then replicated as many times as specified by the preprocessor:


```

%assign i 0
%rep 64
    inc    word [table+2*i]
%assign i i+1
%endrep

```

This will generate a sequence of 64 INC instructions, incrementing every word of memory from [table] to [table+126].

For more complex termination conditions, or to break out of a repeat loop partway along, you can use the %exitrep directive to terminate the loop, like this:

```

fibonacci:
%assign i 0
%assign j 1
%rep 100
%if j > 65535
    %exitrep
%endif

    dw j
%assign k j+i
%assign i j
%assign j k
%endrep

```

```

fib_number equ ($-fibonacci)/2

```

This produces a list of all the Fibonacci numbers that will fit in 16 bits. Note that a maximum repeat count must still be given to %rep. This is to prevent the possibility of NASM getting into an infinite loop in the preprocessor which on multitasking multi-user systems would typically cause all the system memory to be gradually used up and other applications to start crashing.

Note that a maximum repeat count is limited by 6-bit number, though it is hardly possible that you ever need anything bigger.

4.6 Source Files and Dependencies

These commands allow you to split your sources into multiple files.

4.6.1 %include: Including Other Files

Using %include again, very similar syntax to the preprocessor NASM's preprocessor lets you include other source files into your code. This is done by the use of the %include directive

```

#include "macros.mac"

```

will include the contents of the file macros.mac into the source file containing the %include directive.

Include files are searched for in the current directory (the directory you're in when you run NASM) as opposed to the location of the NASM executable or the location of the source file) plus any directories specified on the NASM command line using the -i option.

The standard idiom for preventing a file being included more than once is just as applicable in NASM: if the file macros.mac has the form

```

%ifndef MACROS_MAC
    %define MACROS_MAC
    ; now define some macros
%endif

```

then including the file more than once will not cause errors, because the second time the file is included nothing will happen because the macro `MACROS_MAC` will already be defined. You can force a file to be included even if there is a `%include` directive that explicitly includes it by using the `-p` option on the NASM command line (see section 2.1.18).

4.6.2 `%pathsearch`: Search the Include Path

The `%pathsearch` directive takes a single-line macro name and filename and declares or redefines the specified single-line macro to be the include-path-resolved version of the filename, if the file exists (otherwise, it is passed unchanged.)

For example,

```
%pathsearch MyFoo "foo.bin"
```

... with `-Ibins/` in the include path may end up defining the macro `MyFoo` to be `"bins/`

4.6.3 `%depend`: Add Dependent Files

The `%depend` directive takes a filename and adds it to the list of files to be emitted as dependency generation when the `-M` options and its relatives (see section 2.1.4) are used. It pr

This is generally used in conjunction with `%pathsearch`. For example, a simplified version of the standard macro wrapper for the `INCBIN` directive looks like:

```
%macro incbin 1-2+ 0
%pathsearch dep %1
%depend dep
    incbin dep,%2
%endmacro
```

This first resolves the location of the file into the macro `dep`, then adds it to the dependency lists and finally issues the assembler-level `INCBIN` directive.

4.6.4 `%use`: Include Standard Macro Package

The `%use` directive is similar to `%include` but rather than including the contents of a file, it includes a named standard macro package. The standard macro packages are part of NASM and are described in chapter 5.

Unlike the `%include` directive, package names for the `%use` directive do not require quotes, but quotes are permitted. In NASM 2.0 and 2.03, the unquoted form would be macro-expanded, this is no longer true. Thus, the following lines are equivalent:

```
%use altreg
%use 'altreg'
```

Standard macro packages are protected from multiple inclusion. When a standard macro package is used, a testable single-line macro of the form `__USE_package` is also defined, see s

4.7 The Context Stack

Having a label share a local macro definition is sometimes not quite powerful enough; sometimes you want to be able to share labels between several macro calls. An example might be `REPEAT...UNTIL` loop, in which the expansion of the `REPEAT` macro would need to be able to refer to a label which the `UNTIL` macro had defined. However, for such a macro you would also want to be able to nest these loops.

NASM provides this level of power by means of a *context stack*. The preprocessor maintains a stack of *contexts*, each of which is characterized by name. You add a new context to the stack using the `%push`

directive and remove using `%pop`. You can define labels that are local to a particular context on the stack.

4.7.1 `%push` and `%pop`: Creating and Removing Contexts

The `%push` directive is used to create a new context and place it on the top of the context stack. `%push` takes an optional argument, which is the name of the context. For example:

```
%push    foobar
```

This pushes a new context called `foobar` on the stack. You can have several contexts on the stack with the same name; they can still be distinguished. If no name is given, the context is unnamed (this is normally used when both the `%push` and the `%pop` are inside a single macro definition).

The directive `%pop`, taking an optional argument, removes the top context from the context stack and destroys it, along with any label associated with it. If an argument is given, it must match the name of the current context, otherwise it will issue an error.

4.7.2 Context-Local Labels

Just as the usage `%f` defines a label which is local to the particular macro call in which it is used, the usage `$$f` is used to define a label which is local to the context on the top of the context stack. So the REPEAT and UNTIL example given above could be implemented by means of:

```
%macro repeat 0

    %push    repeat
    %$begin:

%endmacro

%macro until 1

    j%-1     %$begin
    %pop

%endmacro
```

and invoked by means of, for example,

```
mov     cx,string
repeat
add     cx,3
scasb
until   e
```

which would scan every fourth byte of a string in search of the byte in AL.

If you need to define or access labels local to the context *below* the top one on the stack, you can use `$$$foo`, or `$$$$foo` for the context below that, and so on.

4.7.3 Context-Local Single-Line Macros

NASM also allows you to define single-line macros which are local to a particular context, in just the same way:

```
%define %$localmac 3
```

will define the single-line macro `%$localmac` to be local to the top context on the stack. Of course, after a subsequent `%push`, it can then still be accessed by the name `$$$localmac`.

4.7.4 Context Fall-Through Lookup (*deprecated*)

Context fall-through lookup (automatic searching of outer contexts) is a feature that was added in NASM version 0.98.03. Unfortunately, this feature is unintuitive and a result of buggy code that would have otherwise been prevented by NASM's error reporting. As a result, this feature has been *deprecated*. NASM version 2.0 will issue a warning if this *deprecated* feature is detected. Starting with NASM version 2.10, usage of this *deprecated* feature will simply result in an *expression syntax error*.

An example usage of this *deprecated* feature follows:

```
%macro ctxthru 0
%push ctx1
    %assign %%external 1
        %push ctx2
            %assign %%internal 1
            mov eax, %%external
            mov eax, %%internal
        %pop
    %pop
%endmacro
```

As demonstrated, %%external is being defined in the ctx1 context and referenced within the ctx2 context. With context fall-through lookup, referencing an undefined context-local macro like this implicitly searches through all outer contexts until a match is made or isn't found. Any context as a result, %%external referenced within the ctx2 context would implicitly use %%external as defined in ctx1. Most people would expect NASM to issue an error in this situation because %%external was never defined within ctx2 and also isn't qualified with the proper context depth, %%%external.

Here is a revision of the above example with proper context depth:

```
%macro ctxthru 0
%push ctx1
    %assign %%external 1
        %push ctx2
            %assign %%internal 1
            mov eax, %%%external
            mov eax, %%%internal
        %pop
    %pop
%endmacro
```

As demonstrated, %%external is still being defined in the ctx1 context and referenced within the ctx2 context. However, the reference to %%external within ctx2 has been fully qualified with the proper context depth, %%%external, and thus is no longer ambiguous, unintuitive or error-prone.

4.7.5 %repl: Renaming a Context

If you need to change the name of the top context on the stack (in order, for example, to have it respond differently to %ifctx), you can execute %pop followed by %push, but this will have the side effect of destroying all context-local labels and macros associated with the context that was just popped.

NASM provides the directive %repl, which *replaces* a context with a different name, without touching the associated macros and labels. So you could replace the destructive code

```
%pop
%push    newname
```

with the non-destructive version `%repl newname`.

4.7.6 Example Use of the Context Stack: Block IFs

This example makes use of almost all the context-stack features, including the conditional-assembly construct `%ifctx`, to implement a block IF statement as a set of macros.

```
%macro if 1

    %push if
    j%-1  %$ifnot

%endmacro

%macro else 0

    %ifctx if
        %repl  else
        jmp    %$ifend
        %$ifnot:
    %else
        %error "expected 'if' before 'else'"
    %endif

%endmacro

%macro endif 0

    %ifctx if
        %$ifnot:
        %pop
    %elifctx  else
        %$ifend:
        %pop
    %else
        %error "expected 'if' or 'else' before 'endif'"
    %endif

%endmacro
```

This code is more robust than the `REPEAT` and `UNTIL` macros given in section 4.7.2, because it uses conditional assembly to check that the macros are issued in the right order (for example, not calling `endif` before `if`) and issues a `%error` if they're not.

In addition, the `endif` macro has to be able to cope with the two distinct cases of either directly following `if` or following `else`. It achieves this again by using conditional assembly to do different things depending on whether the context on top of the stack is `if` or `else`.

The `else` macro has to preserve the context on the stack, in order to have the `%$ifnot` referred to by the `if` macro be the same as the one defined by the `endif` macro, but has to change the context's name so that `endif` will know there was an intervening `else`. It does this by the use of

A sample usage of these macros might look like:

```
    cmp     ax,bx

    if ae
```

```

        cmp     bx,cx

        if ae
            mov     ax,cx
        else
            mov     ax,bx
        endif

    else
        cmp     ax,cx

        if ae
            mov     ax,cx
        endif

    endif

```

The `lock-if` macro handles nesting quite happily, by means of pushing another context describing the inner if, on top of the one describing the outer if; thus `else` and `endif` always refer to the last unmatched if or else.

4.8 Stack Relative Preprocessor Directives

The following preprocessor directives provide ways to refer to local variables allocated on the stack.

- `%arg` (see section 4.8.1)
- `%stacksize` (see section 4.8.2)
- `%local` (see section 4.8.3)

4.8.1 `%arg` Directive

The `%arg` directive is used to simplify the handling of parameters passed on the stack. Stack based parameter passing is used by many high level languages, including C, C++ and Pascal.

While NASM has macros which attempt to duplicate this functionality (see section 8.4.5) the syntax is not particularly convenient to use and is not TASM compatible. Here is an example which shows the use of `%arg` without any external macros:

some_function:

```

    %push     mycontext           ; save the current context
    %stacksize large             ; tell NASM to use bp
    %arg      i:word, j_ptr:word

    mov     ax,[i]
    mov     bx,[j_ptr]
    add     ax,[bx]
    ret

    %pop                                ; restore original context

```

This is similar to the procedure defined in section 8.4.5 and adds the value in the value pointed to by `j_ptr` and returns the sum in the `ax` register. See section 4.7 for an explanation of `push` and `pop` and the use of context stacks.

4.8.2 %stacksize Directive

The `%stacksize` directive is used in conjunction with the `%arg` (see section 4.8.1) and the `%local` (see section 4.8.3) directives. It tells NASM the default size to use for subsequent `%arg` and `%local` directives. The `%stacksize` directive takes one required argument which is one of `flat`, `flat64`, `large` or `small`.

```
%stacksize flat
```

This form causes NASM to use stack-based parameter addressing relative to `ebp` and assumes that a `near` form of `call` was used to get to this label (i.e. that `eip` is on the stack).

```
%stacksize flat64
```

This form causes NASM to use stack-based parameter addressing relative to `rbp` and assumes that a `near` form of `call` was used to get to this label (i.e. that `rip` is on the stack).

```
%stacksize large
```

This form uses `bp` to do stack-based parameter addressing and assumes that a `far` form of `call` was used to get to this address (i.e. that `ip` and `cs` are on the stack).

```
%stacksize small
```

This form also uses `bp` to address stack parameters, but it is different from `large` because it also assumes that the value of `bp` is pushed onto the stack (i.e. it expects an `ENTER` instruction). In other words, it expects that `bp`, `ip` and `cs` are on the top of the stack, underneath any local space which may have been allocated by `ENTER`. This form is probably most useful when used in combination with the `%local` directive (see section 4.8.3).

4.8.3 %local Directive

The `%local` directive is used to simplify these local temporary stack variables allocated in stack frame. Automatic local variables are an example of this kind of variable. The `%local` directive is most useful when used with the `%stacksize` (see section 4.8.2) and is also compatible with the `%arg` directive (see section 4.8.1). It allows simplified reference to variables on the stack which have been allocated typically by using the `ENTER` instruction. An example of its use is the following:

```
silly_swap:
```

```
%push mycontext          ; save the current context
%stacksize small          ; tell NASM to use bp
%assign %$localsize 0      ; see text for explanation
%local old_ax:word, old_dx:word
```

```
    enter    %$localsize,0  ; see text for explanation
    mov     [old_ax],ax     ; swap ax & bx
    mov     [old_dx],dx     ; and swap dx & cx
    mov     ax,bx
    mov     dx,cx
    mov     bx,[old_ax]
    mov     cx,[old_dx]
    leave   ; restore old bp
    ret     ;
```

```
%pop                      ; restore original context
```

The `%$localsize` variable is used internally by the `%local` directive and *must* be defined within the current context before the `%local` directive is used. Failure to do so will result in an expression

syntax error for each %local variable declared. It then may be used in the construction of an appropriately sized ENTER instruction as shown in the example.

4.9 Reporting User-Defined Errors: %error, %warning, %fatal

The preprocessor directive `%error` will cause NASM to report an error if it occurs in assembled code. So if the user is going to try assembly source files, you can ensure that they define the right macros by means of code like this:

```
%ifdef F1
    ; do some setup
%elifdef F2
    ; do some different setup
%else
    %error "Neither F1 nor F2 was defined."
%endif
```

Then any user who fails to understand the way your code is supposed to be assembled will be quickly warned off the mistake, rather than having to wait until the program crashes or being unsure and then not knowing what went wrong.

Similarly, `%warning` issues a warning, but allows assembly to continue:

```
%ifdef F1
    ; do some setup
%elifdef F2
    ; do some different setup
%else
    %warning "Neither F1 nor F2 was defined, assuming F1."
    %define F1
%endif
```

`%error` and `%warning` are issued only on the final assembly pass. This makes them safe to use in conjunction with tests that depend on symbol values.

`%fatal` terminates assembly immediately regardless of pass. This is useful when there is a point in continuing the assembly further and doing so is likely just going to cause a few confusing error messages.

It is optional for the message string after `%error`, `%warning`, or `%fatal` to be quoted. If it is *not*, then single-line macros are expanded in it, which can be used to display more information to the user. For example:

```
%if foo > 64
    %assign foo_over foo-64
    %error foo is foo_over bytes too large
%endif
```

4.10 Other Preprocessor Directives

NASM has a preprocessor directive which allows access to information from external sources. Currently they include:

- `%line` enables NASM to correctly handle the output of another preprocessor (see section 4.10.1).
- `!enable` enables NASM to read the value of a foreign environment variable, which can then be used in your program (see section 4.10.2).

4.10.1 %line Directive

The `%line` directive is used to notify NASM that the input line corresponds to a specific line number in another file. Typically, this is the file would be the original source file with the current NASM input being the output of the pre-processor. The `%line` directive allows NASM to output messages which indicate the line number of the original source file, instead of the file that is being read.

This preprocessor directive is not generally of use to programmers, but may be of interest to preprocessor authors. The usage of the `%line` preprocessor directive is as follows:

```
%line nnn[+mmm] [filename]
```

In this directive, `nnn` identifies the line of the original source file which this line corresponds to. `mmm` is an optional parameter which specifies a line increment value; each line of the input file read is considered to correspond to `mmm` lines of the original source file. Finally, `filename` is an optional parameter which specifies the file name of the original source file.

After reading a `%line` preprocessor directive, NASM will report all file and line numbers relative to the values specified therein.

4.10.2 %!variable: Read an Environment Variable.

The `%!variable` directive makes it possible to read the value of an environment variable at assembly time. This could, for example, be used to store the contents of an environment variable into a string, which could be used at some other point in your code.

For example, suppose that you have an environment variable `FOO`, and you want the contents of `FOO` to be embedded in your program as a quoted string. You could do that as follows:

```
%defstr FOO          %!FOO
```

See section 4.1.8 for notes on the `%defstr` directive.

If the name of the environment variable contains non-identifier characters, you can set string quotes to surround the name of the variable, for example:

```
%defstr C_colon      %!'C:'
```

4.11 Standard Macros

NASM defines a set of standard macros, which are already defined when it starts to process any source file. If you really need a program to be assembled with no pre-defined macros, you can use the `%clean` directive to empty the preprocessor of everything but context-local preprocessor variables and single-line macros.

Most user-level assembler directives (see chapter 6) are implemented as macros which invoke primitive directives; these are described in chapter 6. The set of the standard macros is described here.

4.11.1 NASM Version Macros

The single-line macros `__NASM_MAJOR__`, `__NASM_MINOR__`, `__NASM_SUBMINOR__` and `__NASM_PATCHLEVEL__` expand to the major, minor, subminor and patch level parts of the version number of NASM being used. So, under NASM 0.98.32, for example, `__NASM_MAJOR__` would be defined to be 0, `__NASM_MINOR__` would be defined as 98, `__NASM_SUBMINOR__` would be defined to 32, and `__NASM_PATCHLEVEL__` would be defined as 1.

Additionally, the macro `__NASM_SNAPSHOT__` is defined for automatically generated snapshot releases *only*.

4.11.2 `__NASM_VERSION_ID__`: NASM Version ID

The single-line macro `__NASM_VERSION_ID__` expands to a word integer representing the full version number of the version of NASM being used. The value is the equivalent to `__NASM_MAJOR__`, `__NASM_MINOR__`, `__NASM_SUBMINOR__` and `__NASM_PATCHLEVEL__` concatenated to produce a single doubleword. Hence, for 0.98.32p1, the returned number would be equivalent to

```
        dd      0x00622001

or

        db      1,32,98,0
```

Note that the above lines are generated exactly the same code, the second line is used just to give an indication of the order that the separate values will be present in memory.

4.11.3 `__NASM_VER__`: NASM Version string

The single-line macro `__NASM_VER__` expands to a string which defines the version number of NASM being used. So, under NASM 0.98.32 for example,

```
        db      __NASM_VER__

would expand to

        db      "0.98.32"
```

4.11.4 `__FILE__` and `__LINE__`: File Name and Line Number

Like the preprocessor, NASM allows the user to find out the file name and line number containing the current instruction. The macro `__FILE__` expands to a string constant giving the name of the current input file (which may change through the course of assembly if include directives are used) and `__LINE__` expands to a numeric constant giving the current line number in the input file.

These macros could be used, for example, to communicate debugging information to a macro, since invoking `__LINE__` inside a macro definition (either single-line or multi-line) will return the line number of the macro *call*, rather than the *definition*. So to determine where in a piece of code a crash is occurring, for example, one could write a routine still here, which is passed a line number in EAX and outputs something like 'line 155: still here'. You could then write a macro

```
%macro  notdeadyet 0

        push    eax
        mov     eax, __LINE__
        call    stillhere
        pop     eax

%endmacro
```

and then pepper your code with calls to `notdeadyet` until you find the crash point.

4.11.5 `__BITS__`: Current BITS Mode

The `__BITS__` standard macro is updated every time that the BITS mode is set using the `BITSXX` or `[BITSXX]` directive, where XX is a valid mode number of 16, 32 or 64. `__BITS__` receives the specified mode number and makes it globally available. This is a very useful feature for those who utilize mode-dependent macros.

4.11.6 `__OUTPUT_FORMAT__`: Current Output Format

The `__OUTPUT_FORMAT__` standard macro holds the current output format, as given by the `-f` option or NASM's default. Type `nasm -hf` for a list.

```
%ifidn __OUTPUT_FORMAT__, win32
%define NEWLINE 13, 10
%elifidn __OUTPUT_FORMAT__, elf32
%define NEWLINE 10
%endif
```

4.11.7 Assembly Date and Time Macros

NASM provides a variety of macros that represent the timestamp of the assembly session.

- The `__DATE__` and `__TIME__` macros give the assembly date and time as strings, in ISO 8601 format ("YYYY-MM-DD" and "HH:MM:SS", respectively.)
- The `__DATE_NUM__` and `__TIME_NUM__` macros give the assembly date and time in numeric form; in the format YYYYMMDD and HHMMSS respectively.
- The `__UTC_DATE__` and `__UTC_TIME__` macros give the assembly date and time in universal time (UTC) as strings, in ISO 8601 format ("YYYY-MM-DD" and "HH:MM:SS", respectively.) If the host platform doesn't provide UTC time, these macros are undefined.
- The `__UTC_DATE_NUM__` and `__UTC_TIME_NUM__` macros give the assembly date and time in universal time (UTC) in numeric form, in the format YYYYMMDD and HHMMSS respectively. If the host platform doesn't provide UTC time, these macros are undefined.
- The `__POSIX_TIME__` macro is defined as a number containing the number of seconds since the POSIX epoch, January 1, 1970 00:00:00 UTC, excluding any leap seconds. This is computed using UTC time if available on the host platform, otherwise it is computed using the local time.

All instances of time and date macros in the same assembly session produce consistent output. For example, in an assembly session started at 42 seconds after midnight on January 1, 2010 in Moscow (time zone UTC+3) the macros would have the following values, assuming of course a properly configured environment with a correct clock:

```
__DATE__           "2010-01-01"
__TIME__           "00:00:42"
__DATE_NUM__       20100101
__TIME_NUM__       000042
__UTC_DATE__       "2009-12-31"
__UTC_TIME__       "21:00:42"
__UTC_DATE_NUM__   20091231
__UTC_TIME_NUM__   210042
__POSIX_TIME__     1262293242
```

4.11.8 `__USE_package__`: Package Include Test

When a standard macro package (see chapter 5) is included with the `%include` directive (see section 4.6.4), a single-line macro of the form `__USE_package__` is automatically defined. This allows testing if a particular package is invoked or not.

For example, if the `altreg` package is included (see section 5.1), then the macro `__USE_ALTREG__` is defined.

4.11.9 `__PASS__`: Assembly Pass

The macro `__PASS__` is defined to be 0 on preparatory passes, and 2 on the final pass. In preprocess-only mode, it is set to 3, and when running only to generate dependencies (due to the `-M` or `-MG` option, see section 2.1.4) it is set to 0.

Avoid using this macro if at all possible. It is tremendously easy to generate very strange errors by misusing it, and the semantics may change in future versions of NASM.

4.11.10 STRUC and ENDSTRUC: Declaring Structure Data Types

Theorem NASM contains an intrinsic means of defining data structures; instead, the preprocessor is sufficiently powerful that data structures can be implemented as sets of macros. The macros `STRUC` and `ENDSTRUC` are used to define a structure data type.

`STRUC` takes one or two parameters. The first parameter is the name of the data type. The second, optional parameter is the base offset of the structure. The name of the data type is defined as a symbol with the value of the base offset, and the name of the data type with the suffix `_size` appended to it is defined as a `EQ` giving the size of the structure. Once `STRUC` has been issued, you are defining the structure and should define fields using the `BES` family of pseudo-instructions and then invoke `ENDSTRUC` to finish the definition.

For example, to define a structure called `mytype` containing a longword, a word, a byte, and a string of bytes, you might code

```
struc    mytype

    mt_long:    resd    1
    mt_word:    resw    1
    mt_byte:    resb    1
    mt_str:     resb    32

endstruc
```

The above code defines six symbols: `mt_long` as 0 (the offset from the beginning of a `mytype` structure to the longword field), `mt_word` as 4, `mt_byte` as 6, `mt_str` as 7, `mytype_size` as 9, and `mytype` itself as zero.

The reason why the structure type name is defined at zero by default is a side effect of following structure ~~to~~ work with the local label mechanism: if your structure members ~~end~~ have the same names in more than one structure, you can define the above structure like this:

```
struc mytype

    .long:      resd    1
    .word:      resw    1
    .byte:      resb    1
    .str:       resb    32

endstruc
```

This defines the offsets of the structure fields as `mytype.long`, `mytype.word`, `mytype.byte`, and `mytype.str`.

NASM, since it has *intrinsic* structure support, does not support any form of period notation to refer to the elements of a structure once you have one (except the above local-label notation). So code such as `mov ax, [mystruc.mt_word]` is not valid; `mt_word` is a constant just like any other constant, so the correct syntax is `mov ax, [mystruc+mt_word]` or `mov ax, [mystruc+mytype.word]`.

Sometimes you only have the address of the structure displaced by an offset. For example, consider this standard stack frame setup:

```
push ebp
mov ebp, esp
sub esp, 40
```

In this case, you could access an element by subtracting the offset:

```
mov [ebp - 40 + mytype.word], ax
```

However, if you do not want to repeat this offset, you can use -40 as a base offset:

```
struc mytype, -40
```

And access an element this way:

```
mov [ebp + mytype.word], ax
```

4.11.11 ISTRUC, AT and IEND: Declaring Instances of Structures

Having defined a structure type, the next thing you typically want to do is declare instances of that structure in your data segment. NASM provides an easy way to do this in the ISTRUC mechanism. To declare a structure of type mytype in a program, you code something like this:

```
mystruc:
    istruc mytype

        at mt_long, dd    123456
        at mt_word, dw    1024
        at mt_byte, db    'x'
        at mt_str,  db    'hello, world', 13, 10, 0

    iend
```

The function of the AT macro is to make use of the TIMES prefix to advance the assembly position to the correct point for the specified structure field, and then to declare the specified data. Therefore the structure fields must be declared in the same order as they were specified in the struct definition.

If the data in a structure field requires more than one source line to specify, the remaining source lines can easily come after the AT line. For example:

```
        at mt_str,  db    123,134,145,156,167,178,189
                                db    190,100,0
```

Depending on personal taste, you can also omit the code part of the AT line completely and start the structure field on the next line:

```
        at mt_str
                                db    'hello, world'
                                db    13,10,0
```

4.11.12 ALIGN and ALIGNB: Data Alignment

The ALIGN and ALIGNB macros provide a convenient way to align code or data on a word, longword, paragraph or the boundary. (Some assemblers call this directive EVEN.) The syntax of the ALIGN and ALIGNB macros is

```
align    4                ; align on 4-byte boundary
align    16               ; align on 16-byte boundary
align    8,db 0            ; pad with 0s rather than NOPs
align    4,resb 1          ; align to 4 in the BSS
alignb   4                ; equivalent to previous line
```

Both macros require their first argument to be a power of two; they both compute the number of additional bytes required to bring the length of the current section up to a multiple of that power of two, and then apply the TIMES prefix to their second argument to perform the alignment.

If the second argument is not specified, the default for ALIGN is NOP, and the default for ALIGNB is RESB. If the second argument is specified, the two macros are equivalent. Normally you can just use ALIGN in code and data sections and ALIGNB in BSS sections, and never need the second argument except for special purposes.

ALIGN and ALIGNB, being simple macros, perform no error checking: they cannot warn you if their first argument fails to be a power of two, or if the second argument generates more than one byte of code. In each of these cases they will silently do the wrong thing.

ALIGNB (or ALIGN with a second argument of RESB 1) can be used within structure definitions.

```
struct mytype2
```

```
    mt_byte:
        resb 1
        alignb 2
    mt_word:
        resw 1
        alignb 4
    mt_long:
        resd 1
    mt_str:
        resb 32
```

```
endstruct
```

This will ensure that the structure members are sensibly aligned relative to the base of the section.

A final caveat: ALIGN and ALIGNB work relative to the beginning of the section, not the beginning of the address space of the final executable. Aligning to a 6-byte boundary when the section you're in is only guaranteed to be aligned to a 4-byte boundary, for example, is a waste of effort. Again, NASM does not check that the section's alignment characteristics are sensible for the use of ALIGN.

Both ALIGN and ALIGNB do call SECTALIGN macro implicitly. See section 4.11.13 for details.

See also the smartalign standard macro package, section 5.2.

4.11.13 SECTALIGN: Section Alignment

The SECTALIGN macro provides a way to modify alignment attributes of output file sections. Unlike the align attribute (which is allowed at section definition only), the SECTALIGN macro may be used at any time.

For example the directive

```
SECTALIGN 16
```

sets the section alignment requirement to 16 bytes. Once increased, it cannot be decreased, the magnitude may grow only.

Note that ALIGN (see section 4.11.12) calls the SECTALIGN macro implicitly so the active section alignment requirement may be updated. This is the default behaviour, if for some reason you want the ALIGN to not call SECTALIGN at all use the directive

```
SECTALIGN OFF
```

It is still possible to turn it on again by

```
SECTALIGN ON
```

Chapter 5: Standard Macro Packages

The `use directive` (see section 4.6.4) includes one of the standard macro packages included with the NASM distribution and compiled into the NASM binary. It operates like the `include directive` (see section 4.6.1), but the included contents is provided by NASM itself.

The names of standard macro packages are case insensitive, and can be quoted or not.

5.1 `altreg`: Alternate Register Names

The `altreg` standard macro package provides alternate register names. It provides numeric register names for all registers (not just R8-R15), the Intel-defined aliases R8L-R15L for the low bytes of register (as opposed to the NASM/AMD standard names R8B-R15B), and the names R0H-R3H (by analogy with R0L-R3L) for AH, CH, DH, and BH.

Example use:

```
%use altreg

proc:
    mov r0l,r3h                ; mov al,bh
    ret
```

See also section 11.1.

5.2 `smartalign`: Smart ALIGN Macro

The `smartalign` standard macro package provides for an `ALIGN` macro which is more powerful than the default (and backwards-compatible) one (see section 4.11.12). When the `smartalign` package is enabled, when `ALIGN` is used without a second argument, NASM will generate a sequence of instructions more efficient than a series of `NOP`. Furthermore, if the padding exceeds a specific threshold, then NASM will generate a jump over the entire padding sequence.

The specific instructions generated can be controlled with the new `ALIGNMODE` macro. This macro takes two parameters: one mode and an optional jump threshold override. If for any reason you need to turn off the jump completely just set jump threshold value to 0 (or set it to `jmp`). The following modes are possible:

- `generic`: Works on all x86 CPUs and should have reasonable performance. The default jump threshold is 8. This is the default.
- `nop`: Pad out with `NOP` instructions. The only difference compared to the standard `ALIGN` macro is that NASM can still jump over a large padding area. The default jump threshold is 8.
- `k7`: Optimize for the AMD7 (Athlon/Altoh XP). These instructions should still work on all x86 CPUs. The default jump threshold is 16.
- `k8`: Optimize for the AMD8 (Opteron/Altoh 64). These instructions should still work on all x86 CPUs. The default jump threshold is 16.
- `p6`: Optimize for Intel CPUs. This uses the `NO` instructions first introduced in Pentium Pro. This is incompatible with all CPUs family, lower as well as some VIA CPUs and several virtualization solutions. The default jump threshold is 16.

The macro `__ALIGNMODE__` is defined to contain the current alignment mode. A number of other macros beginning with `__ALIGN_` are used internally by this macro package.

5.3 fp: Floating-point macros

This package contains the following floating-point convenience macros:

```
%define Inf          __Infinity__
%define NaN          __QNaN__
%define QNaN         __QNaN__
%define SNaN         __SNaN__

%define float8(x)    __float8__(x)
%define float16(x)   __float16__(x)
%define float32(x)   __float32__(x)
%define float64(x)   __float64__(x)
%define float80m(x)  __float80m__(x)
%define float80e(x)  __float80e__(x)
%define float128l(x) __float128l__(x)
%define float128h(x) __float128h__(x)
```

5.4 ifunc: Integer functions

This package contains a set of macros which implement integer functions. These are actually implemented as special operators, but are most conveniently accessed via this macro package.

The macros provided are:

5.4.1 Integer logarithms

These functions calculate the integer logarithm base 2 of their argument, considered an unsigned integer. The only difference between the functions is their respective behavior if their argument provided is not a power of two.

The function `ilog2e()` (alias `ilog2()`) generates an error if the argument is not a power of two.

The function `ilog2f()` rounds the argument down to the nearest power of two; if the argument is zero it returns zero.

The function `ilog2c()` rounds the argument up to the nearest power of two.

The functions `ilog2fw()` (alias `ilog2w()`) and `ilog2cw()` generate a warning if the argument is not a power of two, but otherwise behaves like `ilog2f()` and `ilog2c()`, respectively.

Chapter 6: Assembler Directives

NASM, though it attempts to avoid the bureaucracy of assemblers like MASM and TASM, is nevertheless forced to support a *few* directives. These are described in this chapter.

NASM's directives come in two types: *user-level* directives and *primitive* directives. Typically, each directive has a user-level form and a primitive form. In almost all cases, we recommend that users use the user-level forms of the directives, which are implemented as macros which call the

Primitive directives are enclosed in square brackets; user-level directives are not.

In addition to the universal directives described in this chapter, each object file format optionally supplies extra directives in order to control particular features of that file format. These *format-specific* directives are documented along with the formats that implement them, in chapter 7.

6.1 BITS: Specifying Target Processor Mode

The `BITS` directive specifies whether NASM should generate code designed to run on a processor operating in 16-bit mode, 32-bit mode or 64-bit mode. The syntax is `BITS XX`, where `XX`

In most cases, you should not need to use `BITS` explicitly. The `out`, `coff`, `elf`, `macho`, `win32` and `win64` object formats, which are designed to run on 32-bit or 64-bit operating systems, all cause NASM to select 32-bit or 64-bit mode, respectively, by default. The object format allows you to specify each segment you define as either `USE16` or `USE32`, and NASM will set its operating mode accordingly, so the use of the `BITS` directive is once again unnecessary.

The most likely reason for using the `BITS` directive is to write 32-bit or 64-bit code in a binary file; this is because the default output format is 16-bit mode in anticipation of being used most frequently to write DOS `.COM` programs, DOS `.SYS` device drivers and boot loader software.

The `BITS` directive can also be used to generate code for a different mode than the standard one for the output format.

You do *not* need to specify `BITS32` merely in order to use 32-bit instructions in a 16-bit DOS program; if you do, the assembler will generate incorrect code because it will be writing code targeted at a 32-bit platform, to be run on a 16-bit one.

When NASM is in `BITS16` mode, instructions which use 32-bit data are prefixed with an `0x66` byte, and those referring to 32-bit addresses have an `0x67` prefix. In `BITS32` mode, the reverse is true: 32-bit instructions require no prefixes, whereas instructions using 16-bit data need an `0x66` and those working on 16-bit addresses need an `0x67`.

When NASM is in `BITS64` mode, most instructions operate the same as they do for `BITS32` mode. However, there are 8 more general and SSE registers, and 16-bit addressing is no longer

The default address size is 16 bits; 32-bit addressing can be selected with the `0x67` prefix. The default operand size is still 16 bits, however, and the `0x66` prefix selects 32-bit operand size. The `REX` prefixes used to select 64-bit operand size and access the new registers. NASM automatically inserts `REX` prefixes when necessary.

When the `REX` prefix is used, the processor does not know how to address the `AX`, `BX`, `CH` or `DH` (high 8-bit legacy) registers. Instead, it is possible to access the low 8-bit of the `SP`, `BP`, `SI` and `DI` registers as `SPL`, `BPL`, `SIL` and `DIL`, respectively; but only when the `REX` prefix is used.

The `BITS` directive has an exactly equivalent primitive form, `[BITS16]`, `[BITS32]` and `[BITS64]`. The user-level form is a macro which has no function other than to call the

Note that the space is necessary, e.g. `BITS32` will *not* work!

6.1.1 USE16 & USE32: Aliases for BITS

The 'USE16' and 'USE32' directives can be used in place of 'BITS16' and 'BITS32', for compatibility with other assemblers.

6.2 DEFAULT: Change the assembler defaults

The `DEFAULT` directive changes the assembler defaults. Normally, NASM defaults to a mode where the programmer is expected to explicitly specify features directly. However, this is occasionally obnoxious, as the explicit form is pretty much the only one one wishes to use.

Currently, `DEFAULT` can set `REL` & `ABS` and `BND` & `NOBND`.

6.2.1 REL & ABS: RIP-relative addressing

This sets whether registerless instructions in 64-bit mode are RIP-relative. By default, they are absolute unless overridden with the `REL` specifier (see section 3.3). However, if `DEFAULT REL` is specified, `REL` is default, unless overridden with the `ABS` specifier, *except when used with `FAS` segment override*.

The special handling of `FAS` & `GS` overrides are due to the fact that these registers are generally used as thread pointers for the special functions in 64-bit mode, and generating RIP-relative addresses would be extremely confusing.

`DEFAULT REL` is disabled with `DEFAULT ABS`.

6.2.2 BND & NOBND: BND prefix

If `DEFAULT BND` is set, all bnd-prefixable instructions following this directive are prefixed with `bnd`. To override it, `NOBND` prefix can be used.

```
DEFAULT BND
    call foo                ; BND will be prefixed
    nobnd call foo          ; BND will NOT be prefixed
```

`DEFAULT NOBND` can disable `DEFAULT BND` and the `BND` prefix will be added only when explicitly specified in code.

`DEFAULT BND` is expected to be the normal configuration for writing MPX-enabled code.

6.3 SECTION or SEGMENT: Changing and Defining Sections

The `SECTION` directive (and `SEGMENT`, an exactly equivalent synonym) changes which section of the output file the code you write will be assembled into. In some object file formats, the number and names of sections are fixed; in others, the user may make up as many as they wish. Hence `SECTION` may sometimes give an error message, or may define a new section, if you try to switch to a section that does not (yet) exist.

The Unix object formats, and the bin object format (but see section 7.1.3), all support the standardized section names `text`, `data` and `bss` for the code, data and uninitialized-data sections. The object format, by contrast, does not recognize these section names as being special, and indeed will strip off the leading period of any section name that has one.

6.3.1 The __SECT__ Macro

The `SECTION` directive is an unusual half-user-level form, different from the primitive form. The primitive form, `[SECTION xyz]`, simply switches the current target section to the one given. The user-level form `SECTION xyz` however first defines the single-line macro `__SECT__` to be the primitive `SECTION` directive, which is about to issue, and then issues it. So a user-level directive

```

SECTION .text

expands to the two lines

#define __SECT__          [SECTION .text]
                        [SECTION .text]

Users may find it useful to make use of this in their own macros. For example, the writefile macro
defined in section 4.3.3 can be usefully rewritten in the following more sophisticated form:

%macro writefile 2+

    [section .data]

    %%str:                db          %2
    %%endstr:

    __SECT__

    mov     dx, %%str
    mov     cx, %%endstr-%%str
    mov     bx, %1
    mov     ah, 0x40
    int     0x21

%endmacro

```

This form of the macro once passed a string to output first switches temporarily to the data section of the file, using the primitive form of the SECTION directives as not to modify __SECT__. It then declares the string in the data section and then invokes __SECT__ to switch back to whichever section that was previously working in. It thus avoids the need, in the previous version of the macro, to include a JMP instruction to jump over the data, and also does not fail if, in a complicated DB format module, the user could potentially be assembling the code in any of several separate

6.4 ABSOLUTE: Defining Absolute Labels

The ABSOLUTE directive can be thought of as an alternative form of SECTION: it causes the subsequent code to be directed to a physical section but at a hypothetical section starting at the given absolute address. The only instructions you can use in this mode are the RESB

ABSOLUTE is used as follows:

```

absolute 0x1A

    kbuf_chr    resw    1
    kbuf_free   resw    1
    kbuf        resw    16

```

This example describes a section of the BIOS data area, at segment address 0x40: the above code defines kbuf_chr to be 0x1A, kbuf_free to be 0x1C, and kbuf to be 0x1E.

The user-level form of ABSOLUTE, like that of SECTION, redefines the __SECT__ macro when it is invoked.

STRUC and ENDSTRUC are defined as macros which use ABSOLUTE (and also __SECT__).

ABSOLUTE doesn't have to take an absolute constant as an argument: it can take an expression (actually, a critical expression see section 3.8) and take a value as segment. For example, TSR can re-use its setup code as run-time BSS like this:

```

        org      100h                ; it's a .COM program

        jmp      setup                ; setup code comes last

        ; the resident part of the TSR goes here
setup:
        ; now write the code that installs the TSR here

absolute setup

runtimevar1      resw      1
runtimevar2      resd      20

tsr_end:

```

This defines some variables at the top of the setup code, so that after the setup has finished running the space it took up can be re-used as data storage for the running TSR. The symbol 'tsr_end' can be used to calculate the total size of the part of the TSR that needs to be made resident.

6.5 EXTERN: Importing Symbols from Other Modules

EXTERN is similar to the MASM directive EXTRN and the keyword extern: it is used to declare a symbol which is not defined anywhere in the module being assembled, but is assumed to be defined in some other module and needs to be referred to by this one. Not every object-file format can support external variables: the bin format cannot.

The EXTERN directive takes as many arguments as you like. Each argument is the name of

```

extern _printf
extern _sscanf, _fscanf

```

Some object-file formats provide extra features to the EXTERN directive. In all cases, these extra features are used by suffixing a colon to the symbol name, followed by object-format specific text. For example, the obj format allows you to declare that the default segment base for externals should be the group dgroup by means of the directive

```

extern _variable:wrt dgroup

```

The primitive form of EXTERN differs from the user-level form only in that it can take only one argument at a time: the support for multiple arguments is implemented at the preprocessor level.

You can declare the same variable as EXTERN more than once. NASM will quietly ignore the second and later redeclarations. You can't declare a variable as EXTERN as well as something else.

6.6 GLOBAL: Exporting Symbols to Other Modules

GLOBAL is the other end of EXTERN: if one module declares a symbol as EXTERN and refers to it, then in order to prevent linker errors, some other module must actually *define* the symbol and declare it as GLOBAL. Some assemblers use the name PUBLIC for this purpose.

The GLOBAL directive applying to a symbol must appear *before* the definition of the symbol.

GLOBAL uses the same syntax as EXTERN, except that it must refer to symbols which *are* defined in the same module as the GLOBAL directive. For example:

```

global _main
_main:
        ; some code

```

GLOBAL, like EXTERN, allows object formats to define private extensions by means of colon. The elf object format, for example, lets you specify whether global data items are functions

```
global hashlookup:function, hashtable:data
```

Like EXTERN, the primitive form of GLOBAL differs from the user-level form only in that it can take only one argument at a time.

6.7 COMMON: Defining Common Data Areas

The COMMON directive is used to declare *common variables*. A common variable is much like a global variable declared in the uninitialized data section, so that

```
common intvar 4
```

is similar in function to

```
global intvar
section .bss
```

```
intvar resd 1
```

The difference is that if more than one module defines the same common variable, then at link time those variables will be *merged*, and references to intvar in all modules will point at the same piece of memory.

Like GLOBAL and EXTERN, COMMON supports object-format specific extensions. For example, the obj format allows common variables to be NEAR or FAR, and the elf format allows you to specify the alignment requirements of a common variable:

```
common commvar 4:near ; works in OBJ
common intarray 100:4 ; works in ELF: 4 byte aligned
```

Once again, like EXTERN and GLOBAL, the primitive form of COMMON differs from the user-level form only in that it can take only one argument at a time.

6.8 CPU: Defining CPU Dependencies

The CPU directive restricts assembly to those instructions which are available on the target. Options are:

- CPU 8086 Assemble only 8086 instruction set
- CPU 186 Assemble instructions up to the 80186 instruction set
- CPU 286 Assemble instructions up to the 286 instruction set
- CPU 386 Assemble instructions up to the 386 instruction set
- CPU 486 486 instruction set
- CPU 586 Pentium instruction set
- CPU PENTIUM Same as 586
- CPU 686 P6 instruction set
- CPU PPRO Same as 686
- CPU P2 Same as 686
- CPU P3 Pentium III (Katmai) instruction sets
- CPU KATMAI Same as P3

- CPU P4 Pentium 4 (Willamette) instruction set
- CPU WILLAMETTE Same as P4
- CPU PRESCOTT Prescott instruction set
- CPU X64 x86-64 (x64/AMD64/Intel 64) instruction set
- CPU IA64 IA64 CPU (in x86 mode) instruction set

All options are as sensitive as possible. All instructions will be selected only if they apply to the selected CPU or lower. By default, all instructions are available.

6.9 FLOAT: Handling of floating-point constants

By default, floating-point constants are rounded to nearest and IEEE denormals are supported. The following options can be set to alter this behaviour:

- FLOAT DAZ Flush denormals to zero
- FLOAT NODAZ Do not flush denormals to zero (default)
- FLOAT NEAR Round to nearest (default)
- FLOAT UP Round up (toward +Infinity)
- FLOAT DOWN Round down (toward -Infinity)
- FLOAT ZERO Round toward zero
- FLOAT DEFAULT Restore default settings

The standard macros `__FLOAT_DAZ__`, `__FLOAT_ROUND__`, and `__FLOAT__` contain the current state, as long as the programmer has avoided the use of the bracketed primitive form `__FLOAT__`. `__FLOAT__` contains the full set of floating-point settings; this value can be saved away and invoked later to restore the setting.

6.10 [WARNING]: Enable or disable warnings

The `[WARNING]` directive can be used to enable or disable classes of warnings in the same way as the `-w` option, see section 2.1.25 for more details about warning classes.

- `[warning +warning-class]` enables warnings for *warning-class*.
- `[warning -warning-class]` disables warnings for *warning-class*.
- `[warning warning-class]` restores *warning-class* to the original value, either the default value or as specified on the command line.

The `[WARNING]` directive also accepts the `all`, `error` and `error=warning-class` specifiers. No "user form" (without the brackets) currently exists.

Chapter 7: Output Formats

NASM is a portable assembler designed to be able to compile on any ANSI-C-supporting platform and produce output on a variety of Intel x86 operating systems. For this reason, it has a large number of available output formats, selected using the `-f` option on the NASM command line. Each of these formats, along with its extensions to the base NASM syntax, is detailed in this chapter.

As stated in section 2.1.1, NASM chooses a default name for your output file based on the input file name and the chosen output format. This will be generated by removing the extension (`.asm`, `.s`, or whatever you like) from the input file name and substituting an extension defined by the output format. The extensions are given with each format below.

7.1 bin: Flat-Form Binary Output

The `bin` format does not produce object files; it generates nothing in the output file except the code you wrote. Such pure binary files are used by MS-DOS `.COM` executables and SYSDriver are pure binary files. Pure binary output is also useful for operating system and boot loaders.

The `bin` format supports multiple section names. For details on how NASM handles sections in the `bin` format, see section 7.1.3.

Using the `bin` format puts NASM in default 32-bit mode (see section 6.1). In order to use `bin` to write 32-bit or 64-bit code, such as an OS kernel, you need to explicitly issue the `BITS 32` or `BITS 64` directive.

`bin` has a default output file name extension instead; it leaves your file name as is, since the original extension has been removed. Thus, the default is for NASM to assemble `prog.asm` into a binary file called `binprog`.

7.1.1 ORG: Binary File Program Origin

The `bin` format provides an additional directive, `ORG`, which is given in chapter 6. The function of the `ORG` directive is to specify the origin address which NASM will assume the program begins at when it is loaded into memory.

For example, the following code will generate the longword `0x00000104`:

```
org      0x100
dd      label
label:
```

Unlike the `ORG` directive provided by x86-compatible assemblers, which allows you to jump around in the object file and overwrite code you have already generated, NASM's `ORG` does exactly what the directive says: *origin*. Its sole function is to specify an offset which is added to all internal address references within the section; it does not permit any of the trickery that x86 assemblers do. See section 12.1.3 for further comments.

7.1.2 bin Extensions to the SECTION Directive

The `bin` output format extends the `SECTION` (or `SEGMENT`) directive to allow you to specify the alignment requirements of segments. This is done by appending the `ALIGN` qualifier to the end of the section-definition line. For example,

```
section .data align=16
```

switches to the section `.data` and also specifies that it must be aligned on a 16-byte boundary.

The parameter `ALIGN` specifies how many low bits of the section start address must be forced to zero. The alignment value given may be any power of two.

7.1.3 Multisection Support for the bin Format

The bin format allows these multiple sections of arbitrary names besides the known ".text", ".data", and ".bss" names.

- Sections may be designated progbits or mobjs. Default is progbits (except .bss, which defaults to nobits, of course).
- Sections can be aligned to a specified boundary following the previous section with align=pat an arbitrary byte-granular position with start=.
- Sections can be given a virtual start address, which will be used for the calculation of memory references within that section with vstart=.
- Sections can be ordered using follows=<section> or vfollows=<section> as an alternative to specifying an explicit start address.
- Arguments org, start, vstart, and align are critical expressions. See section 3.8. E.g. align=(1 << ALIGN_SHIFT) - ALIGN_SHIFT must be defined before it is used here.
- Any code which comes before an explicit SECTION directive is directed by default into the text section.
- If an ORG statement is not given, ORG 0 is used by default.
- The .bss section will be placed after the last progbits section, unless start=, vstart=, follows=, or vfollows= has been specified.
- All sections are aligned on dword boundaries, unless a different alignment has been specified.
- Sections may not overlap.
- NASM creates the section.<secname>.start for each section, which may be used in your code.

7.1.4 Map Files

Map files can be generated in bin format by means of the [map] option. Map types of all (default), brief, sections, segments, or symbols may be specified. Output may be directed to stdout (default), stderr, or a specified file. E.g. [map symbols] file.map. No "user form" exists, the square brackets must be used.

7.2 ith: Intel Hex Output

The ith file format produces Intel hex-format files. Just as the bin format, this is a flat memory image format with no support for relocation or linking. It is usually used with ROM programmers and similar utilities.

All extensions supported by the bin file format is also supported by the ith file format. ith provides a default output file-name extension of .ith.

7.3 srec: Motorola S-Records Output

The srec file format produces Motorola S-records files. Just as the bin format, this is a flat memory image format with no support for relocation or linking. It is usually used with ROM programmers and similar utilities.

All extensions supported by the bin file format is also supported by the srec file format. srec provides a default output file-name extension of .srec.

7.4 obj: Microsoft OMF Object Files

The obj file format (NASM calls it obj rather than o for historical reasons) is the one produced by MASM and TASM, which typically feed 16-bit DOS linkers to produce EXE files. It is also the format used by OS/2.

obj provides a default output file-name extension of .obj.

obj is not exclusively a 16-bit format, though NASM has full support for the 32-bit extensions to the format. In particular, 32-bit obj format files are used by Borland's Win32 compilers, instead of using Microsoft's newer win32 object file format.

The obj format does not define any special segment names; you can call your segments anything you like. Typical names for segments in obj format files are CODE, DATA and BSS.

If your source file contains code before specifying an explicit SEGMENT directive, then NASM will invent its own segment called __NASMDEFSEG for you.

When you define a segment in an obj file, NASM defines the segment name as a symbol as well, so that you can access the segment address of the segment. So, for example:

```
segment data
```

```
dvar:    dw      1234
```

```
segment code
```

```
function:
```

```
    mov     ax,data           ; get segment address of data
    mov     ds,ax             ; and move it into DS
    inc     word [dvar]       ; now this reference will work
    ret
```

The obj format also enables the use of the SEG and WR operators, so that you can write code which does things like

```
extern  foo
```

```
    mov     ax,seg foo        ; get preferred segment of foo
    mov     ds,ax
    mov     ax,data           ; a different segment
    mov     es,ax
    mov     ax,[ds:foo]       ; this accesses 'foo'
    mov     [es:foo wrt data],bx ; so does this
```

7.4.1 obj Extensions to the SEGMENT Directive

The obj output format extends the SEGMENT (or SECTION) directive to allow you to specify various properties of the segment you are defining. This is done by appending extra qualifiers to the end of the segment-definition line. For example,

```
segment code private align=16
```

defines the segment code but also declares it to be a private segment, and requires that the portion of it described in this code module must be aligned on a 16-byte boundary.

The available qualifiers are:

- PRIVATE, PUBLIC, COMMON and STACK specify the combination characteristics of the segment. PRIVATE segments do not get combined with any others by the linker; PUBLIC and STACK

segments get concatenated together at link time, and COMMON segments all get overlaid on top of each other rather than stuck end-to-end.

- **ALIGN** is used, as shown above, to specify how many low bits of the segment start address must be forced to zero. The alignment value given may be any power of two from 1 to 4096; in reality, the only values supported are 1, 2, 4, 16, 256 and 4096, so if a specified value will be rounded up to 6, and 32, 64 and 256 will be rounded up to 256, and so on. Note that an alignment to 4096-byte boundaries is a PharLap extension to the format and may not be supported by all linkers.
- **CLASS** is used to specify the segment class; this feature indicates to the linker that segments of the same class should be placed near each other in the output file. The class name can be any word, e.g. `CLASS=CODE`.
- **OVERLAY**, like **CLASS**, is specified with an arbitrary word as an argument, and provides overlay information to an overlay-capable linker.
- Segments can be declared as **USE16** or **USE32**, which has the effect of recording the choice in the object file and ensuring that NASM's default assembly mode when assembling that segment is 16-bit or 32-bit respectively.
- When writing OS/2 object files, you should declare 32-bit segments as **FLAT**, which causes the default segment base for anything in the segment to be the special group **FLAT**, and also defines the group if it is not already defined.
- The obj format also allows segments to be declared as having pre-defined absolute segment addresses, although no linker is currently known to make sensible use of this feature; nevertheless, NASM allows you to declare segments such as `SEGMENT SCREEN ABSOLUTE=0xB800` if you need to. The **ABSOLUTE** and **ALIGN** keywords are mutually exclusive.

NASM's default segment attributes are **PUBLIC**, **ALIGN=1**, no class, no overlay, and **USE**

7.4.2 GROUP: Defining Groups of Segments

The obj format also allows segments to be grouped, so that a single segment register can be used to refer to all the segments in a group. NASM therefore supplies the **GROUP** directive, whereby you can code

```
segment data
```

```
    ; some data
```

```
segment bss
```

```
    ; some uninitialized data
```

```
group dgroup data bss
```

which will define a group called `dgroup` to contain the segments `data` and `bss`. Like **SEGMENT**, **GROUP** causes the group name to be defined as a symbol, so that you can refer to a variable `var` in the `data` segment as `var wrt data` or as `var wrt dgroup`, depending on which segment value is currently in your segment register.

If you just refer to `var`, however, and `var` is declared in a segment which is part of a group, then NASM will default to giving you the offset of `var` from the beginning of the group, not the segment. Therefore `SEG var`, also, will return the group base rather than the segment base.

NASM will allow a segment to be part of more than one group, but will generate a warning if you do this. Variables declared in a segment which is part of more than one group will default to being relative to the first group that was defined to contain the segment.

A group does not have to contain any segments; you can still make a WR reference to a group which does not contain the variable you are referring to. OS/2, for example, defines the special group FLAT with no segments in it.

7.4.3 UPPERCASE: Disabling Case Sensitivity in Output

Although NASM itself is case-sensitive, some other linkers are not; therefore it can be useful for NASM to output single-case object files. The UPPERCASE format-specific directive causes all segment group and symbol names that are written to the object file to be forced to uppercase just before being written. Within a source file, NASM is still case-sensitive, but the object file is written entirely in upper case if desired.

UPPERCASE is used alone on a line; it requires no parameters.

7.4.4 IMPORT: Importing DLL Symbols

The IMPORT format-specific directive defines symbols to be imported from a DLL, for use if you are writing a DLL's import library in NASM. You still need to declare the symbols as EXTERNALs, as well as using the IMPORT directive.

The IMPORT directive takes two required parameters, separated by whitespace, which are (respectively) the name of the symbol you wish to import and the name of the library you wish to import it from. For example:

```
import  WSASStartup wsock32.dll
```

A third optional parameter gives the name by which the symbol is known in the library you are importing it from, in case this is not the same as the name you wish the symbol to be known by to your code once you have imported it. For example:

```
import  asyncsel wsock32.dll WSAAsyncSelect
```

7.4.5 EXPORT: Exporting DLL Symbols

The EXPORT format-specific directive defines a global symbol to be exported as a DLL symbol, for use if you are writing a DLL in NASM. You still need to declare the symbol as GLOBAL as well as using the EXPORT directive.

EXPORT takes one required parameter, which is the name of the symbol you wish to export, as it was defined in your source file. An optional second parameter (separated by whitespace from the first) gives the *external* name of the symbol: the name by which you wish the symbol to be known to programs using the DLL. If this name is the same as the internal name, you may leave the second parameter off.

Further parameters are given to define attributes of the exported symbol. These parameters, like the second, are separated by whitespace. If further parameters are given, the external name must also be specified, even if it is the same as the internal name. The available attributes are:

- `resident` indicates that the exported name is to be kept resident by the system loader. This is an optimisation for frequently used symbols imported by name.
- `nodata` indicates that the exported symbol is a function which does not make use of any initialized data.
- `parm=NNN`, where `NNN` is an integer, sets the number of parameter words for the case in which the symbol is a call gate between 32-bit and 16-bit segments.
- An attribute which is just a number indicates that the symbol should be exported with an identifying number (ordinal), and gives the desired number.

For example:

```

export myfunc
export myfunc TheRealMoreFormalLookingFunctionName
export myfunc myfunc 1234 ; export by ordinal
export myfunc myfunc resident parm=23 nodata

```

7.4.6 `..start`: Defining the Program Entry Point

OMF linker requires exactly one of the object files being linked to define the program entry point, where execution will begin when the program is run. If the object file has defined the entry point assembled using NASM, you specify the entry point by declaring the special symbol `..start` at the point where you wish execution to begin.

7.4.7 `obj` Extensions to the `EXTERN` Directive

If you declare an external symbol with the directive

```
extern foo
```

then references such as `mov ax,foo` will give you the offset of `foo` from its preferred segment base (as specified in whichever module `foo` is actually defined in). So to access the contents of `foo` you will usually need to do something like

```

mov     ax,seg foo      ; get preferred segment base
mov     es,ax           ; move it into ES
mov     ax,[es:foo]     ; and use offset 'foo' from it

```

This is a little awkward, particularly if you know that an external is going to be accessible from a given segment or group, say `dgroup`. So if `DS` already contained `dgroup`, you could simply code

```
mov     ax,[foo wrt dgroup]
```

However, having to type this every time you want to access `foo` can be a pain; so NASM allows you to declare `foo` in the alternative form

```
extern foo:wrt dgroup
```

This form causes NASM to pretend that the preferred segment base of `foo` is in fact `dgroup`; so the expression `seg foo` will now return `dgroup`, and the expression `foo` is equivalent to `foo wrt dgroup`.

This default-WRT mechanism can be used to make externals appear to be relative to any group or segment in your program. It can also be applied to common variables: see section 7.4.8

7.4.8 `obj` Extensions to the `COMMON` Directive

The `obj` format allows common variables to be either near or far; NASM allows you to specify which your variables should be by the use of the syntax

```

common nearvar 2:near ; 'nearvar' is a near common
common farvar 10:far  ; and 'farvar' is far

```

Far common variables may be greater in size than 64Kb, and the OMF specification says that they are declared as a number of *elements* of a given size. So a 10-byte far common variable could be declared as ten one-byte elements, five two-byte elements, two five-byte elements or one ten-

Some OMF linker requires the element size, as well as the variable size, to match when resolving common variables declared in more than one module. Therefore NASM must allow you to specify the element size on your far common variables. This is done by the following syntax:

```

common c_5by2 10:far 5 ; two five-byte elements
common c_2by5 10:far 2 ; five two-byte elements

```

If element size is specified, the default is 1. Also, the `FA` keyword is not required when an element size is specified, since only far common symbols have element size at all. So the above declarations could equivalently be

```
common  c_5by2  10:5          ; two five-byte elements
common  c_2by5  10:2          ; five two-byte elements
```

In addition to these extensions, the `COMMON` directive also supports default-WRT specification like `EXTERN` does (explained in section 7.4.7). So you can also declare things like

```
common  foo      10:wrt dgroup
common  bar      16:far 2:wrt data
common  baz      24:wrt data:6
```

7.4.9 Embedded File Dependency Information

Since NASM 1.13.02, object files contain embedded dependency file information. To suppress the generation of dependencies, use

```
%pragma obj nodepend
```

7.5 win32: Microsoft Win32 Object Files

The win32 output format generates Microsoft Win32 object files, suitable for passing to Microsoft linkers such as Visual C++. Note that Borland Win32 compilers do not use this format, but use `obj` instead (see section 7.4).

win32 provides a default output file-name extension of `.obj`.

Note that although Microsoft says that Win32 object files follow the COFF (Common Object File Format) standard, the object files produced by Microsoft Win32 compilers are not compatible with COFF linkers such as DJGPP's, and vice versa. This is due to a difference of opinion over the precise semantics of PC-relative relocations. To produce COFF files suitable for DJGPP, use NASM's `sof` output format; conversely, the `coff` format does not produce object files that Win32 linkers can generate correct output from.

7.5.1 win32 Extensions to the SECTION Directive

Like the `obj` format, win32 allows you to specify additional information on the `SECTION` directive line to control the type and properties of sections you declare. Section types and properties are generated automatically by NASM for the standard section names `.text`, `.data` and `.bss`, but may still be overridden by these qualifiers.

The available qualifiers are:

- `code`, or equivalently `text`, defines the section to be a code section. This marks the section as readable and executable, but not writable, and also indicates to the linker that the type of the section is code.
- `data` and `bss` define the section to be a data section, analogously to code. Data sections are marked as readable and writable, but not executable; `data` declares an initialized data section, whereas `bss` declares an uninitialized data section.
- `rdata` declares an initialized data section that is readable but not writable. Microsoft compilers use this section to place constants in it.
- `info` defines the section to be an information section, which is not included in the executable file by the linker, but may (for example) pass information to the linker. For example, declaring an `info-type` section called `directve` causes the linker to interpret the contents of the section as command-line options.

- `align=` used with a trailing number as in `obj gives the alignment requirements of the section`. The maximum you may specify is 64; the Win32 object file format contains no means to request a greater section alignment than this. If alignment is explicitly specified, the default is 16-byte alignment for code sections, 8-byte alignment for data sections and 4-byte alignment for data and BSS sections. Informational sections get default alignment of 1 byte (alignment) though the value does not matter.

The defaults assumed by NASM if you do not specify the above qualifiers are:

```
section .text    code   align=16
section .data    data   align=4
section .rdata   rdata  align=8
section .bss     bss    align=4
```

Any other section name is treated by default like `.text`.

7.5.2 win32: Safe Structured Exception Handling

Among other improvements in Windows XP SP2 and Windows Server 2003 Microsoft has introduced concept of safe structured exception handling. General idea is to collect handlers entry points in designated dead-only table and have alleged entry point verified against this table prior exception control is passed to the handler. In order for an executable module to be equipped with such "safe exception handler table," all object modules on linker command line has to comply with certain criteria. If one single module among them does not, then the table in question is omitted and above mentioned run-time check will not be performed for application in question. Table omission is by default silent and therefore can be easily overlooked. One can instruct linker to refuse to produce binary without such table by passing `/safeseh` command line option.

Without regard to this run-time check, it is natural to expect NASM to be capable of generating modules suitable for `/safeseh` linking. From developer's viewpoint the problem is two

- how to adapt modules not deploying exception handlers of their own;
- how to adapt/develop modules utilizing custom exception handling;

Former can be easily achieved with any NASM version by adding following line to source

```
$@feat.00 equ 1
```

As of version 2.0 NASM adds this absolute symbol automatically. If it's not already present, the precise `__if` for whatever reason developer would choose to assign another value to source file, it would still be perfectly possible.

Registering custom exception handler on the other hand requires certain "magic." As of version 2.03 additional directive `__safeseh` is implemented, which instructs assembler to produce appropriately formatted input data for above mentioned "safe exception handler table." Its typical

```
section .text
extern _MessageBoxA@16
%if    __NASM_VERSION_ID__ >= 0x02030000
safeseh handler          ; register handler as "safe handler"
%endif
handler:
    push    DWORD 1 ; MB_OKCANCEL
    push    DWORD caption
    push    DWORD text
    push    DWORD 0
    call    _MessageBoxA@16
    sub     eax,1      ; incidentally suits as return value
                    ; for exception handler
```

```

        ret
global  _main
_main:
        push    DWORD handler
        push    DWORD [fs:0]
        mov     DWORD [fs:0],esp ; engage exception handler
        xor     eax,eax
        mov     eax,DWORD[eax]   ; cause exception
        pop     DWORD [fs:0]     ; disengage exception handler
        add     esp,4
        ret
text:   db      'OK to rethrow, CANCEL to generate core dump',0
caption:db      'SEGV',0

section .drectve info
        db      '/defaultlib:user32.lib /defaultlib:msvcrt.lib '

```

As you might imagine, it's perfectly possible to produce an executable with a "safe exception handler table" and engage an unregistered exception handler. Indeed, the handler is engaged by simply manipulating [fs:0] location at run-time, something linker has no power over, run-time that is. It should be explicitly mentioned that such failure to register handler's entry point with a safe seh directive has undesired side effect at run-time. If exceptions are raised and unregistered handlers are executed, the application is abruptly terminated without any notification whatsoever. One might argue that the system could at least have logged some kind of "non-safe exception handler in .exe at address ..." message in event log, but no, literally no notification is provided and user is left with no clue on what caused application failure.

Finally, I mention a linker bug in this paragraph for few Microsoft linker version 7.0 and later. Presence of @feat.00 symbol and input data for "safe exception handler table" causes no backward incompatibilities and "safeseh" module generated by NASM 0.99 and later can still be linked by earlier versions or non-Microsoft linkers.

7.5.3 Debugging formats for Windows

The win32 and win64 format support the Microsoft CodeView debugging format. Currently CodeView version 8 format is supported (cv8) but newer versions of the CodeView debugger should be able to handle this format as well.

7.6 win64: Microsoft Win64 Object Files

The win64 output format generates Microsoft Win64 object files, which is nearly 100% identical to the win32 object format (section 7.5) with the exception that it is meant to target 64-bit code and the x86-64 platform together. This object file is used exactly the same as the win32 object format (section 7.5), in NASM, with regard to this exception.

7.6.1 win64: Writing Position-Independent Code

While @EL takes good care of RIP-relative addressing, there is one aspect that is easy to overlook for a Win64 programmer: indirect references. Consider a switch dispatch table:

```

        jmp     qword [dsptch+rax*8]
        ...
dsptch: dq      case0
        dq      case1
        ...

```

Even a novice Win64 assembler programmer will soon realize that the code is not 64-bit savvy. Most notably linker will refuse to link it with

'ADDR32' relocation to '.text' invalid without /LARGEADDRESSAWARE:NO

So [s]he will have to split jmp instruction as following:

```
lea    rbx,[rel dsptch]
jmp    qword [rbx+rax*8]
```

What happens behind the scenes is that effective address is encoded relative to instruction pointer, in perfectly position-independent manner. But this is only part of the problem. Troubles that in .dll context case relocations will make the way to the final module and might have to be adjusted at .dll load time. To be specific, when it can't be loaded at preferred address. And when this occurs, pages with such relocations will be rendered private to current process, which kind of undermines the idea of sharing .dll. But no worry, it's trivial to fix:

```
lea    rbx,[rel dsptch]
add    rbx,[rbx+rax*8]
jmp    rbx
...
dsptch: dq    case0-dsptch
        dq    case1-dsptch
...
```

NASM version 2.03 and later provides another alternative, wrt ..imagebase operator, which returns offset from base address of the current image, be it exe or .dll module; here for the same. For those acquainted with PE-COFF format, base address denotes start of IMAGE_DOS_HEADER structure. Here is how to implement switch with these image-relative references:

```
lea    rbx,[rel dsptch]
mov    eax,[rbx+rax*4]
sub    rbx,dsptch wrt ..imagebase
add    rbx,rax
jmp    rbx
...
dsptch: dd    case0 wrt ..imagebase
        dd    case1 wrt ..imagebase
```

One can argue that the operator is redundant. Indeed, snippet before last works just fine with any NASM version and is not even Windows specific... The real reason for implementing wrt ..imagebase will become apparent in next paragraph.

It should be noted that wrt ..imagebase is defined as 32-bit operand only:

```
dd    label wrt ..imagebase    ; ok
dq    label wrt ..imagebase    ; bad
mov    eax,label wrt ..imagebase    ; ok
mov    rax,label wrt ..imagebase    ; bad
```

7.6.2 win64: Structured Exception Handling

Structured exception handling in Win64 is completely different matter from Win32. Upon exception program counter value is noted, and linker-generated table comprising target addresses of all the functions in given executable module is traversed and compared to the saved program counter. Thus, so-called UNWIND_INFO structure is identified. If it's not found, then offending subroutines is assumed to be leaf and just mentioned lookup procedure attempted on its caller. In Win64 leaf function is such function that does not call any other function nor modifies any Win64 non-volatile registers, including rax pointer. The latter ensures that, possibly, identified function's caller by simply pulling the value from the top of the stack.

While majority of subroutines written in assembly are not calling any other function, requirement for non-volatile registers, immutability leaves developer with more than a few registers and stack frame which is not necessarily what's he counted with. Customarily, one would meet the requirement by saving non-volatile registers on stack and restoring them upon return, what can go wrong if and only if an exception is raised at run-time and UNWIND_INFO structure associated with such "leaf" function, the stack unwind procedure will expect to find caller's return address at the top of stack immediately followed by frame. Given that developer pushed caller's non-volatile registers on stack, would the value at top point to some code segment or even addressable space. Well, developer can attempt copying caller's return address to the top of stack and this would actually work in some very specific circumstances. But unless developer can guarantee that these circumstances are always met, it's more appropriate to assume worst case scenario, i.e. stack unwind procedure goes berserk. Relevant question is what happens then. Application abruptly terminated without any notification whatsoever. Just like in Win32 case, one can argue that system could at least have logged "unwind procedure went berserk in x.exe at address n" in event log, but no, no trace of failure.

Now when we understand significance of the UNWIND_INFO structure, let's discuss what's in and/or how it's processed. First, it is checked for presence of reference to custom language-specific exception handler. If there is one, then it's invoked. Depending on the return value, execution flows resumed (exception is said to be "handled"), or rest of UNWIND_INFO structure is processed as following. Besides optional reference to custom handler, it carries information about current callee's stack frame and where non-volatile registers are saved. Information is detailed enough to be able to reconstruct contents of caller's non-volatile registers prior to current callee. And caller's context is reconstructed and then unwind procedure is repeated, i.e. another UNWIND_INFO structure is associated, this time with caller's instruction pointer, which is checked for presence of reference to language-specific handler. The procedure is recursively repeated till exceptions handled. As last resort system "handles" it by generating memory core dump and terminating the application.

As for the moment of this writing, NASM unfortunately does not facilitate generation of above mentioned detailed information about stack frame layout. But as of version 2.03, it implements building blocks for generating structures involved in stack unwinding. As simple example, here is how to deploy custom exception handler for leaf function:

```
default rel
section .text
extern MessageBoxA
handler:
    sub     rsp, 40
    mov     rcx, 0
    lea     rdx, [text]
    lea     r8, [caption]
    mov     r9, 1      ; MB_OKCANCEL
    call    MessageBoxA
    sub     eax, 1      ; incidentally suits as return value
                        ; for exception handler
    add     rsp, 40
    ret
global main
main:
    xor     rax, rax
    mov     rax, QWORD[rax] ; cause exception
    ret
main_end:
text:  db      'OK to rethrow, CANCEL to generate core dump', 0
caption: db    'SEGV', 0
```

```

section .pdata rdata align=4
    dd      main wrt ..imagebase
    dd      main_end wrt ..imagebase
    dd      xmain wrt ..imagebase
section .xdata rdata align=8
xmain:  db      9,0,0,0
        dd      handler wrt ..imagebase
section .drectve info
        db      '/defaultlib:user32.lib /defaultlib:msvcrt.lib '

```

What you see in .pdata section is a table comprising start and end addresses of function along with reference to associated UNWIND_INFO structure. And what you see in .xdata section is UNWIND_INFO structure describing function with frame pointer with designated exception handler. References are required to be image-relative (which is the reason for implementing wrt ..imagebase operator). It should be noted that rdata align=n, as well as wrt ..imagebase are optional in these two segments contexts, i.e. can be omitted. Latter means that all 2-bit references not only above listed required ones placed in these two segments but also image-relative. Why is it important to understand? Developer is allowed to open handler-specific data in UNWIND_INFO structure and [s] adds 2-bit reference, then [s] will have to remember to adjust its value to obtain the real pointer.

As already mentioned, in Win64 terms leaf function is one that does not call any other function nor modifies any non-volatile register, including stack pointer. Built 'so' is uncommon has assembler programmer plans to utilize every single register and sometimes even have variable stack frame. Is there anything new with bar building blocks? Besides manually composing fully-fledged UNWIND_INFO structure, which would surely be considered error-prone. Yes, there is. Recall that exception handler is called first before stack layout is analyzed. As turned out, it's perfectly possible to manipulate current callee's context in custom handler in manner that permits further stack unwinding. General idea is that handler would not actually handle the exception, but instead store callee's context as a wait entry point and thus mimic leaf function. In the words handler would simply undertake part of unwinding procedure. Consider following example:

```

function:
    mov     rax, rsp                ; copy rsp to volatile register
    push    r15                    ; save non-volatile registers
    push    rbx
    push    rbp
    mov     r11, rsp               ; prepare variable stack frame
    sub     r11, rcx
    and     r11, -64
    mov     QWORD[r11], rax        ; check for exceptions
    mov     rsp, r11              ; allocate stack frame
    mov     QWORD[rsp], rax        ; save original rsp value
magic_point:
    ...
    mov     r11, QWORD[rsp]        ; pull original rsp value
    mov     rbp, QWORD[r11-24]
    mov     rbx, QWORD[r11-16]
    mov     r15, QWORD[r11-8]
    mov     rsp, r11              ; destroy frame
    ret

```

The keyword is that up to magic_point original rsp value remains in those volatile registers and non-volatile registers except for rsp, is modified. While past magic_point rsp remains constant till the very end of the function. In this case custom language-specific exception handler would look like this:

```

EXCEPTION_DISPOSITION handler (EXCEPTION_RECORD *rec, ULONG64 frame,
    CONTEXT *context, DISPATCHER_CONTEXT *disp)
{
    ULONG64 *rsp;
    if (context->Rip < (ULONG64)magic_point)
        rsp = (ULONG64 *)context->Rax;
    else
    {
        rsp = ((ULONG64 **)context->Rsp)[0];
        context->Rbp = rsp[-3];
        context->Rbx = rsp[-2];
        context->R15 = rsp[-1];
    }
    context->Rsp = (ULONG64)rsp;

    memcpy (disp->ContextRecord, context, sizeof(CONTEXT));
    RtlVirtualUnwind (UNW_FLAG_NHANDLER, disp->ImageBase,
        disp->ControlPc, disp->FunctionEntry, disp->ContextRecord,
        &disp->HandlerData, &disp->EstablisherFrame, NULL);
    return ExceptionContinueSearch;
}

```

A custom handler mimics `lea` function, corresponding `UNWIND_INFO` structure does not have to contain any information about stack frame and its layout.

7.7 coff: Common Object File Format

The coff output type produces COFF object files suitable for linking with the DJGPP. coff provides a default output file-name extension of `.o`.

The coff format supports the same extensions as the `SECTION` directive as win32 does, except that the align qualifier and the info section type are not supported.

7.8 macho32 and macho64: Mach Object File Format

The macho32 and macho64 output formats produce Mach-Object files suitable for linking with the MacOS X linker. macho is a synonym for macho32.

macho provides a default output file-name extension of `.o`.

7.8.1 macho extensions to the SECTION Directive

The macho output formats specify section names in the format "*segment, section*". No spaces are allowed around the comma. The following flags can also be specified:

- data - this section contains initialized data items
- text - this section contains code exclusively
- mixed - this section contains both code and data
- bss - this section is uninitialized and filled with zero
- zerofill - same as bss
- no_dead_strip - inhibit dead code stripping for this section
- live_support - set the live support flag for this section
- strip_static_syms - strip static symbols for this section
- debug - this section contains debugging information
- align=*alignment* - specify section alignment

The default is data, unless the section name is `__text` or `__bss` in which case the default is `text` or `bss`, respectively.

For compatibility with other Unix platforms, the following standard names are also supported:

```
.text    = __TEXT,__text    text
.rodata  = __DATA,__const   data
.data    = __DATA,__data    data
.bss     = __DATA,__bss     bss
```

If the `.rodata` section contains relocations, it is instead put into the `__TEXT,__const` section unless this section has already been specified explicitly. However, it probably better to specify `__TEXT,__const` and `__DATA,__const` explicitly as appropriate.

7.8.2 Thread Local Storage in Mach-O: macho special symbols and WRT

Mach-O defines the following special symbol that can be used on the right-hand side of the WRT operator:

- `..tlvp` is used to specify access to thread-local storage.
- `..gotpcrel` is used to specify reference to the Global Offset Table. The GOT is supported in the macho64 format only.

7.8.3 macho specific directive subsections_via_symbols

The directive `subsections_via_symbols` sets the `MH_SUBSECTIONS_VIA_SYMBOLS` flag in the Mach-O header, which tells the linker that the symbol in the file matches the convention required to allow for link-time dead code elimination.

This directive takes no arguments.

This is a macro implemented as a `%pragma`. It can also be specified in its `%pragma` form, in which case it will not affect non-Mach-O builds of the same source code:

```
%pragma macho subsections_via_symbols
```

7.8.4 macho specific directive no_dead_strip

The directive `no_dead_strip` sets the `MCH_NO_DEAD_STRIP` section flag on the section containing a specific symbol. This directive takes a list of symbols as its arguments.

This is a macro implemented as a `%pragma`. It can also be specified in its `%pragma` form, in which case it will not affect non-Mach-O builds of the same source code:

```
%pragma macho no_dead_strip symbol...
```

7.9 elf32, elf64, elfx32: Executable and Linkable Format Object Files

The `elf32`, `elf64` and `elfx32` output formats generate ELF32 and ELF64 (Executable and Linkable Format) object files, as used by Linux and Unix systems, including Solaris, x86 UnixWare and SCO Unix. `elf` provides a default output file-name extension of `.o`. `elf` is a synonym for `elf64`.

The `elfx32` format is used for the x32 ABI, which is a 32-bit ABI with the CPU in 64-bit mode.

7.9.1 ELF specific directive osabi

The `ELF` header specifies the application binary interface for the target operating system (OSABI). This field can be set using the `osabi` directive with the numerical value (0-255) of the target system. If this directive is not used, the default value will be `"UNIX System V ABI" (0)`, which will work on most systems which support ELF.

7.9.2 elf extensions to the SECTION Directive

Like the obj format, elf allows you to specify additional information on the SECTION directive line, to control the type and properties of sections you declare. Section types and properties are generated automatically by NASM for the standard section names, but may still be overridden by

The available qualifiers are:

- `alloc` defines the section to be one which is loaded into memory when the program is run.
`noalloc` defines it to be one which is not, such as an informational or comment section.
- `exec` defines the section to be one which should have execute permission when the program is run.
`noexec` defines it as one which should not.
- `write` defines the section to be one which should be writable when the program is run.
`nowrite` defines it as one which should not.
- `progbits` defines the section to be one with explicit contents stored in the object file: ordinary code or data section, for example. `nobits` defines the section to be one with no explicit contents given, such as a BSS section.
- `align=`, used with a trailing number as in `obj`, gives the alignment requirements of
- `tls` defines the section to be one which contains thread local variables.

The defaults assumed by NASM if you do not specify the above qualifiers are:

<code>section .text</code>	<code>progbits</code>	<code>alloc</code>	<code>exec</code>	<code>nowrite</code>	<code>align=16</code>	
<code>section .rodata</code>	<code>progbits</code>	<code>alloc</code>	<code>noexec</code>	<code>nowrite</code>	<code>align=4</code>	
<code>section .lrodata</code>	<code>progbits</code>	<code>alloc</code>	<code>noexec</code>	<code>nowrite</code>	<code>align=4</code>	
<code>section .data</code>	<code>progbits</code>	<code>alloc</code>	<code>noexec</code>	<code>write</code>	<code>align=4</code>	
<code>section .ldata</code>	<code>progbits</code>	<code>alloc</code>	<code>noexec</code>	<code>write</code>	<code>align=4</code>	
<code>section .bss</code>	<code>nobits</code>	<code>alloc</code>	<code>noexec</code>	<code>write</code>	<code>align=4</code>	
<code>section .lbss</code>	<code>nobits</code>	<code>alloc</code>	<code>noexec</code>	<code>write</code>	<code>align=4</code>	
<code>section .tdata</code>	<code>progbits</code>	<code>alloc</code>	<code>noexec</code>	<code>write</code>	<code>align=4</code>	<code>tls</code>
<code>section .tbss</code>	<code>nobits</code>	<code>alloc</code>	<code>noexec</code>	<code>write</code>	<code>align=4</code>	<code>tls</code>
<code>section .comment</code>	<code>progbits</code>	<code>noalloc</code>	<code>noexec</code>	<code>nowrite</code>	<code>align=1</code>	
<code>section other</code>	<code>progbits</code>	<code>alloc</code>	<code>noexec</code>	<code>nowrite</code>	<code>align=1</code>	

(Any section name other than those in the above table is treated by default like `other` in the above table. Please note that section names are case sensitive.)

7.9.3 Position-Independent Code: macho Special Symbols and WRT

Since ELF does not support segment-based references, the WRT operator is not used for its normal purpose; therefore, NASM's elf output format makes use of WRT for a different purpose, namely the PIC-specific relocation types.

elf defines five special symbols which you can use as the right-hand side of the WRT operator to obtain PIC relocation types. They are `..gotpc`, `..gotoff`, `..got`, `..plt` and `..sym`. Their functions are summarized here:

- Referring to the symbol marking the global offset table base using `wrt..gotpc` will end up giving the distance from the beginning of the current section to the global offset table. (`_GLOBAL_OFFSET_TABLE` is the standard symbol name used to refer to the GOT.) So you would then need to add \$\$ to the result to get the real address of the GOT.
- Referring to a location in one of your own sections using `wrt..gotoff` will give the distance from the beginning of the GOT to the specified location, so that adding on the address of the GOT would give the real address of the location you wanted.

- Referring to an external global symbol using `wrt.got` causes the linker to build an entry in the GOT containing the address of the symbol, and the reference gives the distance from the beginning of the GOT to the entry; so you can add to the address of the GOT, load from the resulting address, and end up with the address of the symbol.
- Referring to a procedure name using `wrt.plt` causes the linker to build a procedure linkage table entry for the symbol, and the reference gives the address of the PLT entry. You can only use this in context which would generate PC-relative relocation normally (i.e. as the destination for CALL or JMP), since ELF contains no relocation type to refer to PLT entries absolutely.
- Referring to a symbol name using `wrt..sym` causes NASM to write an ordinary relocation, but instead of making the relocation relative to the start of the section and then adding the offset to the symbol, it will write a relocation record immediately to the symbol. The distinction is a necessary one due to a peculiarity of the dynamic linker.

A fuller explanation of how to use these relocation types for writing shared libraries entirely in NASM is given in section 9.2.

7.9.4 Thread Local Storage in ELF: `elf` Special Symbols and WRT

- In ELF32 mode, referring to an external global symbol using `wrt.tlsie` causes the linker to build an entry in the GOT containing the offset of the symbol within the TLS block, so you can access the value of the symbol with code such as:

```
mov  eax,[tid wrt ..tlsie]
mov  [gs:eax],ebx
```

- In ELF64/ELF32 mode, referring to an external global symbol using `wrt.gottpoff` causes the linker to build an entry in the GOT containing the offset of the symbol within the TLS block, so you can access the value of the symbol with code such as:

```
mov  rax,[rel tid wrt ..gottpoff]
mov  rcx,[fs:rax]
```

7.9.5 `elf` Extensions to the GLOBAL Directive

ELF object files can contain more information about a global symbol than just its address: they can contain the size of the symbol and its type as well. These are not merely debugger conveniences but are actually necessary when the program being written is a shared library. NASM therefore supports some extensions to the GLOBAL directive, allowing you to specify these features.

You can specify whether a global variable is a function or a data object by suffixing the name with a colon and the word `function` or `data`. (object is a synonym for data.) For example:

```
global  hashlookup:function, hashtable:data
```

exports the global symbol `hashlookup` as a function and `hashtable` as a data object.

Optionally you can control the ELF visibility of the symbol. Just add one of the visibility keywords: `default`, `internal`, `hidden`, or `protected`. The default is `default` of course. For example, to make `hashlookup` hidden:

```
global  hashlookup:function hidden
```

You can also specify the size of the data associated with the symbol as a numeric expression (which may involve labels, and even forward references) after the type specifier. Like this:

```
global  hashtable:data (hashtable.end - hashtable)
```

```
hashtable:
```

```
    db this,that,theother ; some data here
```

```
.end:
```

This makes NASM automatically calculate the length of the table and place that information into the ELF symbol table.

Declaring the type and size of global symbols is necessary when writing shared library code. For more information, see section 9.2.4.

7.9.6 elf Extensions to the COMMON Directive

ELF also allows you to specify alignment requirements on common variables. This is done by putting a number (which must be a power of two) after the name and size of the common variable, separated (as usual) by a colon. For example, an array of doublewords would benefit from 4-byte alignment.

```
common dwordarray 128:4
```

This declares the total size of the array to be 28 bytes, and requires that it be aligned on a 4-byte boundary.

7.9.7 16-bit code and ELF

The ELF32 specification doesn't provide relocation for 8 and 16-bit values, but the GNU linker adds these as an extension. NASM can generate GNU-compatible relocations to allow 16-bit code to be linked as ELF using GNU ld. If NASM is used with the `-w+gnu-elf-extensions` option, a warning is issued when one of these relocations is generated.

7.9.8 Debug formats and ELF

ELF provides debug information in STAB and DWARF formats. Line number information is generated for all executable sections, but please note that only the ".text" section is executed.

7.10 aout: Linux a.out Object Files

The aout format generates a.out object files, in the form used by early Linux systems (current Linux systems use ELF, see section 7.9). These differ from the a.out object files in that the magic number in the first four bytes of the file is different; also, some implementations of a.out, for example NetBSD's, support position-independent code, which Linux's implementation does not.

a.out provides a default output file-name extension of .o.

a.out is a very simple object format. It supports special directives, special symbols, and use of SEGWRIT and extensions. It supports only the three standard section names .text, .data and .bss.

7.11 aoutb: NetBSD/FreeBSD/OpenBSD a.out Object Files

The aoutb format generates a.out object files, in the form used by the various free BSD Unix clones, NetBSD, FreeBSD, and OpenBSD. For simple object files, this object format is exactly the same as a.out except for the magic number in the first four bytes of the file. However, the aoutb format supports position-independent code in the same way as the elf format, so you can use it to write BSD shared libraries.

aoutb provides a default output file-name extension of .o.

aoutb supports special directives, special symbols, and only the three standard section names .text, .data, and .bss. However, it also supports the same use of WRIT as elf does, to provide position-independent code relocation types. See section 7.9.3 for full documentation.

aoutb also supports the same extensions to the GLOBAL directive as elf does, see section 7.9. For documentation of this.

7.12 as86: Minix/Linux as86 Object Files

The Minix/Linux 16-bit assembler as86 has its own non-standard object file format. Although its companion linker ld86 produces something lost to ordinary a.out binaries as output, the object file format used to communicate between as86 and ld86 is not itself a.out.

NASM supports this format, just in case it is useful, as as86 provides a default output file-name extension of .o.

as86 is a very simple object format (from the NASM user's point of view). It supports no special directives, no use of SEG, WRT, and extensions to any standard directives. It supports only the three standard section names: .text, .data and .bss. The only special symbols supported is `..start`.

7.13 rdf: Relocatable Dynamic Object File Format

The default output format produces RDF Object Files (RDOFF, Relocatable Dynamic Object File Format) is a some-grown object file format designed alongside NASM itself and reflecting in its file format the internal structure of the assembler.

RDOFF is not used by any well-known operating systems. Those writing their own systems, however, may well wish to use RDOFF as their object format, on the ground that it is designed primarily for simplicity and contains very little file-header bureaucracy.

The Unix NASM archive, and the DOS archive which includes sources, both contain an `rdoff` subdirectory holding `getRDOFF` utilities, a `RDFinker`, a `RDFstatic-librarian`, a `RDFfile` dump utility, and a program which will load and execute an RDF executable under Linux.

`rdf` supports only the standard section names `.text`, `.data` and `.bss`.

7.13.1 Requiring a Library: The LIBRARY Directive

RDOFF contains a mechanism for an object file to demand a given library to be linked to the module, either at load time or runtime. This is done by the `LIBRARY` directive, which takes one argument which is the name of the module:

```
library mylib.rdl
```

7.13.2 Specifying a Module Name: The MODULE Directive

Special RDOFF header records are used to store the name of the module. It can be used, for example, by run-time loader to perform dynamic linking. `MODULE` directive takes one argument which is the name of current module:

```
module mymodname
```

Note that when you statically link modules and tell linker to strip the symbols from output file, all module names will be stripped too. To avoid it, you should start module names with `$`:

```
module $kernel.core
```

7.13.3 rdf Extensions to the GLOBAL Directive

RDOFF global symbols can contain additional information needed by the static linker. You can mark global symbols exported, thus telling the linker not to strip from a large executable or library file. Like in ELF, you can also specify whether an exported symbol is a procedure (function).

Suffixing the name with a colon and the word `export` you make the symbol exported:

```
global sys_open:export
```

To specify that exported symbol is a procedure (function), you add the word `proc` or `function` after declaration:


```
global sys_open:export proc
```

Similarly, to specify exported data object, add the word data or object to the directive:

```
global kernel_ticks:export data
```

7.13.4 rdf Extensions to the EXTERN Directive

By default the EXTERN directive declares pure external symbols. i.e. the static linker will complain if such symbol is not resolved. To declare an imported symbol which must be resolved later during dynamic linking phase, RDF offers an additional import modifier. As GLOBAL, you can also specify whether an imported symbol is a procedure (function) or data object.

```
library $libc
extern _open:import
extern _printf:import proc
extern _errno:import data
```

Here the directive LIBRARY is also included, which gives the dynamic linker a hint as to where to find requested symbols.

7.14 dbg: Debugging Format

The dbg format does not output object files as such; instead, it outputs a text file which contains a complete list of all the transactions between the main body of NASM and the output-format backend module. It is primarily intended for people who want to write their own output drivers, so that they can get a clearer idea of the various requests the main program makes of the output driver, and what order they happen.

For simple files, one can easily use the dbg format like this:

```
nasm -f dbg filename.asm
```

which will generate a diagnostic file called filename.dbg. However, this will not work well for files which were designed for a different object format, because each object format defines its own macros (usually user-level forms of directives), and those macros will not be defined in the dbg format. Therefore, to be safe, you can run NASM twice, in order to do the preprocessing with the native object format selected:

```
nasm -e -f rdf -o rdfprog.i rdfprog.asm
nasm -a -f dbg rdfprog.i
```

This preprocesses rdfprog.asm into rdfprog.i, keeping the native object format selected, in order to make sure all special directives are converted into primitive form correctly. Then the preprocessed source is fed through the dbg format to generate the final diagnostic output.

This workaround will still typically not work for programs intended for obj format, because the obj SEGMENT and GROUP directives have side effects of defining these segment and group names as symbols; dbg will not do this, so the program will not assemble. You will have to work around that by defining the symbols yourself (using EXTERN, for example) if you really need to get a dbg trace on an obj-specific source file.

dbg accepts any section name and any directives at all, and logs them all to its output.

dbg accepts and logs any %pragma, but the specific %pragma:

```
%pragma dbg maxdump <size>
```

where <size> is either a number or unlimited, can be used to control the maximum size for dumping the full contents of a raw data output object.

Chapter 8: Writing 16-bit Code (DOS, Windows 3/3.1)

This chapter attempts to cover some of the common issues encountered when writing 16-bit code to run under MS-DOS or Windows 3.x. It covers how to link programs to produce .EXE or .COM files, how to write .SYS device drivers, and how to interface assembly language code with 16-bit C compilers and with Borland Pascal.

8.1 Producing .EXE Files

Any large program written under DOS needs to be built as a .EXE file: only .EXE files have the necessary internal structure required to span more than one 64K segment. Windows programs also, have to be built as .EXE files, since Windows does not support the .COM format.

In general, you generate .EXE files by using the obj output format to produce one or more .OBJ files, and then linking them together using a linker. However, NASM also supports the direct generation of simple DOS .EXE files using the bin output format (by using `OB` and `OW` to construct the .EXE file header) and a macro package is supplied to do this. Thanks to Yan Guido for contributing the code for this.

NASM may also support .EXE natively as another output format in future releases.

8.1.1 Using the obj Format To Generate .EXE Files

This section describes the usual method of generating .EXE files by linking .OBJ files.

Most 16-bit programming language packages come with a suitable linker; if you have none of these, there is a free linker called `VAL`, available in LZH archive format from ftp.oulu.fi. An LZH archiver can be found at ftp.simtel.net. There is another 'free' linker (though this one doesn't come with sources) called `FREELINK`, available from www.pcorner.com. A third `djlink` written by D. Delorie, is available at www.delorie.com. A fourth linker, `ALINK`, written by Anthony A. J. Williams, is available at alink.sourceforge.net.

When linking several .OBJ files into a .EXE file, you should ensure that exactly one of them has a start point defined using the `.start` special symbol defined by the obj format (see section 7.4.6). If no module defines a start point, the linker will not know what value to give the entry-point field in the output file header; if more than one defines a start point, the linker will not know

An example of a NASM source file which can be assembled to a .OBJ file and linked on its own to a .EXE is given here. It demonstrates the basic principles of defining stack, initialising the segment registers, and declaring a start point. This file is also provided in the `subdirectory` of the NASM archives, under the name `objexe.asm`.

```
segment code
```

```
..start:
    mov     ax, data
    mov     ds, ax
    mov     ax, stack
    mov     ss, ax
    mov     sp, stacktop
```

This initial piece of code sets up `DS` point to the data segment, and initializes `SS` and `SP` point to the top of the provided stack. Notice that interrupts are implicitly disabled from one instruction after `movnt ss` precisely for this situation, so that there's a chance of an interrupt occurring between the loads of `SS` and `SP` and not having a stack to execute on.

Not also that the special symbol `._start` is defined at the beginning of this code, which means that will be the entry point into the resulting executable file.

```
mov     dx,hello
mov     ah,9
int     0x21
```

The above is the main program: load `DS:DX` with a pointer to the greeting message (hello is implicitly relative to the segment data, which was loaded into `DS` in the setup code, so the pointer is valid), and call the DOS print-string function.

```
mov     ax,0x4c00
int     0x21
```

This terminates the program using another DOS system call.

```
segment data
```

```
hello: db      'hello, world', 13, 10, '$'
```

The data segment contains the string we want to display.

```
segment stack stack
        resb 64
```

```
stacktop:
```

The above code declares a stack segment containing 64 bytes of uninitialized stack space and points `stacktop` at the top of it. The directive `segment stack stack` defines a segment called `stack`, and also of type `STACK`. The latter is not necessary for the correct running of the program, but linkers are likely to issue warnings or errors if your program has no segment of type `STACK`.

The above file, when assembled into a `OBJ` file, will link on its own to a valid `EXE` file, which when run will print 'hello, world' and then exit.

8.1.2 Using the bin Format To Generate .EXE Files

The `EXE` file format is simple enough that it's possible to build a `EXE` file by writing pure-binary program and sticking a 32-byte header on the front. This header is simple enough that it can be generated using `DB` and `DW` commands by `NASM` itself, so that you can use the bin output format to directly generate `.EXE` files.

Included in the `NASM` archives, in the `subdirectory` is `file.exebin.mam` macros. It defines three macros: `EXE_begin`, `EXE_stack` and `EXE_end`.

To produce a `.EXE` file using this method, you should start by using `%include` to load the `exebin.mam` macro package into your source file. You should then issue the `EXE_begin` macro call (which takes no arguments) to generate the file header data. Then write code as normal for the bin format—you can use all three standard sections: `text`, `.data` and `bss`. At the end of the file you should call the `EXE_end` macro (again, no arguments), which defines some symbols to mark section sizes, and these symbols are referred to in the header code generated by `EXE_begin`.

In this model, the code you end up writing starts at `0x100`, just like a `COM` file. In fact, if you strip off the 32-byte header from the resulting `EXE` file, you will have a valid `COM` program. All the segment bases are the same, so you are limited to a 64K program, again just like a `COM` file. Note that an `ORG` directive is issued by the `EXE_begin` macro, so you should not explicitly issue one.

You can't directly refer to your segment base value, unfortunately, since this would require relocation in the header, and things would get a lot more complicated. So you should get your segment base by copying it out of `CS` instead.

On entry to your .EXE file, SS:SP are already set up to point to the top of 64K stack. You can adjust the default stack size of 2K by calling the EXE_stack macro. For example, to change the stack size of your program to 64 bytes, you would call EXE_stack 64.

A sample program which generates a .EXE file in this way is given in the tests subdirectory of the NASM archive, as binexe.asm.

8.2 Producing .COM Files

While large DOS programs must be written as EXE files, small ones are often better written as .COM files. .COM files are pure binary, and therefore most easily produced using the bin

8.2.1 Using the bin Format To Generate .COM Files

.COM files are expected to be loaded at offset 100h into the i386 segment (though this segment may change). Execution then begins at 100h, i.e. right at the start of the program. So to write a .COM program, you would create a source file looking like

```
org 100h

section .text

start:
    ; put your code here

section .data

    ; put data items here

section .bss

    ; put uninitialized data here
```

The bin format puts the .text section first in the file, so you can declare data or BSS items before beginning to write code if you want to and the code will still end up at the front of the file where it belongs.

The BSS (uninitialized data) section does not take up space in the .COM file itself; instead, addresses of BSS items are resolved to point to space beyond the end of the file, on the grounds that this will be free memory when the program is run. Therefore you should not rely on your BSS being initialized to all zeros when you run.

To assemble the above program, you should use a command line like

```
nasm myprog.asm -fbin -o myprog.com
```

The bin format would produce a file called myprog if no explicit output file name was specified, so you have to override it and give the desired file name.

8.2.2 Using the obj Format To Generate .COM Files

If you are writing a .COM program as more than one module, you may wish to assemble several .OBJ files and link them together into a .COM program. You can do this, provided you have a linker capable of outputting .COM files directly (TLINK does this) or alternatively convert a program such as EXE2BIN to transform the .EXE file output from the linker into a .COM file.

If you do this, you need to take care of several things:

- The first object file containing code should start its code segment with a `ljmp $, 0` (or `ljmp $, 0x0000`). This is to ensure that the code begins at offset 100h relative to the beginning of the code segment, so

that the linker or converted program does not have to adjust address references within the file when generating the COM file. Other assemblers use an `ORG` directive for this purpose, but `ORG` in NASM is a format-specific directive to the output format, and does not mean the same thing as it does in MASM-compatible assemblers.

- You don't need to define a stack segment.
- All your segments should be in the same group, so that every time your code or data references a symbol offset, it is relative to the same segment base. This is because when a COM file is loaded, all the segment registers contain the same value.

8.3 Producing .SYS Files

MS-DOS device drivers, SY files, are pure binary files, similar to COM files, except that they start at origin zero rather than 100h. Therefore, if you are writing device drivers in the i format, you do not need the `ORG` directive, since the default origin for bin is zero. Similarly, if you are using obj, you do not need the `RESB 100h` at the start of your code segment.

.SY files start with a header structure containing pointers to the various routines inside the driver which do the work. This structure should be defined at the start of the code segment, even though it is not actually code.

For more information on the format of SY files, and the data which has to go in the header structure, a list of books is given in the Frequently Asked Questions list for the newsgroup `comp.os.msdos.programmer`.

8.4 Interfacing to 16-bit C Programs

This section covers the basics of writing assembly routines that all are called from programs. To do this, you would typically write an assembly module as a .OBJ file, and link it with your modules to produce a mixed-language program.

8.4.1 External Symbol Names

Compilers have the convention that the names of all global symbols (functions or data) they define are formed by prefixing an underscore to the name as it appears in the program. So, for example, the function a C programmer thinks of as `printf` appears to an assembly language programmer as `_printf`. This means that in your assembly programs, you can define symbols without a leading underscore, and not have to worry about name clashes with C symbols.

If you find the underscores inconvenient, you can define a macro to replace the `GLOBAL` and `EXTERN` directives as follows:

```
%macro  cglobal 1

    global  _%1
    %define %1 _%1

%endmacro

%macro  cextern 1

    extern  _%1
    %define %1 _%1

%endmacro
```

(These forms of the macros only take one argument at a time; a `%rep` construct could do better.) If you then declare an external like this:

`cextern printf`

then the macro will expand it as

```
extern _printf
#define printf _printf
```

Thereafter, you can reference `printf` as if it was a symbol, and the preprocessor will put the leading underscore on where necessary.

The global macro works similarly. You must use `global` before defining the symbol in question, but you would have had to do that anyway if you used `GLOBAL`.

Also see section 2.1.28.

8.4.2 Memory Models

NASM contains mechanisms to support the various memory models directly; you have to keep track yourself of which one you are writing for. This means you have to keep track of the

- In models using a single code segment (tiny, small, and compact), functions are near. This means that function pointers are 32 bits long, data segments are pushed on the stack, function arguments, and 6 bits long and contain only a 6-bit offset field (the `EIP` register never changes its value and always gives the segment part of the full function address), and that functions are called using ordinary `near CALL` instructions and return using `RET` (which, in NASM, is synonymous with `RETN`). This means both that you should write your own routines to return with `RET`, and that you should call external C routines with `near CALL` instructions.
- In models using more than one code segment (medium, large, and huge), functions are far. This means that function pointers are 32 bits long (consisting of a 16-bit offset followed by a 16-bit segment), and that functions are called using `CALL FAR` (or `CALL seg:offset`) and return using `RETF`. Again, you should therefore write your own routines to return with `RETF` and use `CALL FAR` to call external routines.
- In models using a single data segment (tiny, small, and medium), data pointers are 64 bits long, containing only a 6-bit offset field (the `EIP` register doesn't change its value and always gives the segment part of the full data item address).
- In models using more than one data segment (compact, large, and huge), data pointers are 32 bits long, consisting of a 16-bit offset followed by a 16-bit segment. You should still be careful not to modify your routines without restoring afterwards, but it's free for you to use the contents of 32-bit data pointers you are passed.
- The huge memory model allows single data items to exceed 64 KiB size. In all the memory models, you can access the whole data item just by doing arithmetic on the offset field of the pointer you are given, whether the segment field is present or not; in huge model, you have to be more careful of your pointer arithmetic.
- In most memory models, there is a *default* data segment, whose segment address is kept in `DS` throughout the program. This data segment is typically the same segment as the stack, kept in `SS`, so that functions' local variables (which are stored on the stack) and global data items can both be accessed easily without changing `DS`. Particularly, large data items are typically stored in other segments. However, some memory models (though not the standard ones, usually) allow the assumption that `SS` and `DS` hold the same value and be removed. Be careful about functions' local variables in this latter case.

In models with a single code segment, the segment is called `_TEXT`, so your code segment must also go by this name in order to be linked into the same place as the main code segment. In models with a single data segment, or with a default data segment, it is called `_DATA`.

8.4.3 Function Definitions and Function Calls

The calling convention in 6-bi programs is as follows. In the following description the words *caller* and *callee* are used to denote the function doing the calling and the function which gets called.

- The caller pushes the function's parameters on the stack, in reverse order (right to left, so that the first argument specified to the function is pushed last).
- The caller then executes a CALL instruction to pass control to the callee. This CALL is either near or far depending on the memory model.
- The callee receives control, and typically (although this is not actually necessary, if functions which do not need to access their parameters) starts by saving the value of SP in BP, so as to be able to use BP as a pointer to find parameters on the stack. However, the callee was probably doing this too, so part of the calling convention states that BP must be preserved by any function. Hence the callee, if it is going to set up BP as a *frame pointer*, must push the previous value of BP.
- The callee may then access its parameters relative to BP. The word at [BP] holds the previous value of BP as it was pushed; the next word, at [BP+2], holds the offset part of the return address, pushed implicitly by CALL. In a small-model (near) function the parameter starts after that at [BP+4]; in a large-model (far) function the segment part of the return address lives at [BP+4], and the parameter begins at [BP+6]. The leftmost parameter of the function, since it was pushed last, is accessible at this offset from BP; the others follow at successively greater offsets. Thus in a function such as `printf` which takes a variable number of parameters, the pushing of the parameters in reverse order means that the function knows where to find its first parameter which tells it the number and type of the remaining ones.
- The callee may also wish to decrease SP further, so as to allocate space on the stack for local variables, which will then be accessible at negative offsets from BP.
- The callee, if it wishes to return a value to the caller, should leave the value in AL, AX or DX:AX depending on the size of the value. Floating-point results are sometimes (depending on the compiler) returned in ST0.
- Once the callee has finished processing, it restores SP from BP if it had allocated local stack space, then pops the previous value of BP, and returns via RETN or RETF depending on memory model.
- When the caller regains control from the callee, the function parameters are still on the stack, so it typically adds an immediate constant to SP to remove them (instead of executing a number of `POP` instructions). Thus, if a function is accidentally called with the wrong number of parameters due to a prototype mismatch, the stack will still be returned to a sensible state since the caller, which *knows* how many parameters it pushed, does the removing.

It is instructive to compare this calling convention with that of a Pascal program (described in section 8.5.1). Pascal has simpler conventions since functions have a variable number of parameters. Therefore the callee knows how many parameters it should have been passed and is able to deallocate them from the stack itself by passing an immediate argument to the `RET` or `RETF` instruction, so the caller does not have to do it. Also, the parameters are pushed in left-to-right order, not right-to-left, which means that a compiler can give better guarantees about sequence points without performance suffering.

Thus, you would define a function in C style in the following way. The following example is for a small model:

```
global _myfunc

_myfunc:
    push    bp
    mov     bp, sp
```



```

sub     sp,0x40          ; 64 bytes of local stack space
mov     bx,[bp+4]        ; first parameter to function

; some more code

mov     sp,bp            ; undo "sub sp,0x40" above
pop     bp
ret

```

For a large-model function, you would replace RET by RETF, and look for the first parameter at [BP+6] instead of [BP+4]. Of course, if one of the parameters is a pointer, then the offsets of subsequent parameters will change depending on the memory model, as well as a pointer takes four bytes on the stack when passed as a parameter, whereas near pointers take up two. At the end of the process, to call a function from your assembly code, you would do something like this:

```

extern _printf

; and then, further down...

push    word [myint]      ; one of my integer variables
push    word mystring     ; pointer into my data segment
call    _printf
add     sp,byte 4         ; 'byte' saves space

; then those data items...

```

```

segment _DATA

```

```

myint    dw    1234
mystring db    'This number -> %d <- should be 1234',10,0

```

This piece of code is the small-model assembly equivalent of the C code

```

int myint = 1234;
printf("This number -> %d <- should be 1234\n", myint);

```

In a large model, the function-call code might look more like this. In this example, it is assumed that DS already holds the segment base of the segment _DATA. If not, you would have to initialize it.

```

push     word [myint]
push     word seg mystring ; Now push the segment, and...
push     word mystring    ; ... offset of "mystring"
call     far _printf
add     sp,byte 6

```

The integer value still takes up one word on the stack, since a large model does not affect the size of the int data type. The first argument (pushed last) to printf, however, is a pointer, and therefore has to contain a segment and offset part. These segments should be stored second in memory, and therefore must be pushed first. (Of course, PUSHDS would have been a shorter instruction than PUSHWORD SEG mystring, if DS was set up as the above example assumed.) Then the actual call becomes a far call, since functions expect far calls in a large model, and DS has been increased by 6 rather than 4 afterwards to make up for the extra word of parameters.

8.4.4 Accessing Data Items

To get the contents of variables or to declare variables which can be accessed, you need only declare the names as `GLOBAL` or `EXTERN`. (Again, the names require leading underscores as stated in section 8.4.1.) Thus, a C variable declared as `int i` can be accessed from assembler as

```
extern _i
```

```
mov ax, [_i]
```

And to declare your own integer variable which programs can access as `extern int j`, you do this (making sure you are assembling in the `_DATA` segment, if necessary):

```
global _j
```

```
_j      dw      0
```

To access an array, you need to know the size of the component of the array. For example, `int` variables are two bytes long, so if a program declares an array as `inta[10]`, you can access `a[3]` by doing `mov ax, [_a+6]`. (The byte offset is obtained by multiplying the desired array index, 3, by the size of the array element, 2.) The sizes of the basic types in 16-bit compilers are: for `char`, 2, for `short` and `int`, 4, for `long` and `float`, and 8 for `double`.

To access a data structure, you need to know the offset from the base of the structure to the field you are interested in. You can do this by converting the structure definition into a NASM structure definition (using `STRUC`), or by calculating the one offset and using just that.

To do either of these, you should read your compiler's manual to find out how it organizes data structures. NASM gives no special alignment to structure members in its own `STRUC` macro, so you have to specify alignment yourself if the compiler generates it. Typically, you might find a data structure like

```
struct {
    char c;
    int i;
} foo;
```

might be four bytes long rather than three, since the `int` field would be aligned to a two-byte boundary. However, this sort of feature tends to be a configurable option in the compiler, either using command-line options or `#pragma` lines, so you have to find out how your own compiler

8.4.5 c16.mac: Helper Macros for the 16-bit C Interface

Included in the NASM archives, in the `misc` directory, is file `c16.mac` of macros. It defines three macros `proc`, `arg`, and `endproc`. These are intended to be used for C-style procedure definitions, and they automate a lot of the work involved in keeping track of the calling convention.

(An alternative TASM-compatible form of `arg` is also built into NASM's preprocessor. See section 4.8 for details.)

An example of an assembly function using the macro set is given here:

```
proc    _nearproc

%i      arg
%j      arg
    mov     ax, [bp + %i]
    mov     bx, [bp + %j]
    add     ax, [bx]
```

```
endproc
```

This defines `_nearproc` as a procedure taking two arguments, the first (`i`) an integer and the second (`j`) a pointer to an integer. It returns `i + *j`.

Note that the `arg` macro has an `EQ` as the first line of its expansion, and since the label before the macro call gets prepended to the first line of the expanded macro, the `EQ` works, defining `$$i` to be an offset from BP. A context-local variable is used, local to the context pushed by the `proc` macro and popped by the `endproc` macro, so that the same argument name can be used in later procedures. Of course, you don't *have* to do that.

The macro produces code for one of two function types (tiny, small and compact-model code by default. You can have it generate far functions (medium, large and huge-model code) by means of coding `%define FARCODE`. This changes the kind of return instruction generated by `endproc`, and also changes the starting point for the argument offsets. The macro set contains no intrinsic dependencies on whether data pointers are far or not.

`arg` takes an optional parameter, giving the size of the argument. If no size is given, 2 is assumed, since it is likely that many function parameters will be of type `int`.

The large-model equivalent of the above function would look like this:

```
%define FARCODE
```

```
proc    _farproc
```

```
    %$i    arg
    %$j    arg        4
            mov     ax, [bp + %$i]
            mov     bx, [bp + %$j]
            mov     es, [bp + %$j + 2]
            add     ax, [bx]
```

```
endproc
```

This makes use of the `arg` macro to define a parameter of size 4, because `j` is now a far pointer. When we load from `j`, we must load a segment and an offset.

8.5 Interfacing to Borland Pascal Programs

Interfacing to Borland Pascal programs is similar in concept to interfacing to 16-bit programs. The differences are:

- The leading underscore required for interfacing to C programs is not required for Pascal.
- The memory model is always large: functions are far, data pointers are far, and data items can be more than 64K long. (Actually, some functions are near, but only those functions that are local to a Pascal unit and never called from outside it. All assembly functions that a Pascal calls and all Pascal functions that assembly routines are able to call are far. However, all static data declared in a Pascal program goes into the default data segment, which is then whose segment address will be in DS when control is passed to your assembly code. The only things that do not live in the default data segment are local variables (they live in the stack segment) and dynamically allocated variables. All data *pointers*, however, are far.
- The function calling convention is different - described below.
- Some data types, such as strings, are stored differently.

- There are restrictions on the segment names you are allowed to use. Borland Pascal will ignore code or data declared in a segment it doesn't like the name of. The restrictions are:

8.5.1 The Pascal Calling Convention

The 6-bit Pascal calling convention is as follows. In the following description, the words *caller* and *callee* are used to denote the function doing the calling and the function which gets called.

- The caller pushes the function's parameters on the stack, one after another, in normal order (left to right, so that the first argument specified to the function is pushed first).
- The caller then executes a far CALL instruction to pass control to the callee.
- The callee receives control, and typically (although this is actually necessary if functions which do not need to access their parameters) starts by saving the value of SP in BP, so as to be able to use BP as a pointer to find the parameters on the stack. However, the callee was probably doing this too, so part of the calling convention states that BP must be preserved by any function. Hence the callee, if it is going to set up BP as a frame pointer, must push the previous value of BP.
- The callee may then access its parameters relative to BP. The word at [BP] holds the previous value of BP as it was pushed. The next word, at [BP+2], holds the offset part of the return address, and the next one at [BP+4] the segment part. The parameters begin at [BP+6]. The rightmost parameter of the function, since it was pushed last, is accessible at this offset from BP; the others follow, at successively greater offsets.
- The callee may also wish to decrease SP further, so as to allocate space on the stack for local variables, which will then be accessible at negative offsets from BP.
- The callee, if it wishes to return a value to the caller, should leave the value in AL, AX or DX:AX depending on the size of the value. Floating-point results are returned in ST0. Results of type Real (Borland's own custom floating-point data type, not handled directly by the CPU) are returned in DX:BX:AX. To return a result of type String, the caller pushes a pointer to a temporary string before pushing the parameters, and the callee places the returned string at the location the pointer is not a parameter, and should not be removed from the stack by the RETF instruction.
- Once the callee has finished processing, it restores SP from BP if it had allocated local stack space, then pops the previous value of BP, and returns via RETF. It uses the form of RETF with an immediate parameter, giving the number of bytes taken up by the parameters on the stack. This causes the parameters to be removed from the stack as a side effect of the return.
- When the caller regains control from the callee, the function parameters have already been removed from the stack, so it needs to do nothing further.

Thus, you would define a function in Pascal style, taking two integer-type parameters, in the following way:

```
global myfunc

myfunc: push    bp
        mov     bp, sp
        sub     sp, 0x40          ; 64 bytes of local stack space
        mov     bx, [bp+8]        ; first parameter to function
        mov     bx, [bp+6]        ; second parameter to function

        ; some more code

        mov     sp, bp            ; undo "sub sp, 0x40" above
        pop     bp
        retf    4                 ; total size of params is 4
```

At the other end of the process, to call a Pascal function from your assembly code, you would do something like this:

```
extern  SomeFunc

        ; and then, further down...

        push    word seg mystring    ; Now push the segment, and...
        push    word mystring        ; ... offset of "mystring"
        push    word [myint]         ; one of my variables
        call    far SomeFunc
```

This is equivalent to the Pascal code

```
procedure SomeFunc(String: PChar; Int: Integer);
    SomeFunc(@mystring, myint);
```

8.5.2 Borland Pascal Segment Name Restrictions

Since Borland Pascal's internal file format is completely different from OBJ, it only makes very sketchy jobs of actually reading and understanding the various information contained in a OBJ file when it links that in. Therefore, an object file intended to be linked to a Pascal program must obey a number of restrictions:

- Procedures and functions must be in a segment whose name is either CODE, CSEG, or something ending in _TEXT.
- initialized data must be in a segment whose name is either CONST or something ending in _CONST.
- Uninitialized data must be in a segment whose name is either DATA, DSEG, or something ending in _BSS.
- Any other segments in the object file are completely ignored. GROUP directives and segment attributes are also ignored.

8.5.3 Using c16.mac With Pascal Programs

The c16.mac macro package described in section 8.4.5 can be used to simplify writing functions to be called from Pascal programs, if you code `%define PASCAL`. This definition ensures that functions are far (it implies FARCODE) and also cause procedure return instructions to be generated with an operand.

Defining PASCAL does not change the code which calculates the argument offsets, you must declare your function's arguments in reverse order. For example:

```
%define PASCAL

proc    _pascalproc

    %$j    arg 4
    %$i    arg
            mov     ax, [bp + %$i]
            mov     bx, [bp + %$j]
            mov     es, [bp + %$j + 2]
            add     ax, [bx]

endproc
```

This defines the same routine conceptually as the example in section 8.4.5, it defines a function taking two arguments, an integer and a pointer to an integer, which returns the sum of the integer and the

contents of the pointer. The only difference between this code and the large-mode version is that PASCAL is defined instead of FARCODE, and that the arguments are declared in reverse

Chapter 9: Writing 32-bit Code (Unix, Win32, DJGPP)

This chapter attempts to cover some of the common issues involved when writing 32-bit code to run under Win32 or Unix, or to be linked with code generated by Unix-style compilers such as DJGPP. It covers how to write assembly code to interface with 32-bit C routines, and how to write position-independent code for shared libraries.

Almost all 32-bit code, and in particular all code running under Win32, DJGPP or any of the Unix variants, runs in a flat memory model. This means that the segment registers and paging have already been set up to give you the same 32-bit 4G address space no matter what segment you work relative to, and that you should ignore segment registers completely. When writing flat-mode application code, you never need to use segment overrides, modify any segment register, and the code-section addresses you pass to CALL and JMP live in the same address space as the data-section addresses you access your variables by, and the stack-section addresses you access local variables and procedure parameters by. Every address is 32 bits long and contains only an offset part.

9.1 Interfacing to 32-bit C Programs

All of the discussion in section 8.4 about interfacing to 16-bit programs still applies when working in 32 bits. The absence of memory models or segmentation worries simplifies things a

9.1.1 External Symbol Names

Most 32-bit compilers share the convention used by 16-bit compilers that the names of all global symbols (functions or data) they define are formed by prefixing an underscore to the name as it appears in the program. However, not all of them do: the ELF specification states that symbols do *not* have a leading underscore on their assembly-language names.

The older Linux a.out compiler, all Win32 compilers, DJGPP, and NetBSD and FreeBSD, all use the leading underscore; for these compilers the macro `extern` and `global` as given in section 8.4.1, will still work. For ELF, though, the leading underscore should not be used.

See also section 2.1.28.

9.1.2 Function Definitions and Function Calls

The calling convention in 32-bit programs is as follows. In the following description, the words *caller* and *callee* are used to denote the function doing the calling and the function which ge

- The callee pushes the function's parameters on the stack, in reverse order (right to left, so that the first argument specified to the function is pushed last).
- The caller then executes a near CALL instruction to pass control to the callee.
- The callee receives control, and typically (although this is not actually necessary, if functions do not need to access their parameters) starts by saving the value of ESI in EBP, so as to be able to use EBP as a base pointer to find its parameters on the stack. However, the caller was probably doing this too, so part of the calling convention states that EBP must be preserved by any function. Hence the callee, if it is going to set up EBP as a frame pointer, must push the p
- The callee may then access its parameters relative to EBP. The double word at [EBP] holds the previous value of EBP as it was pushed; the next double word, at [EBP+4], holds the return address pushed implicitly by CALL. The parameters start after that at [EBP+8]. The leftmost parameter of the function, since it was pushed last, is accessible at this offset from EBP; the others follow at successively greater offsets. Thus, in functions such as `printf` which takes a variable number of parameters, the pushing of the parameters in reverse order means that the function knows where to find its first parameter, which tells it the number and type of the

- The callee may also wish to decrease ESP further, so as to allocate space on the stack for local variables, which will then be accessible at negative offsets from EBP.
- The callee, if it wishes to return a value to the caller, should leave the value in AL, AX or EAX depending on the size of the value. Floating-point results are typically returned
- Once the callee has finished processing, it restores ESP from EBP if it had allocated local stack space, then pops the previous value of EBP, and returns via RET (equivalently, RETI).
- When the caller regains control from the callee, the function parameters are still on the stack, it typically adds an immediate constant to ESP to remove them (instead of executing a number of slow POP instructions). Thus, if a function is accidentally called with the wrong number of parameters due to a prototype mismatch, the stack will still be returned to a sensible state since the caller, which *knows* how many parameters it pushed, does the removing.

There is an alternative calling convention used by Win32 programs for Windows API calls and also for functions called by the Windows API. Such window procedures follow what Microsoft calls the `__stdcall` convention. This is slightly closer to the Pascal convention, in that the callee cleans the stack by passing parameters to the RET instruction. However, the parameters are still pushed in right-to-left order.

Thus, you would define a function in C style in the following way:

```
global _myfunc

_myfunc:
    push    ebp
    mov     ebp, esp
    sub     esp, 0x40          ; 64 bytes of local stack space
    mov     ebx, [ebp+8]      ; first parameter to function

    ; some more code

    leave                    ; mov esp, ebp / pop ebp
    ret
```

At the end of the process, to call a function from your assembly code, you would do something like this:

```
extern _printf

    ; and then, further down...

    push    dword [myint]    ; one of my integer variables
    push    dword mystring   ; pointer into my data segment
    call    _printf
    add     esp, byte 8       ; 'byte' saves space

    ; then those data items...
```

```
segment _DATA
```

```
myint      dd    1234
mystring    db    'This number -> %d <- should be 1234', 10, 0
```

This piece of code is the assembly equivalent of the C code

```
int myint = 1234;
printf("This number -> %d <- should be 1234\n", myint);
```


9.1.3 Accessing Data Items

To get at the contents of variables or to declare variables which can be accessed, you need only declare the names as `GLOBAL` or `EXTERN`. (Again, the names require leading underscores, as stated in section 9.1.1.) Thus, a C variable declared as `int i` can be accessed from assembler as

```
extern _i
mov eax, [_i]
```

And to declare your own integer variable which programs can access as `extern int j`, you do this (making sure you are assembling in the `__DATA` segment, if necessary):

```
global _j
__j      dd 0
```

To access a C array, you need to know the size of the component of the array. For example, `int` variables are four bytes long, so if a program declares an array as `inta[10]`, you can access `a[3]` by doing `mov ax, [_a+12]`. (The byte offset is obtained by multiplying the desired array index 3, by the size of the array element, 4.) The sizes of the basic types in 32-bit compilers are: 1 for `char`, 2 for `short`, 4 for `int`, `long` and `float`, and for `double` pointers, being 32-bit addresses, are also 4 bytes long.

To access a data structure, you need to know the offset from the base of the structure to the field you are interested in. You can do this by converting the structure definition into a NASM structure definition (using `STRUC`), or by calculating the one offset and using just that.

To do either of these, you should read your compiler's manual to find out how it organizes data structures. NASM gives no special alignment to structure members in its own `STRUC` macro, so you have to specify alignment yourself if the compiler generates it. Typically, you might find a data structure like

```
struct {
    char c;
    int i;
} foo;
```

might be eight bytes long rather than five, since the `int` field would be aligned to a four-byte boundary. However, this sort of feature is sometimes a configurable option in the compiler, either using command-line options or `#pragma` lines, so you have to find out how your own compiler does it.

9.1.4 c32.mac: Helper Macros for the 32-bit C Interface

Included in the NASM archives, in the `misc` directory, is file `c32.mac` of macros. It defines three macros `proc`, `arg`, and `endproc`. These are intended to be used for C-style procedure definitions, and they automate a lot of the work involved in keeping track of the calling conventions.

An example of an assembly function using the macro set is given here:

```
proc      _proc32

%$i      arg
%$j      arg
        mov     eax, [ebp + %$i]
        mov     ebx, [ebp + %$j]
        add     eax, [ebx]

endproc
```

This defines `_proc32` to be a procedure taking two arguments, the first (`i`) an integer and the second (`j`) a pointer to an integer. It returns `i + *j`.

Note that the `arg` macro has an `EQU` as the first line of its expansion, and since the label before the macro call gets prepended to the first line of the expanded macro, the `EQU` works, defining `$$` to be an offset from `BP`. A context-local variable is used, local to the context pushed by the `pro` macro and popped by the `endpro` macro, so that the same argument name can be used in later procedures. Of course, you don't *have* to do that.

`arg` can take an optional parameter, giving the size of the argument. If no size is given, 4 is assumed, since it is likely that many function parameters will be of type `int` or pointers.

9.2 Writing NetBSD/FreeBSD/OpenBSD and Linux/ELF Shared Libraries

ELF replaced the older `a.out` object file format under Linux because it contains support for position-independent code (PIC) which makes writing shared libraries much easier. NASM supports the ELF position-independent code features, so you can write Linux ELF shared libraries.

NetBSD and its close cousins FreeBSD and OpenBSD take a different approach by hacking PIC support into the `a.out` format. NASM supports this as the `a.out` output format, so you can write BSD shared libraries in NASM too.

The operating system loads a PIC shared library by memory-mapping the library file at an arbitrarily chosen point in the address space of the running process. The contents of the library's `.code` section must therefore not depend on where it is loaded in memory.

Therefore, you cannot get at your variables by writing code like this:

```
mov     eax, [myvar]           ; WRONG
```

Instead, the linker provides an area of memory called the *global offset table*, or GOT; the GOT is situated at a constant distance from your library's `.code`, so if you can find out where your library is loaded (which is typically done using `CALL` and `POP` combination), you can obtain the address of the GOT, and you can then load the addresses of your variables out of linker-generated entries.

The `.data` section of a PIC shared library does not have these restrictions since the `.data` section is writable, it has to be copied into memory anyway rather than just paged in from the library file, so as long as it's being copied it can be relocated too. So you can put ordinary types of relocation in the `.data` section without too much worry (but see section 9.2.4 for a caveat).

9.2.1 Obtaining the Address of the GOT

Each code module in your shared library should define the GOT as an external symbol:

```
extern _GLOBAL_OFFSET_TABLE_ ; in ELF
extern __GLOBAL_OFFSET_TABLE_ ; in BSD a.out
```

At the beginning of any function in your shared library which plans to access your `.data` or `.bss` sections, you must first calculate the address of the GOT. This is typically done by writing the function in this form:

```
func:  push    ebp
        mov     ebp, esp
        push    ebx
        call    .get_GOT
.get_GOT:
        pop     ebx
        add     ebx, _GLOBAL_OFFSET_TABLE_ + $$ - .get_GOT wrt ..gotpc

        ; the function body comes here

        mov     ebx, [ebp-4]
        mov     esp, ebp
```

```

    pop    ebp
    ret

```

(For BSD, again, the symbol `_GLOBAL_OFFSET_TABLE` requires a second leading underscore)

The first two lines of this function are simply the standard prologue to setup stack frame, and the last three lines are standard function epilogue. The third line, and the fourth as well, save and restore the EBX register, because PIC shared libraries use this register to store the

The interesting bit is the `CALL` instruction and the following two lines. The `CALL` and `POP` combination obtains the address of the label `get_GOT`, without having to know in advance where the program was loaded (since the `CALL` instruction encodes relative to the current position). The `ADD` instruction makes use of one of the special PIC relocation types: `GOTPC relocation`. With the `WRT..gotpc` qualifier specified, the symbol referenced here `_GLOBAL_OFFSET_TABLE_`, the special symbol assigned to the GOT, is given an offset from the beginning of the section. (Actually `ELF` encodes it as the offset from the operand field of the `ADD` instruction, but `NASM` simplifies this deliberately, so do things the same way for both `ELF` and `BSD`.) So the instruction then adds the beginning of the section, to get the real address of the GOT, and subtracts the value of `get_GOT` which it knows is in `EBX`. Therefore, by the time that instruction has finished, `EBX` contains the address of the

If you didn't follow what I don't worry it's not necessary to obtain the address of the GOT by any other means, so you can put those three instructions into a macro and safely ignore them:

```

%macro    get_GOT 0

    call    %%getgot
%%getgot:
    pop     ebx
    add     ebx, _GLOBAL_OFFSET_TABLE_ + $$ - %%getgot wrt ..gotpc

%endmacro

```

9.2.2 Finding Your Local Data Items

Having got the GOT, you can then use it to obtain the addresses of your data items. Most variables will reside in the sections you have declared, they can be accessed using the `.gotoff` special `WRT` type. The way this works is like this:

```

    lea     eax, [ebx+myvar wrt ..gotoff]

```

The expression `myvar wrt ..gotoff` is calculated, when the shared library is linked, to be the offset to the local variable `myvar` from the beginning of the GOT. Therefore, adding it to `EBX` as above will place the real address of `myvar` in `EAX`.

If you declare variables as `GLOBAL` without specifying size for them, they are shared between code modules in the library but do not get exported from the library to the program that loaded it. They will still be in your ordinary data and BSS sections, so you can access them in the same way as local variables, using the above `..gotoff` mechanism.

Note that due to a peculiarity of the way `BSD.out` format handles this relocation type, there must be at least one non-local symbol in the same section as the address you're trying to access.

9.2.3 Finding External and Common Data Items

If your library needs to get at an external variable (external to the library, not just one of the modules within it), you must use the `.gottyp` and `getatit`. The `.gottyp`, instead of giving you the offset from the GOT base to the variable, gives you the offset from the GOT base to a GOT entry containing the address of the variable. The linker will put this GOT entry when it builds the library, and the dynamic linker will place the correct address in it at load time. So to obtain the address of an external variable `extvar` in `EAX`, you would code

```
mov     eax,[ebx+extvar wrt ..got]
```

This loads the address of extvar out of an entry in the GOT. The linker, when it builds the shared library, collects together every relocation of type .got, and builds the GOT to ensure that every necessary entry is present.

Common variables must also be accessed in this way.

9.2.4 Exporting Symbols to the Library User

If you want to export symbols to the user of the library, you have to declare whether they are functions or data, and if they are data, you have to give the size of the data item. This is because the dynamic linker has built procedure linkage table entries for any exported functions and it moves exported data items away from the library's data section in which they were declared.

So to export a function to users of the library, you must use

```
global func:function          ; declare it as a function

func:  push    ebp

      ; etc.
```

And to export a data item such as an array, you would have to code

```
global array:data array.end-array    ; give the size too

array: resd    128
.end:
```

Be careful if you export a variable to the library user by declaring it as GLOBAL and supplying a size, the variable will end up living in the data section of the main program rather than in your library's data section, where you declared it. So you will have to access your own global variable with the .got mechanism rather than ..gotoff, as if it were external (which, effectively, it has become).

Equally, if you need to store the address of an exported global in one of your data sections, you can't do it by means of the standard sort of code:

```
dataptr:      dd      global_data_item      ; WRONG
```

NASM will interpret this code as an ordinary relocation, in which global_data_item is merely an offset from the beginning of the data section (whatever), so this reference will end up pointing at your data section instead of at the exported global which resides elsewhere.

Instead of the above code, then, you must write

```
dataptr:      dd      global_data_item wrt ..sym
```

which makes use of the special WRType ..sym to instruct NASM to search the symbol table for a particular symbol at that address, rather than just relocating by section base.

Either method will work for functions: referring to one of your functions by means of

```
funcptr:      dd      my_function
```

will give the user the address of the code you wrote, whereas

```
funcptr:      dd      my_function wrt ..sym
```

will give the address of the procedure linkage table for the function, which is where the calling program will *believe* the function lives. Either address is a valid way to call the function.

9.2.5 Calling Procedures Outside the Library

Calling procedures outside your shared library has been done by means of `procedure linkage table`, or PLT. The PLT is placed at a known offset from where the library is loaded, so the library code can make calls to the PLT in a position-independent way. Within the PLT there is code to jump to offsets contained in the GOT, so function calls to other shared libraries or routines in the main program can be transparently passed off to their real destinations.

To call an external routine, you must use another special relocation type, `WRT.plt`. This is much easier than the GOT-based ones: you simply replace calls such as `CALL printf` with the PLT-relative version `CALL printf WRT ..plt`.

9.2.6 Generating the Library File

Having written some code modules and assembled them to .o files, you then generate your shared library with a command such as

```
ld -shared -o library.so module1.o module2.o      # for ELF
ld -Bshareable -o library.so module1.o module2.o  # for BSD
```

For ELF, if your shared library is going to reside in system directories such as `/usr/lib` or `/lib`, it is usually worth using the `-soname` flag to the linker to store the final library file name, with a version number, into the library:

```
ld -shared -soname library.so.1 -o library.so.1.2 *.o
```

You would then copy `library.so.1.2` into the library directory, and create `library.so.1` as a symbolic link to it.

Chapter 10: Mixing 16 and 32 Bit Code

This chapter tries to cover some of the issues, largely related to unusual forms of addressing and jump instructions, encountered when writing operating system code for protected-mode initialisation routines, which require code that operates mixed segment sizes, such as code in a 16-bit segment trying to modify data in a 32-bit one, or jumps between different-size segments.

10.1 Mixed-Size Jumps

The most common form of mixed-size instruction is the one used when writing a 32-bit OS having done your setup in 16-bit mode, such as loading the kernel, you then have to do this by switching into protected mode and jumping to the 32-bit kernel start address. In fully 32-bit OS, this ends to be the *only* mixed-size instruction you need, since everything before it can be done in pure 16-bit code and everything after it can be pure 32-bit.

This jump must specify a 32-bit address, since the target segment is 32-bit one. However, it must be assembled in a 16-bit segment, so just coding, for example,

```
jmp      0x1234:0x56789ABC      ; wrong!
```

will not work, since the offset part of the address will be truncated to 0x9ABC and the jump will be an ordinary 16-bit far one.

The `inuk` kernel setup code gets around this inability by using the `qword` prefix to generate the required instruction by coding manually using instructions. NASM is a better than that, but actually generating the right instruction itself. Here's how to do it right:

```
jmp      dword 0x1234:0x56789ABC      ; right
```

The `WORD` prefix, strictly speaking, it should come *after* the colons, since it is declaring the *offset* field to be a doubleword, but NASM will accept either form, since both are unambiguous. For ease of the offset part to be treated as far, it has the assumption that you are deliberately writing a jump from a 16-bit segment to a 32-bit one.

You can do the reverse operation, jumping from a 32-bit segment to a 16-bit one, by means of the `WORD` prefix:

```
jmp      word 0x8765:0x4321      ; 32 to 16 bit
```

If the `WORD` prefix is specified in 16-bit mode, the `WORD` prefix in 32-bit mode they will be ignored, since each is explicitly forcing NASM into a mode it was in anyway.

10.2 Addressing Between Different-Size Segments

If your OS is mixed 16 and 32-bit, or if you are writing a DOS extender, you are likely to have to deal with some 16-bit segments and some 32-bit ones. At some point, you will probably end up writing code in a 16-bit segment which has to access data in a 32-bit segment, or vice versa.

If the data you are trying to access in a 32-bit segment lies within the first 64K of the segment, you may be able to get away with using ordinary 16-bit addressing operation for the purpose, but sooner or later, you will want to do 32-bit addressing from 16-bit mode.

The easiest way to do this is to make sure you use a register for the address, since any effective address containing a 32-bit register is forced to be a 32-bit address. So you can do

```
mov      eax, offset_into_32_bit_segment_specified_by_fs
mov      dword [fs:eax], 0x11223344
```

This is fine, but it might seem a little wasteful since you already know the precise offset you are aiming at. The x86 architecture does allow 32-bit effective addresses to specify nothing but a 4-byte offset, so why shouldn't NASM be able to generate the best instruction for the purpose?

In section 10.1, you need only prefix the address with the `DWORD` keyword, and it will be forced to be a 32-bit address:

```
mov     dword [fs:dword my_offset], 0x11223344
```

Also in section 10.1, NASM is not fussy about whether the `DWORD` prefix comes before or after the segment override, so arguably a nicer-looking way to code the above instruction is

```
mov     dword [dword fs:my_offset], 0x11223344
```

Don't confuse the `DWORD` prefix *outside* the square brackets, which controls the size of the data stored at the address, with the one *inside* the square brackets which controls the length of the address itself. The two can quite easily be different:

```
mov     word [dword 0x12345678], 0x9ABC
```

This moves 16 bits of data to an address specified by a 32-bit offset.

You can also specify `WORD`, `DWORD` prefixes along with the `FAR` prefix to indirect far jumps or calls. For example:

```
call     dword far [fs:word 0x4321]
```

This instruction contains an address specified by a 16-bit offset, it loads a 32-bit value from that (16-bit segment and 32-bit offset), and calls that address.

10.3 Other Mixed-Size Instructions

The other way you might want to access data might be using the string instructions (`LODSx`, `STOSx` and `SCASx`). These instructions, since they take a parameter, might seem to have no easy way to make them perform 32-bit addressing when assembled in a 16-bit segment.

This is the purpose of NASM's `a16`, `a32` and `a64` prefixes. If you are coding `LODSB` in a 16-bit segment but it is supposed to be accessing a 32-bit segment, you should load the desired address into `ESI` and then code

```
a32     lodsb
```

The prefix forces the addressing size to 32 bits, meaning that `LODSB` loads from `[DS:ESI]` instead of `[DS:SI]`. To access a string in a 16-bit segment when coding in a 32-bit one, the corresponding `a16` prefix can be used.

The `a16`, `a32` and `a64` prefixes can be applied to any instruction in NASM's instruction table, but most of them generate all these useful forms without them. The prefixes are necessary only for instructions with implicit addressing: `CMPSx`, `SCASx`, `LODSx`, `STOSx`, `MOVSx`, `INSx`, `OUTSx` and `XLATB`. Also, the various push and pop instructions (`PUSHA` and `POPF` as well as the more usual `PUSH` and `POP`) can accept `a16`, `a32` or `a64` prefixes to force a particular one of `SP`, `ESP` or `RSP` to be used as a stack pointer, in case the stack segment in use is a different size from the code segment.

`PUSH` and `POP`, when applied to segment registers, also have the slightly odd behaviour that they push and pop 4 bytes at a time, of which the top two are ignored and the bottom two give the value of the segment register being manipulated. To force the 16-bit behaviour of segment-register push and pop instructions, you can use the operand-size prefix `o16`:

```
o16 push    ss
o16 push    ds
```


This code saves a doubleword of stack space by fitting two segment registers into the space which would normally be consumed by pushing one.

(You can also use the 32-bit prefix to force 32-bit behaviour when in 16-bit mode, but this seems less useful.)

Chapter 11: Writing 64-bit Code (Unix, Win64)

This chapter attempts to cover some of the common issues involved when writing 64-bit code to run under Win64 or Unix. It covers how to write assembly code to interface with 64-bit routines, and how to write position-independent code for shared libraries.

All 64-bit code uses a flat memory model, since segmentation is not available in 64-bit mode. The one exception is the FS and GS registers, which still add their bases.

Position independence in 64-bit mode is significantly simpler, since the processor supports RIP-relative addressing directly; see the `RIP` keyword in section 8.3. On most 64-bit platforms, it is probably desirable to make that the default, using the directive `DEFAULT REL` (section 5.1).

64-bit programming is relatively similar to 32-bit programming, but of course pointers are 64 bits long; additionally, existing platforms pass arguments in registers rather than on the stack. Furthermore, 64-bit platforms use SSE2 by default for floating-point. Please see the ABI documentation for your platform.

64-bit platforms differ in the size of the C/C++ fundamental data types, not just from 32-bit platforms but from each other. If a specific size data type is desired, it is probably best to use the types defined in the standard C header `<inttypes.h>`.

All known 64-bit platforms except some embedded platforms require that the stack is 16-byte aligned at the entry of a function. In order to enforce that, the stack pointer (RSP) needs to be aligned on an odd multiple of 8 bytes before the `CALL` instruction.

In 64-bit mode, the default instruction size is still 32 bits. When loading a value into a 32-bit register (but not an 8- or 16-bit register), the upper 32 bits of the corresponding 64-bit register are zeroed.

11.1 Register Names in 64-bit Mode

NASM uses the following names for general-purpose registers in 64-bit mode, for 8-, 16-, 32- and 64-bit references, respectively:

```
AL/AH, CL/CH, DL/DH, BL/BH, SPL, BPL, SIL, DIL, R8B-R15B
AX, CX, DX, BX, SP, BP, SI, DI, R8W-R15W
EAX, ECX, EDX, EBX, ESP, EBP, ESI, EDI, R8D-R15D
RAX, RCX, RDX, RBX, RSP, RBP, RSI, RDI, R8-R15
```

This is consistent with the AMD documentation and most other assemblers. The Intel documentation, however, uses the names `R8L-R15H` for 8-bit references to the higher registers. It is possible to use those names by defining them as macros; similarly, if one wants to use numeric names for the lower registers, define them as macros. The standard macro package `altreg` (section 5.1) can be used for this purpose.

11.2 immediates and Displacements in 64-bit Mode

In 64-bit mode, immediates and displacements are generally only 32 bits wide. NASM will therefore truncate most displacements and immediates to 32 bits.

The only instruction which takes a full 64-bit immediate is:

```
MOV reg64, imm64
```

NASM will produce this instruction whenever the programmer uses `MOV` with an immediate into a 64-bit register. If this is not desirable, simply specify the equivalent 32-bit register which will be automatically zero-extended by the processor, or specify the immediate as `DWORD:`

```

mov rax,foo                ; 64-bit immediate
mov rax,qword foo          ; (identical)
mov eax,foo                ; 32-bit immediate, zero-extended
mov rax,dword foo          ; 32-bit immediate, sign-extended

```

The length of these instructions are 10, 5 and 7 bytes, respectively.

If optimization is enabled and NASM determines at assembly time that a shorter instruction will suffice, the shorter instruction will be emitted unless of course `STRICTWORD` or `STRICTWORD` is specified (see section 3.7):

```

mov rax,1                  ; Assembles as "mov eax,1" (5 bytes)
mov rax,strict qword 1     ; Full 10-byte instruction
mov rax,strict dword 1     ; 7-byte instruction
mov rax,symbol             ; 10 bytes, not known at assembly time
lea rax,[rel symbol]       ; 7 bytes, usually preferred by the ABI

```

Note that `lea rax,[rel symbol]` is position-independent, whereas `mov rax,symbol` is not. Most ABIs prefer never require position-independent code in 64-bit mode. However, the `MOV` instruction is able to reference a symbol anywhere in the 64-bit address space, whereas `LEA` is only able to access a symbol within within 2 GB of the instruction itself (see below.)

The only instructions which take a full 64-bit displacement for loading or storing using `MOV`, `RAX`, `EAX` or `RAX` (but not other registers) is an absolute 64-bit address. Since this is relatively rarely used instruction (64-bit mode generally uses relative addressing), the programmer has to explicitly declare the displacement size as `ABS QWORD`:

```

default abs

mov eax,[foo]              ; 32-bit absolute disp, sign-extended
mov eax,[a32 foo]          ; 32-bit absolute disp, zero-extended
mov eax,[qword foo]        ; 64-bit absolute disp

default rel

mov eax,[foo]              ; 32-bit relative disp
mov eax,[a32 foo]          ; d:o, address truncated to 32 bits(!)
mov eax,[qword foo]        ; error
mov eax,[abs qword foo]    ; 64-bit absolute disp

```

A sign-extended absolute displacement can access from -2 GB to 2 GB, a zero-extended absolute displacement can access from 0 to 4 GB.

11.3 Interfacing to 64-bit C Programs (Unix)

On Unix, the 64-bit ABI as well as the x32 ABI (32-bit ABI with the CPU in 64-bit mode) is defined by the documents at:

<http://www.nasm.us/abi/unix64>

Although written for AT&T-syntax assembly, the concepts apply equally well for NASM-style assembly. What follows is a simplified summary.

The first six integer arguments (from the left) are passed in `RDI`, `RSI`, `RDY`, `RCX`, `R8`, and `R9`, in that order. Additional integer arguments are passed on the stack. These registers plus `RAX`, `R10`, and `R11` are destroyed by function calls, and thus are available for use by the function with

Integer return values are passed in `RAX` and `RDY`, in that order.

~~Floating-point is done using SSE registers, except for long double, which is 80 bits (TWORD) on most platforms (Android is an exception; there long double is 64 bits and treated the same as double.)~~
Floating-point arguments are passed in XMM0 to XMM7; return is XMM0 and XMM1. long double are passed on the stack, and returned in ST0 and ST1.

All SSE and x87 registers are destroyed by function calls.

On 64-bit Unix, long is 64 bits.

Integer and SSE register arguments are counted separately, so for the case of

```
void foo(long a, double b, int c)
```

a is passed in RDI, b in XMM0, and c in ESI.

11.4 Interfacing to 64-bit C Programs (Win64)

The Win64 ABI is described by the document at:

<http://www.nasm.us/abi/win64>

What follows is a simplified summary.

~~The first four integer arguments are passed in RCX, RDX, R8, and R9, in that order. Additional integer arguments are passed on the stack. These registers plus RAX, R10, and R11 are destroyed by function calls, and thus are available for use by the function without saving.~~

Integer return values are passed in RAX only.

~~Floating-point is done using SSE registers, except for long double.~~
Floating-point arguments are passed in XMM0 to XMM3; return is XMM0 only.

On Win64, long is 32 bits; long long or _int64 is 64 bits.

Integer and SSE register arguments are counted together, so for the case of

```
void foo(long long a, double b, int c)
```

a is passed in RCX, b in XMM1, and c in R8D.

Chapter 12: Troubleshooting

This chapter describes some of the common problems that users have been known to encounter with NASM, and answers them. If you think you have found a bug in NASM, please see section 2.1.23.

12.1 Common Problems

12.1.1 NASM Generates Inefficient Code

We sometimes get 'bug' reports about NASM generating inefficient, or even 'wrong', code on instructions such as `ADESP, 8`. This is a deliberate design feature, connected to predictability of output. NASM, on seeing `ADESP, 8`, will generate the form of the instruction which leaves room for a 32-bit offset. You need to code `ADDESP, BYTE 8` if you want the space-efficient form of the instruction. This isn't 'bug' it's an error if you prefer to have NASM produce the more efficient code automatically enable optimization with the `-O` option (see section 2.1.23).

12.1.2 My Jumps are Out of Range

Similarly people complain that when they issue conditional jumps which are `SHORT` by default that try to jump too far, NASM reports 'short jump out of range' instead of making the jump.

This again is partly a predictability issue but in fact has more practical reasons as well. NASM also means to be told what type of processor the code it is generating will be run on, so it cannot decide for itself that it should generate `JNEAR` instructions because it doesn't know what it's working for. On 386 and above alternatively, it could replace out-of-range short `JNE` instructions with very short `JNE` instructions that jump over a `JNEAR`; this is a sensible solution for processors below 386, but hardly efficient on processors which have good branch prediction and could have used `JNEAR` instead. So once again, it's up to the user, not the assembler, to decide what instructions should be generated. See section 2.1.23.

12.1.3 ORG Doesn't Work

People writing boot sector programs in the `bin` format often complain that `ORG` doesn't work the way they'd like in order to place the `0xAA55` signature word at the end of the 12-byte boot sector, people who are used to MASM tend to code

```
ORG 0

; some boot sector code

ORG 510
DW 0xAA55
```

This is not the intended use of the `ORG` directive in NASM, and will not work. The correct way to solve this problem in NASM is to use the `TIMES` directive, like this:

```
ORG 0

; some boot sector code

TIMES 510-($-$$) DB 0
DW 0xAA55
```

The `TIMES` directive will insert exactly enough zero bytes into the output to move the assembly point up to 510. This method also has the advantage that if you accidentally fill your boot sector to full, NASM will catch the problem at assembly time and report it, so you won't end up with a boot sector that you have to disassemble to find out what's wrong with it.

12.1.4 TIMES Doesn't Work

The other common problem with the above code is people who write the TIMES line as

```
TIMES 510-$ DB 0
```

by reasoning that \$ should be a pure number, just like 510, so the difference between them is also a pure number and can happily be fed to TIMES.

NASM's modular assembler: the various component parts are designed to be easily separable for re-use, so they don't exchange information unnecessarily. In consequence, the bin output format, even though it has been told by the ORG directive that the text sections should start at 0, does not pass that information back to the expression evaluator. So from the evaluator's point of view, \$ isn't a pure number; it's an offset from section base. Therefore the difference between \$ and 510 is also not a pure number, but involves section base. Values involving section bases cannot be passed as arguments to TIMES.

The solution, as in the previous section, is to code the TIMES line in the form

```
TIMES 510-($-$$) DB 0
```

in which \$ and \$\$ are offsets from the same section base, and so their difference is a pure number. This will solve the problem and generate sensible code.

Appendix A: Ndisasm

The Netwide Disassembler, NDISASM

A.1 Introduction

The Netwide Disassembler is a small companion program to the Netwide Assembler, NASM. It seemed a shame to have an x86 assembler, complete with full instruction table, and not make as much use of it as possible, so here's a disassembler which shares the instruction table (and some of the bits of code) with NASM.

The Netwide Disassembler does nothing except to produce disassemblies of *binary* source files. NDISASM does not have any understanding of object file formats, like objdump, and it will not understand DOS .EXE files like debug will. It just disassembles.

A.2 Running NDISASM

To disassemble a file, you will typically use a command of the form

```
ndisasm -b {16|32|64} filename
```

NDISASM can disassemble 16-, 32- or 64-bit code equally easily, provided of course that you remember to specify which it is to work with. If no switch is present, NDISASM works in 16-bit mode by default. The -u switch (for USE32) also invokes 32-bit mode.

Two more command line options are -r which reports the version number of NDISASM you are running, and -h which gives a short summary of command line options.

A.2.1 COM Files: Specifying an Origin

To disassemble a DOS COM file correctly, a disassembler must assume that the first instruction in the file is loaded at address 0x100, rather than at zero. NDISASM, which assumes by default that any file you give it is loaded at zero, will therefore need to be informed of this.

The option allows you to declare a different origin for the file you are disassembling. Its argument may be expressed in any of the NASM numeric formats: decimal by default, if it begins with '\$' or '0x' or ends in 'H' it's hex, if it ends in 'Q' it's octal, and if it ends in 'B' it's binary.

Hence, to disassemble a .COM file:

```
ndisasm -o100h filename.com
```

will do the trick.

A.2.2 Code Following Data: Synchronisation

Suppose you are disassembling a file which contains some data which isn't machine code, and then contains some machine code. NDISASM will faithfully plough through the data section producing machine instructions wherever it can (although most of them will look bizarre, and some may have unusual prefixes, e.g. 'FSAX, 0x240A') and generating DB instructions everywhere it's totally stumped. Then it will reach the code section.

Supposing NDISASM has just finished generating a strange machine instruction from part of the data section, and its file position is now one byte *before* the beginning of the code section. It's entirely possible that another spurious instruction will be generated, starting with the final byte of the data section, and then the correct first instruction in the code section will be missed because the starting point skipped over it. This isn't really ideal.

To avoid this you can specify a synchronisation point, indeed many synchronisation points as you like (although NDISASM only handles 2147483647 sync points internally). The definition of sync point is this: NDISASM guarantees this sync point exactly during disassembly. If it is thinking about generating an instruction which would cause it to jump over a sync point, it will discard that instruction and output a db instead. So *it will* start disassembly exactly from the sync point and so you *will* see all the instructions in your code section.

Sync points are specified using the option they are measured in terms of the program origin, not the file position. So if you want to synchronize after 32 bytes of a .COM file, you want

```
ndisasm -o100h -s120h file.com
```

rather than

```
ndisasm -o100h -s20h file.com
```

As stated above, you can specify multiple sync markers if you need to, just by repeating the option.

A.2.3 Mixed Code and Data: Automatic (Intelligent) Synchronisation

Suppose you are disassembling the boot sector of a DOS floppy (maybe it has a virus, and you need to understand the virus so that you know what kinds of damage it might have done to you). Typically, this will contain a JMP instruction, then some data, then the rest of the code. So there's a very good chance of NDISASM being *misaligned* when the data ends and the code begins. Hence a sync point is needed.

On the other hand, why should you have to specify the sync point manually? What you'd do in order to find where the sync point would be, surely, would be to read the JMP instruction, and then use its target address as a sync point. So can NDISASM do that for you?

The answer, of course, is yes using either of the synonymous switches -a (for automatic sync) or -i (for intelligent sync). Will enable auto-syn mode. Auto-syn mode automatically generates sync points for forward-referring PC-relative jumps and all instructions that NDISASM encounters. (Since NDISASM is one-pass, if it encounters a PC-relative jump whose target has already been processed, there isn't much it can do about it...)

Only PC-relative jumps are processed, since an absolute jump is either through a register (in which case NDISASM doesn't know what the register contains) or involves segment address (in which case the target code isn't in the same segment that NDISASM is working in, and the sync point can't be placed anywhere useful).

For some kinds of file, this mechanism will automatically put sync points in all the right places and save you from having to place any sync points manually. However, it should be stressed that auto-sync mode is *not* guaranteed to catch all the sync points, and you may still have to place some manually.

Auto-syn mode doesn't prevent you from declaring manual sync points; it just adds automatically generated ones to the ones you provide. It's perfectly feasible to specify -i *and* some manual sync points.

Another caveat with auto-syn mode is that if, by some unpleasant fluke, something in your data section should disassemble to a PC-relative absolute jump instruction, NDISASM may be tempted to place a sync point in a totally random place, for example in the middle of one of the instructions in your code section. So you may end up with a wrong disassembly even if you use auto-sync. Again, there isn't much I can do about this. If you have problems, you'll have to use manual sync points, or use the -k option (documented below) to suppress disassembly of the data area.

A.2.4 Other Options

The option -s skips the header of the file by ignoring the first n bytes. This means that the header is *not* counted towards the disassembly offset. If you give -e10 -o10, disassembly will start at byte 10 in the file, and this will be given offset 10, not 20.

The `k` option is provided with two comma-separated numeric arguments, the first of which is an assembly offset and the second a number of bytes to skip. This *will* count the skipped bytes towards the assembly offset; it is used to suppress disassembly of a data section which wouldn't contain anything you wanted to see anyway.

Appendix B: Instruction List

B.1 Introduction

The following sections show the instructions which NASM currently supports. For each instruction, there is a separate entry for each supported addressing mode. The third column shows the processor type in which the instruction was introduced and, when appropriate, one or more usage

B.1.1 Special instructions...

DB		
DW		
DD		
DQ		
DT		
DO		
DY		
DZ		
RESB	imm	8086
RESW		
RESD		
RESQ		
REST		
RESO		
RESY		
RESZ		

B.1.2 Conventional instructions

AAA		8086, NO LONG
AAD		8086, NO LONG
AAD	imm	8086, NO LONG
AAM		8086, NO LONG
AAM	imm	8086, NO LONG
AAS		8086, NO LONG
ADC	mem, reg8	8086, LOCK
ADC	reg8, reg8	8086
ADC	mem, reg16	8086, LOCK
ADC	reg16, reg16	8086
ADC	mem, reg32	386, LOCK
ADC	reg32, reg32	386
ADC	mem, reg64	X64, LOCK
ADC	reg64, reg64	X64
ADC	reg8, mem	8086
ADC	reg8, reg8	8086
ADC	reg16, mem	8086
ADC	reg16, reg16	8086
ADC	reg32, mem	386
ADC	reg32, reg32	386
ADC	reg64, mem	X64
ADC	reg64, reg64	X64
ADC	rm16, imm8	8086, LOCK
ADC	rm32, imm8	386, LOCK

ADC	rm64,imm8	X64,LOCK
ADC	reg_al,imm	8086
ADC	reg_ax,sbytedword	8086,ND
ADC	reg_ax,imm	8086
ADC	reg_eax,sbytedword	386,ND
ADC	reg_eax,imm	386
ADC	reg_rax,sbytedword	X64,ND
ADC	reg_rax,imm	X64
ADC	rm8,imm	8086,LOCK
ADC	rm16,sbytedword	8086,LOCK,ND
ADC	rm16,imm	8086,LOCK
ADC	rm32,sbytedword	386,LOCK,ND
ADC	rm32,imm	386,LOCK
ADC	rm64,sbytedword	X64,LOCK,ND
ADC	rm64,imm	X64,LOCK
ADC	mem,imm8	8086,LOCK,ND
ADC	mem,sbytedword16	8086,LOCK,ND
ADC	mem,imm16	8086,LOCK
ADC	mem,sbytedword32	386,LOCK,ND
ADC	mem,imm32	386,LOCK
ADC	rm8,imm	8086,LOCK,ND,NOLONG
ADD	mem,reg8	8086,LOCK
ADD	reg8,reg8	8086
ADD	mem,reg16	8086,LOCK
ADD	reg16,reg16	8086
ADD	mem,reg32	386,LOCK
ADD	reg32,reg32	386
ADD	mem,reg64	X64,LOCK
ADD	reg64,reg64	X64
ADD	reg8,mem	8086
ADD	reg8,reg8	8086
ADD	reg16,mem	8086
ADD	reg16,reg16	8086
ADD	reg32,mem	386
ADD	reg32,reg32	386
ADD	reg64,mem	X64
ADD	reg64,reg64	X64
ADD	rm16,imm8	8086,LOCK
ADD	rm32,imm8	386,LOCK
ADD	rm64,imm8	X64,LOCK
ADD	reg_al,imm	8086
ADD	reg_ax,sbytedword	8086,ND
ADD	reg_ax,imm	8086
ADD	reg_eax,sbytedword	386,ND
ADD	reg_eax,imm	386
ADD	reg_rax,sbytedword	X64,ND
ADD	reg_rax,imm	X64
ADD	rm8,imm	8086,LOCK
ADD	rm16,sbytedword	8086,LOCK,ND
ADD	rm16,imm	8086,LOCK
ADD	rm32,sbytedword	386,LOCK,ND
ADD	rm32,imm	386,LOCK
ADD	rm64,sbytedword	X64,LOCK,ND
ADD	rm64,imm	X64,LOCK

ADD	mem,imm8	8086, LOCK
ADD	mem,sbytedword16	8086, LOCK, ND
ADD	mem,imm16	8086, LOCK
ADD	mem,sbytedword32	386, LOCK, ND
ADD	mem,imm32	386, LOCK
ADD	rm8,imm	8086, LOCK, ND, NOLONG
AND	mem,reg8	8086, LOCK
AND	reg8,reg8	8086
AND	mem,reg16	8086, LOCK
AND	reg16,reg16	8086
AND	mem,reg32	386, LOCK
AND	reg32,reg32	386
AND	mem,reg64	X64, LOCK
AND	reg64,reg64	X64
AND	reg8,mem	8086
AND	reg8,reg8	8086
AND	reg16,mem	8086
AND	reg16,reg16	8086
AND	reg32,mem	386
AND	reg32,reg32	386
AND	reg64,mem	X64
AND	reg64,reg64	X64
AND	rm16,imm8	8086, LOCK
AND	rm32,imm8	386, LOCK
AND	rm64,imm8	X64, LOCK
AND	reg_al,imm	8086
AND	reg_ax,sbytedword	8086, ND
AND	reg_ax,imm	8086
AND	reg_eax,sbytedword	386, ND
AND	reg_eax,imm	386
AND	reg_rax,sbytedword	X64, ND
AND	reg_rax,imm	X64
AND	rm8,imm	8086, LOCK
AND	rm16,sbytedword	8086, LOCK, ND
AND	rm16,imm	8086, LOCK
AND	rm32,sbytedword	386, LOCK, ND
AND	rm32,imm	386, LOCK
AND	rm64,sbytedword	X64, LOCK, ND
AND	rm64,imm	X64, LOCK
AND	mem,imm8	8086, LOCK
AND	mem,sbytedword16	8086, LOCK, ND
AND	mem,imm16	8086, LOCK
AND	mem,sbytedword32	386, LOCK, ND
AND	mem,imm32	386, LOCK
AND	rm8,imm	8086, LOCK, ND, NOLONG
ARPL	mem,reg16	286, PROT, NOLONG
ARPL	reg16,reg16	286, PROT, NOLONG
BB0_RESET		PENT, CYRIX, ND, OBSOLETE
BB1_RESET		PENT, CYRIX, ND, OBSOLETE
BOUND	reg16,mem	186, NOLONG
BOUND	reg32,mem	386, NOLONG
BSF	reg16,mem	386
BSF	reg16,reg16	386
BSF	reg32,mem	386

BSF	reg32, reg32	386
BSF	reg64, mem	X64
BSF	reg64, reg64	X64
BSR	reg16, mem	386
BSR	reg16, reg16	386
BSR	reg32, mem	386
BSR	reg32, reg32	386
BSR	reg64, mem	X64
BSR	reg64, reg64	X64
BSWAP	reg32	486
BSWAP	reg64	X64
BT	mem, reg16	386
BT	reg16, reg16	386
BT	mem, reg32	386
BT	reg32, reg32	386
BT	mem, reg64	X64
BT	reg64, reg64	X64
BT	rm16, imm	386
BT	rm32, imm	386
BT	rm64, imm	X64
BTC	mem, reg16	386, LOCK
BTC	reg16, reg16	386
BTC	mem, reg32	386, LOCK
BTC	reg32, reg32	386
BTC	mem, reg64	X64, LOCK
BTC	reg64, reg64	X64
BTC	rm16, imm	386, LOCK
BTC	rm32, imm	386, LOCK
BTC	rm64, imm	X64, LOCK
BTR	mem, reg16	386, LOCK
BTR	reg16, reg16	386
BTR	mem, reg32	386, LOCK
BTR	reg32, reg32	386
BTR	mem, reg64	X64, LOCK
BTR	reg64, reg64	X64
BTR	rm16, imm	386, LOCK
BTR	rm32, imm	386, LOCK
BTR	rm64, imm	X64, LOCK
BTS	mem, reg16	386, LOCK
BTS	reg16, reg16	386
BTS	mem, reg32	386, LOCK
BTS	reg32, reg32	386
BTS	mem, reg64	X64, LOCK
BTS	reg64, reg64	X64
BTS	rm16, imm	386, LOCK
BTS	rm32, imm	386, LOCK
BTS	rm64, imm	X64, LOCK
CALL	imm	8086, BND
CALL	imm near	8086, ND, BND
CALL	imm far	8086, ND, NOLONG
CALL	imm16	8086, NOLONG, BND
CALL	imm16 near	8086, ND, NOLONG, BND
CALL	imm16 far	8086, ND, NOLONG
CALL	imm32	386, NOLONG, BND

CALL	imm32 near	386,ND,NOLONG,BND
CALL	imm32 far	386,ND,NOLONG
CALL	imm64	X64,BND
CALL	imm64 near	X64,ND,BND
CALL	imm:imm	8086,NOLONG
CALL	imm16:imm	8086,NOLONG
CALL	imm:imm16	8086,NOLONG
CALL	imm32:imm	386,NOLONG
CALL	imm:imm32	386,NOLONG
CALL	mem far	8086,NOLONG
CALL	mem far	X64
CALL	mem16 far	8086
CALL	mem32 far	386
CALL	mem64 far	X64
CALL	mem near	8086,ND,BND
CALL	rm16 near	8086,NOLONG,ND,BND
CALL	rm32 near	386,NOLONG,ND,BND
CALL	rm64 near	X64,ND,BND
CALL	mem	8086,BND
CALL	rm16	8086,NOLONG,BND
CALL	rm32	386,NOLONG,BND
CALL	rm64	X64,BND
CBW		8086
CDQ		386
CDQE		X64
CLC		8086
CLD		8086
CLI		8086
CLTS		286,PRIV
CMC		8086
CMP	mem,reg8	8086
CMP	reg8,reg8	8086
CMP	mem,reg16	8086
CMP	reg16,reg16	8086
CMP	mem,reg32	386
CMP	reg32,reg32	386
CMP	mem,reg64	X64
CMP	reg64,reg64	X64
CMP	reg8,mem	8086
CMP	reg8,reg8	8086
CMP	reg16,mem	8086
CMP	reg16,reg16	8086
CMP	reg32,mem	386
CMP	reg32,reg32	386
CMP	reg64,mem	X64
CMP	reg64,reg64	X64
CMP	rm16,imm8	8086
CMP	rm32,imm8	386
CMP	rm64,imm8	X64
CMP	reg_al,imm	8086
CMP	reg_ax,sbytedword	8086,ND
CMP	reg_ax,imm	8086
CMP	reg_eax,sbytedword	386,ND
CMP	reg_eax,imm	386

CMP	reg_rax, sbytedword	X64, ND
CMP	reg_rax, imm	X64
CMP	rm8, imm	8086
CMP	rm16, sbytedword	8086, ND
CMP	rm16, imm	8086
CMP	rm32, sbytedword	386, ND
CMP	rm32, imm	386
CMP	rm64, sbytedword	X64, ND
CMP	rm64, imm	X64
CMP	mem, imm8	8086
CMP	mem, sbytedword16	8086, ND
CMP	mem, imm16	8086
CMP	mem, sbytedword32	386, ND
CMP	mem, imm32	386
CMP	rm8, imm	8086, ND, NOLONG
CMPSB		8086
CMPSD		386
CMPSQ		X64
CMPSW		8086
CMPXCHG	mem, reg8	PENT, LOCK
CMPXCHG	reg8, reg8	PENT
CMPXCHG	mem, reg16	PENT, LOCK
CMPXCHG	reg16, reg16	PENT
CMPXCHG	mem, reg32	PENT, LOCK
CMPXCHG	reg32, reg32	PENT
CMPXCHG	mem, reg64	X64, LOCK
CMPXCHG	reg64, reg64	X64
CMPXCHG486	mem, reg8	486, UNDOC, ND, LOCK, OBSOLETE
CMPXCHG486	reg8, reg8	486, UNDOC, ND, OBSOLETE
CMPXCHG486	mem, reg16	486, UNDOC, ND, LOCK, OBSOLETE
CMPXCHG486	reg16, reg16	486, UNDOC, ND, OBSOLETE
CMPXCHG486	mem, reg32	486, UNDOC, ND, LOCK, OBSOLETE
CMPXCHG486	reg32, reg32	486, UNDOC, ND, OBSOLETE
CMPXCHG8B	mem	PENT, LOCK
CMPXCHG16B	mem	X64, LOCK
CPUID		PENT
CPU_READ		PENT, CYRIX
CPU_WRITE		PENT, CYRIX
CQO		X64
CWD		8086
CWDE		386
DAA		8086, NOLONG
DAS		8086, NOLONG
DEC	reg16	8086, NOLONG
DEC	reg32	386, NOLONG
DEC	rm8	8086, LOCK
DEC	rm16	8086, LOCK
DEC	rm32	386, LOCK
DEC	rm64	X64, LOCK
DIV	rm8	8086
DIV	rm16	8086
DIV	rm32	386
DIV	rm64	X64
DMINT		P6, CYRIX

EMMS		PENT,MMX
ENTER	imm,imm	186
EQU	imm	8086
EQU	imm:imm	8086
F2XM1		8086,FPU
FABS		8086,FPU
FADD	mem32	8086,FPU
FADD	mem64	8086,FPU
FADD	fpureg to	8086,FPU
FADD	fpureg	8086,FPU
FADD	fpureg, fpu0	8086,FPU
FADD	fpu0, fpureg	8086,FPU
FADD		8086,FPU,ND
FADDP	fpureg	8086,FPU
FADDP	fpureg, fpu0	8086,FPU
FADDP		8086,FPU,ND
FBLD	mem80	8086,FPU
FBLD	mem	8086,FPU
FBSTP	mem80	8086,FPU
FBSTP	mem	8086,FPU
FCHS		8086,FPU
FCLEX		8086,FPU
FCMOVB	fpureg	P6,FPU
FCMOVB	fpu0, fpureg	P6,FPU
FCMOVB		P6,FPU,ND
FCMOVBE	fpureg	P6,FPU
FCMOVBE	fpu0, fpureg	P6,FPU
FCMOVBE		P6,FPU,ND
FCMOVE	fpureg	P6,FPU
FCMOVE	fpu0, fpureg	P6,FPU
FCMOVE		P6,FPU,ND
FCMOVNB	fpureg	P6,FPU
FCMOVNB	fpu0, fpureg	P6,FPU
FCMOVNB		P6,FPU,ND
FCMOVNBE	fpureg	P6,FPU
FCMOVNBE	fpu0, fpureg	P6,FPU
FCMOVNBE		P6,FPU,ND
FCMOVNE	fpureg	P6,FPU
FCMOVNE	fpu0, fpureg	P6,FPU
FCMOVNE		P6,FPU,ND
FCMOVNU	fpureg	P6,FPU
FCMOVNU	fpu0, fpureg	P6,FPU
FCMOVNU		P6,FPU,ND
FCMOVU	fpureg	P6,FPU
FCMOVU	fpu0, fpureg	P6,FPU
FCMOVU		P6,FPU,ND
FCOM	mem32	8086,FPU
FCOM	mem64	8086,FPU
FCOM	fpureg	8086,FPU
FCOM	fpu0, fpureg	8086,FPU
FCOM		8086,FPU,ND
FCOMI	fpureg	P6,FPU
FCOMI	fpu0, fpureg	P6,FPU
FCOMI		P6,FPU,ND

FCOMIP	fpureg	P6, FPU
FCOMIP	fpu0, fpureg	P6, FPU
FCOMIP		P6, FPU, ND
FCOMP	mem32	8086, FPU
FCOMP	mem64	8086, FPU
FCOMP	fpureg	8086, FPU
FCOMP	fpu0, fpureg	8086, FPU
FCOMP		8086, FPU, ND
FCOMPP		8086, FPU
FCOS		386, FPU
FDECSTP		8086, FPU
FDISI		8086, FPU
FDIV	mem32	8086, FPU
FDIV	mem64	8086, FPU
FDIV	fpureg to	8086, FPU
FDIV	fpureg	8086, FPU
FDIV	fpureg, fpu0	8086, FPU
FDIV	fpu0, fpureg	8086, FPU
FDIV		8086, FPU, ND
FDIVP	fpureg	8086, FPU
FDIVP	fpureg, fpu0	8086, FPU
FDIVP		8086, FPU, ND
FDIVR	mem32	8086, FPU
FDIVR	mem64	8086, FPU
FDIVR	fpureg to	8086, FPU
FDIVR	fpureg, fpu0	8086, FPU
FDIVR	fpureg	8086, FPU
FDIVR	fpu0, fpureg	8086, FPU
FDIVR		8086, FPU, ND
FDIVRP	fpureg	8086, FPU
FDIVRP	fpureg, fpu0	8086, FPU
FDIVRP		8086, FPU, ND
FEMMS		PENT, 3DNOW
FENI		8086, FPU
FFREE	fpureg	8086, FPU
FFREE		8086, FPU
FFREEP	fpureg	286, FPU, UNDOC
FFREEP		286, FPU, UNDOC
FIADD	mem32	8086, FPU
FIADD	mem16	8086, FPU
FICOM	mem32	8086, FPU
FICOM	mem16	8086, FPU
FICOMP	mem32	8086, FPU
FICOMP	mem16	8086, FPU
FIDIV	mem32	8086, FPU
FIDIV	mem16	8086, FPU
FIDIVR	mem32	8086, FPU
FIDIVR	mem16	8086, FPU
FILD	mem32	8086, FPU
FILD	mem16	8086, FPU
FILD	mem64	8086, FPU
FIMUL	mem32	8086, FPU
FIMUL	mem16	8086, FPU
FINCSTP		8086, FPU

FINIT		8086, FPU
FIST	mem32	8086, FPU
FIST	mem16	8086, FPU
FISTP	mem32	8086, FPU
FISTP	mem16	8086, FPU
FISTP	mem64	8086, FPU
FISTTP	mem16	PRESCOTT, FPU
FISTTP	mem32	PRESCOTT, FPU
FISTTP	mem64	PRESCOTT, FPU
FISUB	mem32	8086, FPU
FISUB	mem16	8086, FPU
FISUBR	mem32	8086, FPU
FISUBR	mem16	8086, FPU
FLD	mem32	8086, FPU
FLD	mem64	8086, FPU
FLD	mem80	8086, FPU
FLD	fpureg	8086, FPU
FLD		8086, FPU, ND
FLD1		8086, FPU
FLDCW	mem	8086, FPU, SW
FLDENV	mem	8086, FPU
FLDL2E		8086, FPU
FLDL2T		8086, FPU
FLDLG2		8086, FPU
FLDLN2		8086, FPU
FLDPI		8086, FPU
FLDZ		8086, FPU
FMUL	mem32	8086, FPU
FMUL	mem64	8086, FPU
FMUL	fpureg to	8086, FPU
FMUL	fpureg, fpu0	8086, FPU
FMUL	fpureg	8086, FPU
FMUL	fpu0, fpureg	8086, FPU
FMUL		8086, FPU, ND
FMULP	fpureg	8086, FPU
FMULP	fpureg, fpu0	8086, FPU
FMULP		8086, FPU, ND
FNCLEX		8086, FPU
FNDISI		8086, FPU
FNENI		8086, FPU
FNINIT		8086, FPU
FNOP		8086, FPU
FNSAVE	mem	8086, FPU
FNSTCW	mem	8086, FPU, SW
FNSTENV	mem	8086, FPU
FNSTSW	mem	8086, FPU, SW
FNSTSW	reg_ax	286, FPU
FPATAN		8086, FPU
FPREM		8086, FPU
FPREM1		386, FPU
FPTAN		8086, FPU
FRNDINT		8086, FPU
FRSTOR	mem	8086, FPU
FSAVE	mem	8086, FPU

FSCALE		8086, FPU
FSETPM		286, FPU
FSIN		386, FPU
FSINCOS		386, FPU
FSQRT		8086, FPU
FST	mem32	8086, FPU
FST	mem64	8086, FPU
FST	fpureg	8086, FPU
FST		8086, FPU, ND
FSTCW	mem	8086, FPU, SW
FSTENV	mem	8086, FPU
FSTP	mem32	8086, FPU
FSTP	mem64	8086, FPU
FSTP	mem80	8086, FPU
FSTP	fpureg	8086, FPU
FSTP		8086, FPU, ND
FSTSW	mem	8086, FPU, SW
FSTSW	reg_ax	286, FPU
FSUB	mem32	8086, FPU
FSUB	mem64	8086, FPU
FSUB	fpureg to	8086, FPU
FSUB	fpureg, fpu0	8086, FPU
FSUB	fpureg	8086, FPU
FSUB	fpu0, fpureg	8086, FPU
FSUB		8086, FPU, ND
FSUBP	fpureg	8086, FPU
FSUBP	fpureg, fpu0	8086, FPU
FSUBP		8086, FPU, ND
FSUBR	mem32	8086, FPU
FSUBR	mem64	8086, FPU
FSUBR	fpureg to	8086, FPU
FSUBR	fpureg, fpu0	8086, FPU
FSUBR	fpureg	8086, FPU
FSUBR	fpu0, fpureg	8086, FPU
FSUBR		8086, FPU, ND
FSUBRP	fpureg	8086, FPU
FSUBRP	fpureg, fpu0	8086, FPU
FSUBRP		8086, FPU, ND
FTST		8086, FPU
FUCOM	fpureg	386, FPU
FUCOM	fpu0, fpureg	386, FPU
FUCOM		386, FPU, ND
FUCOMI	fpureg	P6, FPU
FUCOMI	fpu0, fpureg	P6, FPU
FUCOMI		P6, FPU, ND
FUCOMIP	fpureg	P6, FPU
FUCOMIP	fpu0, fpureg	P6, FPU
FUCOMIP		P6, FPU, ND
FUCOMP	fpureg	386, FPU
FUCOMP	fpu0, fpureg	386, FPU
FUCOMP		386, FPU, ND
FUCOMPP		386, FPU
FXAM		8086, FPU
FXCH	fpureg	8086, FPU

FXCH	fpureg, fpu0	8086, FPU
FXCH	fpu0, fpureg	8086, FPU
FXCH		8086, FPU, ND
FXTRACT		8086, FPU
FYL2X		8086, FPU
FYL2XP1		8086, FPU
HLT		8086, PRIV
IBTS	mem, reg16	386, SW, UNDOC, ND, OBSOLETE
IBTS	reg16, reg16	386, UNDOC, ND, OBSOLETE
IBTS	mem, reg32	386, SD, UNDOC, ND, OBSOLETE
IBTS	reg32, reg32	386, UNDOC, ND, OBSOLETE
ICEBP		386, ND
IDIV	rm8	8086
IDIV	rm16	8086
IDIV	rm32	386
IDIV	rm64	X64
IMUL	rm8	8086
IMUL	rm16	8086
IMUL	rm32	386
IMUL	rm64	X64
IMUL	reg16, mem	386
IMUL	reg16, reg16	386
IMUL	reg32, mem	386
IMUL	reg32, reg32	386
IMUL	reg64, mem	X64
IMUL	reg64, reg64	X64
IMUL	reg16, mem, imm8	186
IMUL	reg16, mem, sbytedword	186, ND
IMUL	reg16, mem, imm16	186
IMUL	reg16, mem, immn	186, ND
IMUL	reg16, reg16, imm8	186
IMUL	reg16, reg16, sbytedword	186, ND
IMUL	reg16, reg16, imm16	186
IMUL	reg16, reg16, immn	186, ND
IMUL	reg32, mem, imm8	386
IMUL	reg32, mem, sbytedword	386, ND
IMUL	reg32, mem, imm32	386
IMUL	reg32, mem, immn	386, ND
IMUL	reg32, reg32, imm8	386
IMUL	reg32, reg32, sbytedword	386, ND
IMUL	reg32, reg32, imm32	386
IMUL	reg32, reg32, immn	386, ND
IMUL	reg64, mem, imm8	X64
IMUL	reg64, mem, sbytedword	X64, ND
IMUL	reg64, mem, imm32	X64
IMUL	reg64, mem, immn	X64, ND
IMUL	reg64, reg64, imm8	X64
IMUL	reg64, reg64, sbytedword	X64, ND
IMUL	reg64, reg64, imm32	X64
IMUL	reg64, reg64, immn	X64, ND
IMUL	reg16, imm8	186
IMUL	reg16, sbytedword	186, ND
IMUL	reg16, imm16	186
IMUL	reg16, immn	186, ND

IMUL	reg32,imm8	386
IMUL	reg32,sbytedword	386,ND
IMUL	reg32,imm32	386
IMUL	reg32,imm	386,ND
IMUL	reg64,imm8	X64
IMUL	reg64,sbytedword	X64,ND
IMUL	reg64,imm32	X64
IMUL	reg64,imm	X64,ND
IN	reg_al,imm	8086
IN	reg_ax,imm	8086
IN	reg_eax,imm	386
IN	reg_al,reg_dx	8086
IN	reg_ax,reg_dx	8086
IN	reg_eax,reg_dx	386
INC	reg16	8086,NOLONG
INC	reg32	386,NOLONG
INC	rm8	8086,LOCK
INC	rm16	8086,LOCK
INC	rm32	386,LOCK
INC	rm64	X64,LOCK
INCBIN		
INSB		186
INSD		386
INSW		186
INT	imm	8086
INT01		386,ND
INT1		386
INT03		8086,ND
INT3		8086
INTO		8086,NOLONG
INVD		486,PRIV
INVPCID	reg32,mem128	INVPCID,PRIV,NOLONG
INVPCID	reg64,mem128	INVPCID,PRIV, LONG
INVLPG	mem	486,PRIV
INVLPGA	reg_ax,reg_ecx	X86_64,AMD,NOLONG
INVLPGA	reg_eax,reg_ecx	X86_64,AMD
INVLPGA	reg_rax,reg_ecx	X64,AMD
INVLPGA		X86_64,AMD
IRET		8086
IRETD		386
IRETQ		X64
IRETW		8086
JCXZ	imm	8086,NOLONG
JECXZ	imm	386
JRCXZ	imm	X64
JMP	imm short	8086
JMP	imm	8086,ND
JMP	imm	8086,BND
JMP	imm near	8086,ND,BND
JMP	imm far	8086,ND,NOLONG
JMP	imm16	8086,NOLONG,BND
JMP	imm16 near	8086,ND,NOLONG,BND
JMP	imm16 far	8086,ND,NOLONG
JMP	imm32	386,NOLONG,BND

JMP	imm32 near	386,ND,NOLONG,BND
JMP	imm32 far	386,ND,NOLONG
JMP	imm64	X64,BND
JMP	imm64 near	X64,ND,BND
JMP	imm:imm	8086,NOLONG
JMP	imm16:imm	8086,NOLONG
JMP	imm:imm16	8086,NOLONG
JMP	imm32:imm	386,NOLONG
JMP	imm:imm32	386,NOLONG
JMP	mem far	8086,NOLONG
JMP	mem far	X64
JMP	mem16 far	8086
JMP	mem32 far	386
JMP	mem64 far	X64
JMP	mem near	8086,ND,BND
JMP	rm16 near	8086,NOLONG,ND,BND
JMP	rm32 near	386,NOLONG,ND,BND
JMP	rm64 near	X64,ND,BND
JMP	mem	8086,BND
JMP	rm16	8086,NOLONG,BND
JMP	rm32	386,NOLONG,BND
JMP	rm64	X64,BND
JMPE	imm	IA64
JMPE	imm16	IA64
JMPE	imm32	IA64
JMPE	rm16	IA64
JMPE	rm32	IA64
LAHF		8086
LAR	reg16,mem	286,PROT,SW
LAR	reg16,reg16	286,PROT
LAR	reg16,reg32	386,PROT
LAR	reg16,reg64	X64,PROT,ND
LAR	reg32,mem	386,PROT,SW
LAR	reg32,reg16	386,PROT
LAR	reg32,reg32	386,PROT
LAR	reg32,reg64	X64,PROT,ND
LAR	reg64,mem	X64,PROT,SW
LAR	reg64,reg16	X64,PROT
LAR	reg64,reg32	X64,PROT
LAR	reg64,reg64	X64,PROT
LDS	reg16,mem	8086,NOLONG
LDS	reg32,mem	386,NOLONG
LEA	reg16,mem	8086
LEA	reg32,mem	386
LEA	reg64,mem	X64
LEAVE		186
LES	reg16,mem	8086,NOLONG
LES	reg32,mem	386,NOLONG
LFENCE		X64,AMD
LFS	reg16,mem	386
LFS	reg32,mem	386
LFS	reg64,mem	X64
LGDT	mem	286,PRIV
LGS	reg16,mem	386

LGS	reg32, mem	386
LGS	reg64, mem	X64
LIDT	mem	286, PRIV
LLDT	mem	286, PROT, PRIV
LLDT	mem16	286, PROT, PRIV
LLDT	reg16	286, PROT, PRIV
LMSW	mem	286, PRIV
LMSW	mem16	286, PRIV
LMSW	reg16	286, PRIV
LOADALL		386, UNDOC, ND, OBSOLETE
LOADALL286		286, UNDOC, ND, OBSOLETE
LODSB		8086
LODSD		386
LODSQ		X64
LODSW		8086
LOOP	imm	8086
LOOP	imm, reg_cx	8086, NOLONG
LOOP	imm, reg_ecx	386
LOOP	imm, reg_rcx	X64
LOOPE	imm	8086
LOOPE	imm, reg_cx	8086, NOLONG
LOOPE	imm, reg_ecx	386
LOOPE	imm, reg_rcx	X64
LOOPNE	imm	8086
LOOPNE	imm, reg_cx	8086, NOLONG
LOOPNE	imm, reg_ecx	386
LOOPNE	imm, reg_rcx	X64
LOOPNZ	imm	8086
LOOPNZ	imm, reg_cx	8086, NOLONG
LOOPNZ	imm, reg_ecx	386
LOOPNZ	imm, reg_rcx	X64
LOOPZ	imm	8086
LOOPZ	imm, reg_cx	8086, NOLONG
LOOPZ	imm, reg_ecx	386
LOOPZ	imm, reg_rcx	X64
LSL	reg16, mem	286, PROT, SW
LSL	reg16, reg16	286, PROT
LSL	reg16, reg32	386, PROT
LSL	reg16, reg64	X64, PROT, ND
LSL	reg32, mem	386, PROT, SW
LSL	reg32, reg16	386, PROT
LSL	reg32, reg32	386, PROT
LSL	reg32, reg64	X64, PROT, ND
LSL	reg64, mem	X64, PROT, SW
LSL	reg64, reg16	X64, PROT
LSL	reg64, reg32	X64, PROT
LSL	reg64, reg64	X64, PROT
LSS	reg16, mem	386
LSS	reg32, mem	386
LSS	reg64, mem	X64
LTR	mem	286, PROT, PRIV
LTR	mem16	286, PROT, PRIV
LTR	reg16	286, PROT, PRIV
MFENCE		X64, AMD

MONITOR		PRESCOTT
MONITOR	reg_eax, reg_ecx, reg_edx	PRESCOTT, NOLONG, ND
MONITOR	reg_rax, reg_ecx, reg_edx	X64, ND
MONITORX		AMD
MONITORX	reg_rax, reg_ecx, reg_edx	X64, AMD, ND
MONITORX	reg_eax, reg_ecx, reg_edx	AMD, ND
MONITORX	reg_ax, reg_ecx, reg_edx	AMD, ND
MOV	mem, reg_sreg	8086, SW
MOV	reg16, reg_sreg	8086
MOV	reg32, reg_sreg	386
MOV	reg64, reg_sreg	X64, OPT, ND
MOV	rm64, reg_sreg	X64
MOV	reg_sreg, mem	8086, SW
MOV	reg_sreg, reg16	8086, OPT, ND
MOV	reg_sreg, reg32	386, OPT, ND
MOV	reg_sreg, reg64	X64, OPT, ND
MOV	reg_sreg, reg16	8086
MOV	reg_sreg, reg32	386
MOV	reg_sreg, rm64	X64
MOV	reg_al, mem_offs	8086
MOV	reg_ax, mem_offs	8086
MOV	reg_eax, mem_offs	386
MOV	reg_rax, mem_offs	X64
MOV	mem_offs, reg_al	8086, NOHLE
MOV	mem_offs, reg_ax	8086, NOHLE
MOV	mem_offs, reg_eax	386, NOHLE
MOV	mem_offs, reg_rax	X64, NOHLE
MOV	reg32, reg_creg	386, PRIV, NOLONG
MOV	reg64, reg_creg	X64, PRIV
MOV	reg_creg, reg32	386, PRIV, NOLONG
MOV	reg_creg, reg64	X64, PRIV
MOV	reg32, reg_dreg	386, PRIV, NOLONG
MOV	reg64, reg_dreg	X64, PRIV
MOV	reg_dreg, reg32	386, PRIV, NOLONG
MOV	reg_dreg, reg64	X64, PRIV
MOV	reg32, reg_treg	386, NOLONG, ND
MOV	reg_treg, reg32	386, NOLONG, ND
MOV	mem, reg8	8086
MOV	reg8, reg8	8086
MOV	mem, reg16	8086
MOV	reg16, reg16	8086
MOV	mem, reg32	386
MOV	reg32, reg32	386
MOV	mem, reg64	X64
MOV	reg64, reg64	X64
MOV	reg8, mem	8086
MOV	reg8, reg8	8086
MOV	reg16, mem	8086
MOV	reg16, reg16	8086
MOV	reg32, mem	386
MOV	reg32, reg32	386
MOV	reg64, mem	X64
MOV	reg64, reg64	X64
MOV	reg8, imm	8086

MOV	reg16,imm	8086
MOV	reg32,imm	386
MOV	reg64,udword	X64,OPT,ND
MOV	reg64,sdword	X64,OPT,ND
MOV	reg64,imm	X64
MOV	rm8,imm	8086
MOV	rm16,imm	8086
MOV	rm32,imm	386
MOV	rm64,imm	X64
MOV	rm64,imm32	X64
MOV	mem,imm8	8086
MOV	mem,imm16	8086
MOV	mem,imm32	386
MOVD	mmxreg,rm32	PENT,MMX,SD
MOVD	rm32,mmxreg	PENT,MMX,SD
MOVD	mmxreg,rm64	X64,MMX,SX,ND
MOVD	rm64,mmxreg	X64,MMX,SX,ND
MOVQ	mmxreg,mmxrm	PENT,MMX
MOVQ	mmxrm,mmxreg	PENT,MMX
MOVQ	mmxreg,rm64	X64,MMX
MOVQ	rm64,mmxreg	X64,MMX
MOVSB		8086
MOVSD		386
MOVSQ		X64
MOVSW		8086
MOVSX	reg16,mem	386
MOVSX	reg16,reg8	386
MOVSX	reg32,rm8	386
MOVSX	reg32,rm16	386
MOVSX	reg64,rm8	X64
MOVSX	reg64,rm16	X64
MOVXSD	reg64,rm32	X64
MOVSX	reg64,rm32	X64,ND
MOVZX	reg16,mem	386
MOVZX	reg16,reg8	386
MOVZX	reg32,rm8	386
MOVZX	reg32,rm16	386
MOVZX	reg64,rm8	X64
MOVZX	reg64,rm16	X64
MUL	rm8	8086
MUL	rm16	8086
MUL	rm32	386
MUL	rm64	X64
MWAIT		PRESCOTT
MWAIT	reg_eax,reg_ecx	PRESCOTT,ND
MWAITX		AMD
MWAITX	reg_eax,reg_ecx	AMD,ND
NEG	rm8	8086,LOCK
NEG	rm16	8086,LOCK
NEG	rm32	386,LOCK
NEG	rm64	X64,LOCK
NOP		8086
NOP	rm16	P6
NOP	rm32	P6

NOP	rm64	X64
NOT	rm8	8086, LOCK
NOT	rm16	8086, LOCK
NOT	rm32	386, LOCK
NOT	rm64	X64, LOCK
OR	mem, reg8	8086, LOCK
OR	reg8, reg8	8086
OR	mem, reg16	8086, LOCK
OR	reg16, reg16	8086
OR	mem, reg32	386, LOCK
OR	reg32, reg32	386
OR	mem, reg64	X64, LOCK
OR	reg64, reg64	X64
OR	reg8, mem	8086
OR	reg8, reg8	8086
OR	reg16, mem	8086
OR	reg16, reg16	8086
OR	reg32, mem	386
OR	reg32, reg32	386
OR	reg64, mem	X64
OR	reg64, reg64	X64
OR	rm16, imm8	8086, LOCK
OR	rm32, imm8	386, LOCK
OR	rm64, imm8	X64, LOCK
OR	reg_al, imm	8086
OR	reg_ax, sbytedword	8086, ND
OR	reg_ax, imm	8086
OR	reg_eax, sbytedword	386, ND
OR	reg_eax, imm	386
OR	reg_rax, sbytedword	X64, ND
OR	reg_rax, imm	X64
OR	rm8, imm	8086, LOCK
OR	rm16, sbytedword	8086, LOCK, ND
OR	rm16, imm	8086, LOCK
OR	rm32, sbytedword	386, LOCK, ND
OR	rm32, imm	386, LOCK
OR	rm64, sbytedword	X64, LOCK, ND
OR	rm64, imm	X64, LOCK
OR	mem, imm8	8086, LOCK
OR	mem, sbytedword16	8086, LOCK, ND
OR	mem, imm16	8086, LOCK
OR	mem, sbytedword32	386, LOCK, ND
OR	mem, imm32	386, LOCK
OR	rm8, imm	8086, LOCK, ND, NOLONG
OUT	imm, reg_al	8086
OUT	imm, reg_ax	8086
OUT	imm, reg_eax	386
OUT	reg_dx, reg_al	8086
OUT	reg_dx, reg_ax	8086
OUT	reg_dx, reg_eax	386
OUTSB		186
OUTSD		386
OUTSW		186
PACKSSDW	mmxreg, mmxrm	PENT, MMX

PENT,MMX
PENT,MMX
PENT,MMX
PENT,MMX
PENT,MMX
PENT,MMX,CYRIX
PENT,MMX
PENT,MMX
PENT,MMX
PENT,MMX
PENT,MMX
PENT,MMX
8086
PENT,MMX,CYRIX
PENT,3DNOW
PENT,MMX
PENT,MMX
PENT,MMX
PENT,MMX
PENT,MMX
PENT,MMX
PENT,MMX,CYRIX
PENT,3DNOW
PENT,3DNOW
PENT,3DNOW
PENT,3DNOW
PENT,3DNOW
PENT,3DNOW
PENT,3DNOW
PENT,3DNOW
PENT,3DNOW
PENT,3DNOW
PENT,3DNOW
PENT,3DNOW
PENT,3DNOW
PENT,3DNOW
PENT,3DNOW
PENT,3DNOW
PENT,3DNOW
PENT,3DNOW
PENT,3DNOW
PENT,3DNOW
PENT,MMX,CYRIX
PENT,MMX
PENT,MMX,CYRIX
PENT,MMX,CYRIX
PENT,3DNOW
PENT,MMX,CYRIX
PENT,MMX
PENT,MMX
PENT,MMX,CYRIX
PENT,MMX,CYRIX
PENT,MMX,CYRIX
PENT,MMX,CYRIX
8086
386,NOLONG
X64

POP	rm16	8086
POP	rm32	386,NOLONG
POP	rm64	X64
POP	reg_es	8086,NOLONG
POP	reg_cs	8086,UNDOC,ND,OBSOLETE
POP	reg_ss	8086,NOLONG
POP	reg_ds	8086,NOLONG
POP	reg_fs	386
POP	reg_gs	386
POPA		186,NOLONG
POPAD		386,NOLONG
POPAW		186,NOLONG
POPF		8086
POPFD		386,NOLONG
POPfq		X64
POPFW		8086
POR	mmxreg,mmxrm	PENT,MMX
PREFETCH	mem	PENT,3DNOW
PREFETCHW	mem	PENT,3DNOW
PSLLD	mmxreg,mmxrm	PENT,MMX
PSLLD	mmxreg,imm	PENT,MMX
PSLLQ	mmxreg,mmxrm	PENT,MMX
PSLLQ	mmxreg,imm	PENT,MMX
PSLLW	mmxreg,mmxrm	PENT,MMX
PSLLW	mmxreg,imm	PENT,MMX
PSRAD	mmxreg,mmxrm	PENT,MMX
PSRAD	mmxreg,imm	PENT,MMX
PSRAW	mmxreg,mmxrm	PENT,MMX
PSRAW	mmxreg,imm	PENT,MMX
PSRLD	mmxreg,mmxrm	PENT,MMX
PSRLD	mmxreg,imm	PENT,MMX
PSRLQ	mmxreg,mmxrm	PENT,MMX
PSRLQ	mmxreg,imm	PENT,MMX
PSRLW	mmxreg,mmxrm	PENT,MMX
PSRLW	mmxreg,imm	PENT,MMX
PSUBB	mmxreg,mmxrm	PENT,MMX
PSUBD	mmxreg,mmxrm	PENT,MMX
PSUBSB	mmxreg,mmxrm	PENT,MMX
PSUBSIW	mmxreg,mmxrm	PENT,MMX,CYRIX
PSUBSW	mmxreg,mmxrm	PENT,MMX
PSUBUSB	mmxreg,mmxrm	PENT,MMX
PSUBUSW	mmxreg,mmxrm	PENT,MMX
PSUBW	mmxreg,mmxrm	PENT,MMX
PUNPCKHBW	mmxreg,mmxrm	PENT,MMX
PUNPCKHDQ	mmxreg,mmxrm	PENT,MMX
PUNPCKHWD	mmxreg,mmxrm	PENT,MMX
PUNPCKLBW	mmxreg,mmxrm	PENT,MMX
PUNPCKLDQ	mmxreg,mmxrm	PENT,MMX
PUNPCKLWD	mmxreg,mmxrm	PENT,MMX
PUSH	reg16	8086
PUSH	reg32	386,NOLONG
PUSH	reg64	X64
PUSH	rm16	8086
PUSH	rm32	386,NOLONG

PUSH	rm64	X64
PUSH	reg_es	8086,NOLONG
PUSH	reg_cs	8086,NOLONG
PUSH	reg_ss	8086,NOLONG
PUSH	reg_ds	8086,NOLONG
PUSH	reg_fs	386
PUSH	reg_gs	386
PUSH	imm8	186
PUSH	sbytedword16	186,AR0,SIZE,ND
PUSH	imm16	186,AR0,SIZE
PUSH	sbytedword32	386,NOLONG,AR0,SIZE,ND
PUSH	imm32	386,NOLONG,AR0,SIZE
PUSH	sbytedword32	386,NOLONG,SD,ND
PUSH	imm32	386,NOLONG,SD
PUSH	sbytedword64	X64,AR0,SIZE,ND
PUSH	imm64	X64,AR0,SIZE
PUSH	sbytedword32	X64,AR0,SIZE,ND
PUSH	imm32	X64,AR0,SIZE
PUSHA		186,NOLONG
PUSHAD		386,NOLONG
PUSHAW		186,NOLONG
PUSHF		8086
PUSHFD		386,NOLONG
PUSHFQ		X64
PUSHFW		8086
PXOR	mmxreg,mmxrm	PENT,MMX
RCL	rm8,unity	8086
RCL	rm8,reg_cl	8086
RCL	rm8,imm8	186
RCL	rm16,unity	8086
RCL	rm16,reg_cl	8086
RCL	rm16,imm8	186
RCL	rm32,unity	386
RCL	rm32,reg_cl	386
RCL	rm32,imm8	386
RCL	rm64,unity	X64
RCL	rm64,reg_cl	X64
RCL	rm64,imm8	X64
RCR	rm8,unity	8086
RCR	rm8,reg_cl	8086
RCR	rm8,imm8	186
RCR	rm16,unity	8086
RCR	rm16,reg_cl	8086
RCR	rm16,imm8	186
RCR	rm32,unity	386
RCR	rm32,reg_cl	386
RCR	rm32,imm8	386
RCR	rm64,unity	X64
RCR	rm64,reg_cl	X64
RCR	rm64,imm8	X64
RDSHR	rm32	P6,CYRIX,SMM
RDMSR		PENT,PRIV
RDPMC		P6
RDTSR		PENT

RDTSCP		X86_64
RET		8086, BND
RET	imm	8086, SW, BND
RETF		8086
RETF	imm	8086, SW
RETN		8086, BND
RETN	imm	8086, SW, BND
ROL	rm8, unity	8086
ROL	rm8, reg_cl	8086
ROL	rm8, imm8	186
ROL	rm16, unity	8086
ROL	rm16, reg_cl	8086
ROL	rm16, imm8	186
ROL	rm32, unity	386
ROL	rm32, reg_cl	386
ROL	rm32, imm8	386
ROL	rm64, unity	X64
ROL	rm64, reg_cl	X64
ROL	rm64, imm8	X64
ROR	rm8, unity	8086
ROR	rm8, reg_cl	8086
ROR	rm8, imm8	186
ROR	rm16, unity	8086
ROR	rm16, reg_cl	8086
ROR	rm16, imm8	186
ROR	rm32, unity	386
ROR	rm32, reg_cl	386
ROR	rm32, imm8	386
ROR	rm64, unity	X64
ROR	rm64, reg_cl	X64
ROR	rm64, imm8	X64
RDM		P6, CYRIX, ND
RSDC	reg_sreg, mem80	486, CYRIX, SMM
RSLDT	mem80	486, CYRIX, SMM
RSM		PENT, SMM
RSTS	mem80	486, CYRIX, SMM
SAHF		8086
SAL	rm8, unity	8086, ND
SAL	rm8, reg_cl	8086, ND
SAL	rm8, imm8	186, ND
SAL	rm16, unity	8086, ND
SAL	rm16, reg_cl	8086, ND
SAL	rm16, imm8	186, ND
SAL	rm32, unity	386, ND
SAL	rm32, reg_cl	386, ND
SAL	rm32, imm8	386, ND
SAL	rm64, unity	X64, ND
SAL	rm64, reg_cl	X64, ND
SAL	rm64, imm8	X64, ND
SALC		8086, UNDOC
SAR	rm8, unity	8086
SAR	rm8, reg_cl	8086
SAR	rm8, imm8	186
SAR	rm16, unity	8086

SAR	rm16, reg_cl	8086
SAR	rm16, imm8	186
SAR	rm32, unity	386
SAR	rm32, reg_cl	386
SAR	rm32, imm8	386
SAR	rm64, unity	X64
SAR	rm64, reg_cl	X64
SAR	rm64, imm8	X64
SBB	mem, reg8	8086, LOCK
SBB	reg8, reg8	8086
SBB	mem, reg16	8086, LOCK
SBB	reg16, reg16	8086
SBB	mem, reg32	386, LOCK
SBB	reg32, reg32	386
SBB	mem, reg64	X64, LOCK
SBB	reg64, reg64	X64
SBB	reg8, mem	8086
SBB	reg8, reg8	8086
SBB	reg16, mem	8086
SBB	reg16, reg16	8086
SBB	reg32, mem	386
SBB	reg32, reg32	386
SBB	reg64, mem	X64
SBB	reg64, reg64	X64
SBB	rm16, imm8	8086, LOCK
SBB	rm32, imm8	386, LOCK
SBB	rm64, imm8	X64, LOCK
SBB	reg_al, imm	8086
SBB	reg_ax, sbytedword	8086, ND
SBB	reg_ax, imm	8086
SBB	reg_eax, sbytedword	386, ND
SBB	reg_eax, imm	386
SBB	reg_rax, sbytedword	X64, ND
SBB	reg_rax, imm	X64
SBB	rm8, imm	8086, LOCK
SBB	rm16, sbytedword	8086, LOCK, ND
SBB	rm16, imm	8086, LOCK
SBB	rm32, sbytedword	386, LOCK, ND
SBB	rm32, imm	386, LOCK
SBB	rm64, sbytedword	X64, LOCK, ND
SBB	rm64, imm	X64, LOCK
SBB	mem, imm8	8086, LOCK
SBB	mem, sbytedword16	8086, LOCK, ND
SBB	mem, imm16	8086, LOCK
SBB	mem, sbytedword32	386, LOCK, ND
SBB	mem, imm32	386, LOCK
SBB	rm8, imm	8086, LOCK, ND, NOLONG
SCASB		8086
SCASD		386
SCASQ		X64
SCASW		8086
SFENCE		X64, AMD
SGDT	mem	286
SHL	rm8, unity	8086

SHL	rm8, reg_cl	8086
SHL	rm8, imm8	186
SHL	rm16, unity	8086
SHL	rm16, reg_cl	8086
SHL	rm16, imm8	186
SHL	rm32, unity	386
SHL	rm32, reg_cl	386
SHL	rm32, imm8	386
SHL	rm64, unity	X64
SHL	rm64, reg_cl	X64
SHL	rm64, imm8	X64
SHLD	mem, reg16, imm	386
SHLD	reg16, reg16, imm	386
SHLD	mem, reg32, imm	386
SHLD	reg32, reg32, imm	386
SHLD	mem, reg64, imm	X64
SHLD	reg64, reg64, imm	X64
SHLD	mem, reg16, reg_cl	386
SHLD	reg16, reg16, reg_cl	386
SHLD	mem, reg32, reg_cl	386
SHLD	reg32, reg32, reg_cl	386
SHLD	mem, reg64, reg_cl	X64
SHLD	reg64, reg64, reg_cl	X64
SHR	rm8, unity	8086
SHR	rm8, reg_cl	8086
SHR	rm8, imm8	186
SHR	rm16, unity	8086
SHR	rm16, reg_cl	8086
SHR	rm16, imm8	186
SHR	rm32, unity	386
SHR	rm32, reg_cl	386
SHR	rm32, imm8	386
SHR	rm64, unity	X64
SHR	rm64, reg_cl	X64
SHR	rm64, imm8	X64
SHRD	mem, reg16, imm	386
SHRD	reg16, reg16, imm	386
SHRD	mem, reg32, imm	386
SHRD	reg32, reg32, imm	386
SHRD	mem, reg64, imm	X64
SHRD	reg64, reg64, imm	X64
SHRD	mem, reg16, reg_cl	386
SHRD	reg16, reg16, reg_cl	386
SHRD	mem, reg32, reg_cl	386
SHRD	reg32, reg32, reg_cl	386
SHRD	mem, reg64, reg_cl	X64
SHRD	reg64, reg64, reg_cl	X64
SIDT	mem	286
SLDT	mem	286
SLDT	mem16	286
SLDT	reg16	286
SLDT	reg32	386
SLDT	reg64	X64, ND
SLDT	reg64	X64

SKINIT		X64
SMI		386, UNDOC
SMINT		P6, CYRIX, ND
SMINTOLD		486, CYRIX, ND, OBSOLETE
SMSW	mem	286
SMSW	mem16	286
SMSW	reg16	286
SMSW	reg32	386
SMSW	reg64	X64
STC		8086
STD		8086
STI		8086
STOSB		8086
STOSD		386
STOSQ		X64
STOSW		8086
STR	mem	286, PROT
STR	mem16	286, PROT
STR	reg16	286, PROT
STR	reg32	386, PROT
STR	reg64	X64
SUB	mem, reg8	8086, LOCK
SUB	reg8, reg8	8086
SUB	mem, reg16	8086, LOCK
SUB	reg16, reg16	8086
SUB	mem, reg32	386, LOCK
SUB	reg32, reg32	386
SUB	mem, reg64	X64, LOCK
SUB	reg64, reg64	X64
SUB	reg8, mem	8086
SUB	reg8, reg8	8086
SUB	reg16, mem	8086
SUB	reg16, reg16	8086
SUB	reg32, mem	386
SUB	reg32, reg32	386
SUB	reg64, mem	X64
SUB	reg64, reg64	X64
SUB	rm16, imm8	8086, LOCK
SUB	rm32, imm8	386, LOCK
SUB	rm64, imm8	X64, LOCK
SUB	reg_al, imm	8086
SUB	reg_ax, sbytedword	8086, ND
SUB	reg_ax, imm	8086
SUB	reg_eax, sbytedword	386, ND
SUB	reg_eax, imm	386
SUB	reg_rax, sbytedword	X64, ND
SUB	reg_rax, imm	X64
SUB	rm8, imm	8086, LOCK
SUB	rm16, sbytedword	8086, LOCK, ND
SUB	rm16, imm	8086, LOCK
SUB	rm32, sbytedword	386, LOCK, ND
SUB	rm32, imm	386, LOCK
SUB	rm64, sbytedword	X64, LOCK, ND
SUB	rm64, imm	X64, LOCK

SUB	mem, imm8	8086, LOCK
SUB	mem, sbytedword16	8086, LOCK, ND
SUB	mem, imm16	8086, LOCK
SUB	mem, sbytedword32	386, LOCK, ND
SUB	mem, imm32	386, LOCK
SUB	rm8, imm	8086, LOCK, ND, NOLONG
SVDC	mem80, reg_sreg	486, CYRIX, SMM
SVLDT	mem80	486, CYRIX, SMM, ND
SVTS	mem80	486, CYRIX, SMM
SWAPGS		X64
SYSCALL		P6, AMD
SYSENTER		P6
SYSEXIT		P6, PRIV
SYSRET		P6, PRIV, AMD
TEST	mem, reg8	8086
TEST	reg8, reg8	8086
TEST	mem, reg16	8086
TEST	reg16, reg16	8086
TEST	mem, reg32	386
TEST	reg32, reg32	386
TEST	mem, reg64	X64
TEST	reg64, reg64	X64
TEST	reg8, mem	8086
TEST	reg16, mem	8086
TEST	reg32, mem	386
TEST	reg64, mem	X64
TEST	reg_al, imm	8086
TEST	reg_ax, imm	8086
TEST	reg_eax, imm	386
TEST	reg_rax, imm	X64
TEST	rm8, imm	8086
TEST	rm16, imm	8086
TEST	rm32, imm	386
TEST	rm64, imm	X64
TEST	mem, imm8	8086
TEST	mem, imm16	8086
TEST	mem, imm32	386
UD0		186
UD1	reg, rm16	186
UD1	reg, rm32	186
UD1	reg, rm64	186
UD1		186, ND
UD2B		186, ND
UD2B	reg, rm16	186, ND
UD2B	reg, rm32	186, ND
UD2B	reg, rm64	186, ND
UD2		186
UD2A		186, ND
UMOV	mem, reg8	386, UNDOC, ND
UMOV	reg8, reg8	386, UNDOC, ND
UMOV	mem, reg16	386, UNDOC, ND
UMOV	reg16, reg16	386, UNDOC, ND
UMOV	mem, reg32	386, UNDOC, ND
UMOV	reg32, reg32	386, UNDOC, ND

UMOV	reg8, mem	386, UNDOC, ND
UMOV	reg8, reg8	386, UNDOC, ND
UMOV	reg16, mem	386, UNDOC, ND
UMOV	reg16, reg16	386, UNDOC, ND
UMOV	reg32, mem	386, UNDOC, ND
UMOV	reg32, reg32	386, UNDOC, ND
VERR	mem	286, PROT
VERR	mem16	286, PROT
VERR	reg16	286, PROT
VERW	mem	286, PROT
VERW	mem16	286, PROT
VERW	reg16	286, PROT
FWAIT		8086
WBINVD		486, PRIV
WRSHR	rm32	P6, CYRIX, SMM
WRMSR		PENT, PRIV
XADD	mem, reg8	486, LOCK
XADD	reg8, reg8	486
XADD	mem, reg16	486, LOCK
XADD	reg16, reg16	486
XADD	mem, reg32	486, LOCK
XADD	reg32, reg32	486
XADD	mem, reg64	X64, LOCK
XADD	reg64, reg64	X64
XBTS	reg16, mem	386, SW, UNDOC, ND
XBTS	reg16, reg16	386, UNDOC, ND
XBTS	reg32, mem	386, SD, UNDOC, ND
XBTS	reg32, reg32	386, UNDOC, ND
XCHG	reg_ax, reg16	8086
XCHG	reg_eax, reg32na	386
XCHG	reg_rax, reg64	X64
XCHG	reg16, reg_ax	8086
XCHG	reg32na, reg_eax	386
XCHG	reg64, reg_rax	X64
XCHG	reg_eax, reg_eax	386, NOLONG
XCHG	reg8, mem	8086, LOCK
XCHG	reg8, reg8	8086
XCHG	reg16, mem	8086, LOCK
XCHG	reg16, reg16	8086
XCHG	reg32, mem	386, LOCK
XCHG	reg32, reg32	386
XCHG	reg64, mem	X64, LOCK
XCHG	reg64, reg64	X64
XCHG	mem, reg8	8086, LOCK
XCHG	reg8, reg8	8086
XCHG	mem, reg16	8086, LOCK
XCHG	reg16, reg16	8086
XCHG	mem, reg32	386, LOCK
XCHG	reg32, reg32	386
XCHG	mem, reg64	X64, LOCK
XCHG	reg64, reg64	X64
XLATB		8086
XLAT		8086
XOR	mem, reg8	8086, LOCK

XOR	reg8, reg8	8086
XOR	mem, reg16	8086, LOCK
XOR	reg16, reg16	8086
XOR	mem, reg32	386, LOCK
XOR	reg32, reg32	386
XOR	mem, reg64	X64, LOCK
XOR	reg64, reg64	X64
XOR	reg8, mem	8086
XOR	reg8, reg8	8086
XOR	reg16, mem	8086
XOR	reg16, reg16	8086
XOR	reg32, mem	386
XOR	reg32, reg32	386
XOR	reg64, mem	X64
XOR	reg64, reg64	X64
XOR	rm16, imm8	8086, LOCK
XOR	rm32, imm8	386, LOCK
XOR	rm64, imm8	X64, LOCK
XOR	reg_al, imm	8086
XOR	reg_ax, sbytedword	8086, ND
XOR	reg_ax, imm	8086
XOR	reg_eax, sbytedword	386, ND
XOR	reg_eax, imm	386
XOR	reg_rax, sbytedword	X64, ND
XOR	reg_rax, imm	X64
XOR	rm8, imm	8086, LOCK
XOR	rm16, sbytedword	8086, LOCK, ND
XOR	rm16, imm	8086, LOCK
XOR	rm32, sbytedword	386, LOCK, ND
XOR	rm32, imm	386, LOCK
XOR	rm64, sbytedword	X64, LOCK, ND
XOR	rm64, imm	X64, LOCK
XOR	mem, imm8	8086, LOCK
XOR	mem, sbytedword16	8086, LOCK, ND
XOR	mem, imm16	8086, LOCK
XOR	mem, sbytedword32	386, LOCK, ND
XOR	mem, imm32	386, LOCK
XOR	rm8, imm	8086, LOCK, ND, NOLONG
CMOVcc	reg16, mem	P6
CMOVcc	reg16, reg16	P6
CMOVcc	reg32, mem	P6
CMOVcc	reg32, reg32	P6
CMOVcc	reg64, mem	X64
CMOVcc	reg64, reg64	X64
Jcc	imm near	386, BND
Jcc	imm16 near	386, NOLONG, BND
Jcc	imm32 near	386, NOLONG, BND
Jcc	imm64 near	X64, BND
Jcc	imm short	8086, ND, BND
Jcc	imm	8086, ND, BND
Jcc	imm	386, ND, BND
Jcc	imm	8086, ND, BND
Jcc	imm	8086, BND

SETcc	mem	386
SETcc	reg8	386

B.1.3 Katmai Streaming SIMD instructions (SSE — a.k.a. KNI, XMM, MMX2)

ADDPS	xmmreg, xmmrm128	KATMAI, SSE
ADDSS	xmmreg, xmmrm32	KATMAI, SSE
ANDNPS	xmmreg, xmmrm128	KATMAI, SSE
ANDPS	xmmreg, xmmrm128	KATMAI, SSE
CMPEQPS	xmmreg, xmmrm128	KATMAI, SSE
CMPEQSS	xmmreg, xmmrm32	KATMAI, SSE
CMPLEPS	xmmreg, xmmrm128	KATMAI, SSE
CMPLESS	xmmreg, xmmrm32	KATMAI, SSE
CMPLTPS	xmmreg, xmmrm128	KATMAI, SSE
CMPLTSS	xmmreg, xmmrm32	KATMAI, SSE
CMPNEQPS	xmmreg, xmmrm128	KATMAI, SSE
CMPNEQSS	xmmreg, xmmrm32	KATMAI, SSE
CMPNLEPS	xmmreg, xmmrm128	KATMAI, SSE
CMPNLESS	xmmreg, xmmrm32	KATMAI, SSE
CMPNLTPS	xmmreg, xmmrm128	KATMAI, SSE
CMPNLTSS	xmmreg, xmmrm32	KATMAI, SSE
CMPPORDPS	xmmreg, xmmrm128	KATMAI, SSE
CMPPORDSS	xmmreg, xmmrm32	KATMAI, SSE
CMPUNORDPS	xmmreg, xmmrm128	KATMAI, SSE
CMPUNORDSS	xmmreg, xmmrm32	KATMAI, SSE
CMPPS	xmmreg, mem, imm	KATMAI, SSE
CMPPS	xmmreg, xmmreg, imm	KATMAI, SSE
CMPSS	xmmreg, mem, imm	KATMAI, SSE
CMPSS	xmmreg, xmmreg, imm	KATMAI, SSE
COMISS	xmmreg, xmmrm32	KATMAI, SSE
CVTPI2PS	xmmreg, mmxrm64	KATMAI, SSE, MMX
CVTPS2PI	mmxreg, xmmrm64	KATMAI, SSE, MMX
CVTSI2SS	xmmreg, mem	KATMAI, SSE, SD, AR1, ND
CVTSI2SS	xmmreg, rm32	KATMAI, SSE, SD, AR1
CVTSI2SS	xmmreg, rm64	X64, SSE, AR1
CVTSS2SI	reg32, xmmreg	KATMAI, SSE, SD, AR1
CVTSS2SI	reg32, mem	KATMAI, SSE, SD, AR1
CVTSS2SI	reg64, xmmreg	X64, SSE, SD, AR1
CVTSS2SI	reg64, mem	X64, SSE, SD, AR1
CVTTPS2PI	mmxreg, xmmrm	KATMAI, SSE, MMX
CVTTSS2SI	reg32, xmmrm	KATMAI, SSE, SD, AR1
CVTTSS2SI	reg64, xmmrm	X64, SSE, SD, AR1
DIVPS	xmmreg, xmmrm128	KATMAI, SSE
DIVSS	xmmreg, xmmrm32	KATMAI, SSE
LDMXCSR	mem32	KATMAI, SSE
MAXPS	xmmreg, xmmrm128	KATMAI, SSE
MAXSS	xmmreg, xmmrm32	KATMAI, SSE
MINPS	xmmreg, xmmrm128	KATMAI, SSE
MINSS	xmmreg, xmmrm32	KATMAI, SSE
MOVAPS	xmmreg, xmmrm128	KATMAI, SSE
MOVAPS	xmmrm128, xmmreg	KATMAI, SSE
MOVHPS	xmmreg, mem64	KATMAI, SSE
MOVHPS	mem64, xmmreg	KATMAI, SSE
MOVLHPS	xmmreg, xmmreg	KATMAI, SSE

MOVLPS	xmmreg, mem64	KATMAI, SSE
MOVLPS	mem64, xmmreg	KATMAI, SSE
MOVHLPs	xmmreg, xmmreg	KATMAI, SSE
MOVMSKPS	reg32, xmmreg	KATMAI, SSE
MOVMSKPS	reg64, xmmreg	X64, SSE
MOVNTPS	mem128, xmmreg	KATMAI, SSE
MOVSS	xmmreg, xmmrmm32	KATMAI, SSE
MOVSS	mem32, xmmreg	KATMAI, SSE
MOVSS	xmmreg, xmmreg	KATMAI, SSE
MOVUPS	xmmreg, xmmrmm128	KATMAI, SSE
MOVUPS	xmmrmm128, xmmreg	KATMAI, SSE
MULPS	xmmreg, xmmrmm128	KATMAI, SSE
MULSS	xmmreg, xmmrmm32	KATMAI, SSE
ORPS	xmmreg, xmmrmm128	KATMAI, SSE
RCPPS	xmmreg, xmmrmm128	KATMAI, SSE
RCPSS	xmmreg, xmmrmm32	KATMAI, SSE
RSQRTPS	xmmreg, xmmrmm128	KATMAI, SSE
RSQRTSS	xmmreg, xmmrmm32	KATMAI, SSE
SHUFPS	xmmreg, xmmrmm128, imm8	KATMAI, SSE
SQRTPS	xmmreg, xmmrmm128	KATMAI, SSE
SQRTSS	xmmreg, xmmrmm32	KATMAI, SSE
STMXCSR	mem32	KATMAI, SSE
SUBPS	xmmreg, xmmrmm128	KATMAI, SSE
SUBSS	xmmreg, xmmrmm32	KATMAI, SSE
UCOMISS	xmmreg, xmmrmm32	KATMAI, SSE
UNPCKHPS	xmmreg, xmmrmm128	KATMAI, SSE
UNPCKLPS	xmmreg, xmmrmm128	KATMAI, SSE
XORPS	xmmreg, xmmrmm128	KATMAI, SSE

B.1.4 Introduced in Deschutes but necessary for SSE support

FXRSTOR	mem	P6, SSE, FPU
FXRSTOR64	mem	X64, SSE, FPU
FXSAVE	mem	P6, SSE, FPU
FXSAVE64	mem	X64, SSE, FPU

B.1.5 XSAVE group (AVX and extended state)

XGETBV		NEHALEM
XSETBV		NEHALEM, PRIV
XSAVE	mem	NEHALEM
XSAVE64	mem	LONG, NEHALEM
XSAVEC	mem	
XSAVEC64	mem	LONG
XSAVEOPT	mem	
XSAVEOPT64	mem	LONG
XSAVES	mem	
XSAVES64	mem	LONG
XRSTOR	mem	NEHALEM
XRSTOR64	mem	LONG, NEHALEM
XRSTORS	mem	
XRSTORS64	mem	LONG

B.1.6 Generic memory operations

PREFETCHNTA	mem8	KATMAI
PREFETCHT0	mem8	KATMAI
PREFETCHT1	mem8	KATMAI
PREFETCHT2	mem8	KATMAI
SFENCE		KATMAI

B.1.7 New MMX instructions introduced in Katmai

MASKMOVQ	mmxreg, mmxreg	KATMAI, MMX
MOVNTQ	mem, mmxreg	KATMAI, MMX
PAVGB	mmxreg, mmxrm	KATMAI, MMX
PAVGW	mmxreg, mmxrm	KATMAI, MMX
PEXTRW	reg32, mmxreg, imm	KATMAI, MMX
PINSRW	mmxreg, mem, imm	KATMAI, MMX
PINSRW	mmxreg, rml6, imm	KATMAI, MMX
PINSRW	mmxreg, reg32, imm	KATMAI, MMX
PMAXSW	mmxreg, mmxrm	KATMAI, MMX
PMAXUB	mmxreg, mmxrm	KATMAI, MMX
PMINSW	mmxreg, mmxrm	KATMAI, MMX
PMINUB	mmxreg, mmxrm	KATMAI, MMX
PMOVMSKB	reg32, mmxreg	KATMAI, MMX
PMULHUW	mmxreg, mmxrm	KATMAI, MMX
PSADBW	mmxreg, mmxrm	KATMAI, MMX
PSHUFW	mmxreg, mmxrm, imm	KATMAI, MMX

B.1.8 AMD Enhanced 3DNow! (Athlon) instructions

PF2IW	mmxreg, mmxrm	PENT, 3DNOW
PFNACC	mmxreg, mmxrm	PENT, 3DNOW
PFPNACC	mmxreg, mmxrm	PENT, 3DNOW
PI2FW	mmxreg, mmxrm	PENT, 3DNOW
PSWAPD	mmxreg, mmxrm	PENT, 3DNOW

B.1.9 Willamette SSE2 Cacheability Instructions

MASKMOVDQU	xmmreg, xmmreg	WILLAMETTE, SSE2
CLFLUSH	mem	WILLAMETTE, SSE2
MOVNTDQ	mem, xmmreg	WILLAMETTE, SSE2, SO
MOVNTI	mem, reg32	WILLAMETTE, SD
MOVNTI	mem, reg64	X64
MOVNTPD	mem, xmmreg	WILLAMETTE, SSE2, SO
LFENCE		WILLAMETTE, SSE2
MFENCE		WILLAMETTE, SSE2

B.1.10 Willamette MMX instructions (SSE2 SIMD Integer Instructions)

MOVD	mem, xmmreg	WILLAMETTE, SSE2, SD
MOVD	xmmreg, mem	WILLAMETTE, SSE2, SD
MOVD	xmmreg, rm32	WILLAMETTE, SSE2
MOVD	rm32, xmmreg	WILLAMETTE, SSE2
MOVDQA	xmmreg, xmmreg	WILLAMETTE, SSE2
MOVDQA	mem, xmmreg	WILLAMETTE, SSE2, SO
MOVDQA	xmmreg, mem	WILLAMETTE, SSE2, SO
MOVDQA	xmmreg, xmmreg	WILLAMETTE, SSE2
MOVDQU	xmmreg, xmmreg	WILLAMETTE, SSE2

MOVDQU	mem, xmmreg	WILLAMETTE, SSE2, SO
MOVDQU	xmmreg, mem	WILLAMETTE, SSE2, SO
MOVDQU	xmmreg, xmmreg	WILLAMETTE, SSE2
MOVDQ2Q	mmxreg, xmmreg	WILLAMETTE, SSE2
MOVQ	xmmreg, xmmreg	WILLAMETTE, SSE2
MOVQ	xmmreg, xmmreg	WILLAMETTE, SSE2
MOVQ	mem, xmmreg	WILLAMETTE, SSE2
MOVQ	xmmreg, mem	WILLAMETTE, SSE2
MOVQ	xmmreg, rm64	X64, SSE2
MOVQ	rm64, xmmreg	X64, SSE2
MOVQ2DQ	xmmreg, mmxreg	WILLAMETTE, SSE2
PACKSSWB	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PACKSSDW	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PACKUSWB	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PADDB	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PADDW	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PADDD	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PADDQ	mmxreg, mmxrm	WILLAMETTE, MMX
PADDQ	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PADDSB	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PADDSW	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PADDUSB	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PADDUSW	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PAND	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PANDN	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PAVGB	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PAVGW	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PCMPEQB	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PCMPEQW	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PCMPEQD	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PCMPGTB	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PCMPGTW	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PCMPGTD	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PEXTRW	reg32, xmmreg, imm	WILLAMETTE, SSE2
PEXTRW	reg64, xmmreg, imm	X64, SSE2, ND
PINSRW	xmmreg, reg16, imm	WILLAMETTE, SSE2
PINSRW	xmmreg, reg32, imm	WILLAMETTE, SSE2, ND
PINSRW	xmmreg, reg64, imm	X64, SSE2, ND
PINSRW	xmmreg, mem, imm	WILLAMETTE, SSE2
PINSRW	xmmreg, mem16, imm	WILLAMETTE, SSE2
PMADDWD	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PMAXSW	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PMAXUB	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PMINSW	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PMINUB	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PMOVMSKB	reg32, xmmreg	WILLAMETTE, SSE2
PMULHUW	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PMULHW	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PMULLW	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PMULUDQ	mmxreg, mmxrm	WILLAMETTE, SSE2, SO
PMULUDQ	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
POR	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PSADBW	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PSHUFD	xmmreg, xmmreg, imm	WILLAMETTE, SSE2

PSHUFD	xmmreg, mem, imm	WILLAMETTE, SSE2
PSHUFW	xmmreg, xmmreg, imm	WILLAMETTE, SSE2
PSHUFW	xmmreg, mem, imm	WILLAMETTE, SSE2
PSHUFLW	xmmreg, xmmreg, imm	WILLAMETTE, SSE2
PSHUFLW	xmmreg, mem, imm	WILLAMETTE, SSE2
PSLLDQ	xmmreg, imm	WILLAMETTE, SSE2, AR1
PSLLW	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PSLLW	xmmreg, imm	WILLAMETTE, SSE2, AR1
PSLLD	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PSLLD	xmmreg, imm	WILLAMETTE, SSE2, AR1
PSLLQ	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PSLLQ	xmmreg, imm	WILLAMETTE, SSE2, AR1
PSRAW	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PSRAW	xmmreg, imm	WILLAMETTE, SSE2, AR1
PSRAD	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PSRAD	xmmreg, imm	WILLAMETTE, SSE2, AR1
PSRLDQ	xmmreg, imm	WILLAMETTE, SSE2, AR1
PSRLW	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PSRLW	xmmreg, imm	WILLAMETTE, SSE2, AR1
PSRLD	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PSRLD	xmmreg, imm	WILLAMETTE, SSE2, AR1
PSRLQ	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PSRLQ	xmmreg, imm	WILLAMETTE, SSE2, AR1
PSUBB	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PSUBW	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PSUBD	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PSUBQ	mmxreg, mmxrm	WILLAMETTE, SSE2, SO
PSUBQ	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PSUBSB	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PSUBSW	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PSUBUSB	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PSUBUSW	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PUNPCKHBW	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PUNPCKHWD	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PUNPCKHDQ	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PUNPCKHQDQ	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PUNPCKLBW	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PUNPCKLWD	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PUNPCKLDQ	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PUNPCKLQDQ	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
PXOR	xmmreg, xmmrm	WILLAMETTE, SSE2, SO

B.1.11 Willamette Streaming SIMD instructions (SSE2)

ADDPD	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
ADDSD	xmmreg, xmmrm	WILLAMETTE, SSE2
ANDNPD	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
ANDPD	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
CMPEQPD	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
CMPEQSD	xmmreg, xmmrm	WILLAMETTE, SSE2
CMPLEPD	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
CMPLESD	xmmreg, xmmrm	WILLAMETTE, SSE2
CMPLTPD	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
CMPLTSD	xmmreg, xmmrm	WILLAMETTE, SSE2

CMPNEQPD	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
CMPNEQSD	xmmreg, xmmrm	WILLAMETTE, SSE2
CMPNLEPD	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
CMPNLESD	xmmreg, xmmrm	WILLAMETTE, SSE2
CMPNLTPD	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
CMPNLTSD	xmmreg, xmmrm	WILLAMETTE, SSE2
CMPORDPD	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
CMPORDSD	xmmreg, xmmrm	WILLAMETTE, SSE2
CMPUNORDPD	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
CMPUNORDSD	xmmreg, xmmrm	WILLAMETTE, SSE2
CMPPD	xmmreg, xmmrm128, imm8	WILLAMETTE, SSE2
CMPSD	xmmreg, xmmrm128, imm8	WILLAMETTE, SSE2
COMISD	xmmreg, xmmrm	WILLAMETTE, SSE2
CVTDQ2PD	xmmreg, xmmrm	WILLAMETTE, SSE2
CVTDQ2PS	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
CVTPD2DQ	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
CVTPD2PI	mmxreg, xmmrm	WILLAMETTE, SSE2, SO
CVTPD2PS	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
CVTPI2PD	xmmreg, mmxrm	WILLAMETTE, SSE2
CVTPS2DQ	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
CVTPS2PD	xmmreg, xmmrm	WILLAMETTE, SSE2
CVTSD2SI	reg32, xmmreg	WILLAMETTE, SSE2, AR1
CVTSD2SI	reg32, mem	WILLAMETTE, SSE2, AR1
CVTSD2SI	reg64, xmmreg	X64, SSE2, AR1
CVTSD2SI	reg64, mem	X64, SSE2, AR1
CVTSD2SS	xmmreg, xmmrm	WILLAMETTE, SSE2
CVTSI2SD	xmmreg, mem	WILLAMETTE, SSE2, SD, AR1, ND
CVTSI2SD	xmmreg, rm32	WILLAMETTE, SSE2, SD, AR1
CVTSI2SD	xmmreg, rm64	X64, SSE2, AR1
CVTSS2SD	xmmreg, xmmrm	WILLAMETTE, SSE2, SD
CVTTPD2PI	mmxreg, xmmrm	WILLAMETTE, SSE2, SO
CVTTPD2DQ	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
CVTTPS2DQ	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
CVTTSD2SI	reg32, xmmreg	WILLAMETTE, SSE2, AR1
CVTTSD2SI	reg32, mem	WILLAMETTE, SSE2, AR1
CVTTSD2SI	reg64, xmmreg	X64, SSE2, AR1
CVTTSD2SI	reg64, mem	X64, SSE2, AR1
DIVPD	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
DIVSD	xmmreg, xmmrm	WILLAMETTE, SSE2
MAXPD	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
MAXSD	xmmreg, xmmrm	WILLAMETTE, SSE2
MINPD	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
MINSD	xmmreg, xmmrm	WILLAMETTE, SSE2
MOVAPD	xmmreg, xmmreg	WILLAMETTE, SSE2
MOVAPD	xmmreg, xmmreg	WILLAMETTE, SSE2
MOVAPD	mem, xmmreg	WILLAMETTE, SSE2, SO
MOVAPD	xmmreg, mem	WILLAMETTE, SSE2, SO
MOVHPD	mem, xmmreg	WILLAMETTE, SSE2
MOVHPD	xmmreg, mem	WILLAMETTE, SSE2
MOVLPD	mem64, xmmreg	WILLAMETTE, SSE2
MOVLPD	xmmreg, mem64	WILLAMETTE, SSE2
MOVMSKPD	reg32, xmmreg	WILLAMETTE, SSE2
MOVMSKPD	reg64, xmmreg	X64, SSE2
MOVSD	xmmreg, xmmreg	WILLAMETTE, SSE2

MOVSD	xmmreg, xmmreg	WILLAMETTE, SSE2
MOVSD	mem64, xmmreg	WILLAMETTE, SSE2
MOVSD	xmmreg, mem64	WILLAMETTE, SSE2
MOVUPD	xmmreg, xmmreg	WILLAMETTE, SSE2
MOVUPD	xmmreg, xmmreg	WILLAMETTE, SSE2
MOVUPD	mem, xmmreg	WILLAMETTE, SSE2, SO
MOVUPD	xmmreg, mem	WILLAMETTE, SSE2, SO
MULPD	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
MULSD	xmmreg, xmmrm	WILLAMETTE, SSE2
ORPD	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
SHUFPD	xmmreg, xmmreg, imm	WILLAMETTE, SSE2
SHUFPD	xmmreg, mem, imm	WILLAMETTE, SSE2
SQRTPD	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
SQRTSD	xmmreg, xmmrm	WILLAMETTE, SSE2
SUBPD	xmmreg, xmmrm	WILLAMETTE, SSE2, SO
SUBSD	xmmreg, xmmrm	WILLAMETTE, SSE2
UCOMISD	xmmreg, xmmrm	WILLAMETTE, SSE2
UNPCKHPD	xmmreg, xmmrm128	WILLAMETTE, SSE2
UNPCKLPD	xmmreg, xmmrm128	WILLAMETTE, SSE2
XORPD	xmmreg, xmmrm128	WILLAMETTE, SSE2

B.1.12 Prescott New Instructions (SSE3)

ADDSD	xmmreg, xmmrm	PRESCOTT, SSE3, SO
ADDSD	xmmreg, xmmrm	PRESCOTT, SSE3, SO
HADDPD	xmmreg, xmmrm	PRESCOTT, SSE3, SO
HADDPS	xmmreg, xmmrm	PRESCOTT, SSE3, SO
HSUBPD	xmmreg, xmmrm	PRESCOTT, SSE3, SO
HSUBPS	xmmreg, xmmrm	PRESCOTT, SSE3, SO
LDDQU	xmmreg, mem	PRESCOTT, SSE3, SO
MOVDDUP	xmmreg, xmmrm	PRESCOTT, SSE3
MOVSHDUP	xmmreg, xmmrm	PRESCOTT, SSE3
MOVSLDUP	xmmreg, xmmrm	PRESCOTT, SSE3

B.1.13 VMX/SVM Instructions

CLGI		VMX, AMD
STGI		VMX, AMD
VMCALL		VMX
VMCLEAR	mem	VMX
VMFUNC		VMX
VMLAUNCH		VMX
VMLOAD		VMX, AMD
VMMCALL		VMX, AMD
VMPTRLD	mem	VMX
VMPTRST	mem	VMX
VMREAD	rm32, reg32	VMX, NO LONG, SD
VMREAD	rm64, reg64	X64, VMX
VMRESUME		VMX
VMRUN		VMX, AMD
VMSAVE		VMX, AMD
VMWRITE	reg32, rm32	VMX, NO LONG, SD
VMWRITE	reg64, rm64	X64, VMX
VMXOFF		VMX
VMXON	mem	VMX

B.1.14 Extended Page Tables VMX instructions

INVEPT	reg32, mem	VMX, SO, NO LONG
INVEPT	reg64, mem	VMX, SO, LONG
INVVPID	reg32, mem	VMX, SO, NO LONG
INVVPID	reg64, mem	VMX, SO, LONG

B.1.15 Tejas New Instructions (SSSE3)

PABSB	mmxreg, mmxrm	SSSE3, MMX
PABSB	xmmreg, xmmrm	SSSE3
PABSW	mmxreg, mmxrm	SSSE3, MMX
PABSW	xmmreg, xmmrm	SSSE3
PABSD	mmxreg, mmxrm	SSSE3, MMX
PABSD	xmmreg, xmmrm	SSSE3
PALIGNR	mmxreg, mmxrm, imm	SSSE3, MMX
PALIGNR	xmmreg, xmmrm, imm	SSSE3
PHADDW	mmxreg, mmxrm	SSSE3, MMX
PHADDW	xmmreg, xmmrm	SSSE3
PHADDD	mmxreg, mmxrm	SSSE3, MMX
PHADDD	xmmreg, xmmrm	SSSE3
PHADDSW	mmxreg, mmxrm	SSSE3, MMX
PHADDSW	xmmreg, xmmrm	SSSE3
PHSUBW	mmxreg, mmxrm	SSSE3, MMX
PHSUBW	xmmreg, xmmrm	SSSE3
PHSUBD	mmxreg, mmxrm	SSSE3, MMX
PHSUBD	xmmreg, xmmrm	SSSE3
PHSUBSW	mmxreg, mmxrm	SSSE3, MMX
PHSUBSW	xmmreg, xmmrm	SSSE3
PMADDUBSW	mmxreg, mmxrm	SSSE3, MMX
PMADDUBSW	xmmreg, xmmrm	SSSE3
PMULHRSW	mmxreg, mmxrm	SSSE3, MMX
PMULHRSW	xmmreg, xmmrm	SSSE3
PSHUFB	mmxreg, mmxrm	SSSE3, MMX
PSHUFB	xmmreg, xmmrm	SSSE3
PSIGNB	mmxreg, mmxrm	SSSE3, MMX
PSIGNB	xmmreg, xmmrm	SSSE3
PSIGNW	mmxreg, mmxrm	SSSE3, MMX
PSIGNW	xmmreg, xmmrm	SSSE3
PSIGND	mmxreg, mmxrm	SSSE3, MMX
PSIGND	xmmreg, xmmrm	SSSE3

B.1.16 AMD SSE4A

EXTRQ	xmmreg, imm, imm	SSE4A, AMD
EXTRQ	xmmreg, xmmreg	SSE4A, AMD
INSERTQ	xmmreg, xmmreg, imm, imm	SSE4A, AMD
INSERTQ	xmmreg, xmmreg	SSE4A, AMD
MOVNTSD	mem, xmmreg	SSE4A, AMD
MOVNTSS	mem, xmmreg	SSE4A, AMD, SD

B.1.17 New instructions in Barcelona

LZCNT	reg16, rm16	P6, AMD
LZCNT	reg32, rm32	P6, AMD
LZCNT	reg64, rm64	X64, AMD

B.1.18 Penryn New Instructions (SSE4.1)

BLENDDP	xmmreg, xmmrm, imm	SSE41
BLENDPS	xmmreg, xmmrm, imm	SSE41
BLENDVPD	xmmreg, xmmrm, xmm0	SSE41
BLENDVPD	xmmreg, xmmrm	SSE41
BLENDVPS	xmmreg, xmmrm, xmm0	SSE41
BLENDVPS	xmmreg, xmmrm	SSE41
DPPD	xmmreg, xmmrm, imm	SSE41
DPPS	xmmreg, xmmrm, imm	SSE41
EXTRACTPS	rm32, xmmreg, imm	SSE41
EXTRACTPS	reg64, xmmreg, imm	SSE41, X64
INSERTPS	xmmreg, xmmrm, imm	SSE41, SD
MOVNTDQA	xmmreg, mem128	SSE41
MPSADBW	xmmreg, xmmrm, imm	SSE41
PACKUSDW	xmmreg, xmmrm	SSE41
PBLENDVB	xmmreg, xmmrm, xmm0	SSE41
PBLENDVB	xmmreg, xmmrm	SSE41
PBLENDW	xmmreg, xmmrm, imm	SSE41
PCMPEQQ	xmmreg, xmmrm	SSE41
PEXTRB	reg32, xmmreg, imm	SSE41
PEXTRB	mem8, xmmreg, imm	SSE41
PEXTRB	reg64, xmmreg, imm	SSE41, X64
PEXTRD	rm32, xmmreg, imm	SSE41
PEXTRQ	rm64, xmmreg, imm	SSE41, X64
PEXTRW	reg32, xmmreg, imm	SSE41
PEXTRW	mem16, xmmreg, imm	SSE41
PEXTRW	reg64, xmmreg, imm	SSE41, X64
PHMINPOSUW	xmmreg, xmmrm	SSE41
PINSRB	xmmreg, mem, imm	SSE41
PINSRB	xmmreg, rm8, imm	SSE41
PINSRB	xmmreg, reg32, imm	SSE41
PINSRD	xmmreg, mem, imm	SSE41
PINSRD	xmmreg, rm32, imm	SSE41
PINSRQ	xmmreg, mem, imm	SSE41, X64
PINSRQ	xmmreg, rm64, imm	SSE41, X64
PMAXSB	xmmreg, xmmrm	SSE41
PMAXSD	xmmreg, xmmrm	SSE41
PMAXUD	xmmreg, xmmrm	SSE41
PMAXUW	xmmreg, xmmrm	SSE41
PMINSB	xmmreg, xmmrm	SSE41
PMINSD	xmmreg, xmmrm	SSE41
PMINUD	xmmreg, xmmrm	SSE41
PMINUW	xmmreg, xmmrm	SSE41
PMOVSXBW	xmmreg, xmmrm	SSE41
PMOVSXBD	xmmreg, xmmrm	SSE41, SD
PMOVSXBQ	xmmreg, xmmrm	SSE41, SW
PMOVSXWD	xmmreg, xmmrm	SSE41
PMOVSXWQ	xmmreg, xmmrm	SSE41, SD
PMOVSXDQ	xmmreg, xmmrm	SSE41
PMOVZXBW	xmmreg, xmmrm	SSE41
PMOVZXBD	xmmreg, xmmrm	SSE41, SD
PMOVZXBQ	xmmreg, xmmrm	SSE41, SW
PMOVZXWD	xmmreg, xmmrm	SSE41

PMOVZXWQ	xmmreg, xmmrm	SSE41, SD
PMOVZXDQ	xmmreg, xmmrm	SSE41
PMULDQ	xmmreg, xmmrm	SSE41
PMULLD	xmmreg, xmmrm	SSE41
PTEST	xmmreg, xmmrm	SSE41
ROUNDPD	xmmreg, xmmrm, imm	SSE41
ROUNDPS	xmmreg, xmmrm, imm	SSE41
ROUNDSD	xmmreg, xmmrm, imm	SSE41
ROUNDSS	xmmreg, xmmrm, imm	SSE41

B.1.19 Nehalem New Instructions (SSE4.2)

CRC32	reg32, rm8	SSE42
CRC32	reg32, rm16	SSE42
CRC32	reg32, rm32	SSE42
CRC32	reg64, rm8	SSE42, X64
CRC32	reg64, rm64	SSE42, X64
PCMPESTRI	xmmreg, xmmrm, imm	SSE42
PCMPESTRM	xmmreg, xmmrm, imm	SSE42
PCMPISTRI	xmmreg, xmmrm, imm	SSE42
PCMPISTRM	xmmreg, xmmrm, imm	SSE42
PCMPGTQ	xmmreg, xmmrm	SSE42
POPCNT	reg16, rm16	NEHALEM, SW
POPCNT	reg32, rm32	NEHALEM, SD
POPCNT	reg64, rm64	NEHALEM, X64

B.1.20 Intel SMX

GETSEC	KATMAI
--------	--------

B.1.21 Geode (Cyrix) 3DNow! additions

PFRCPV	mmxreg, mmxrm	PENT, 3DNOW, CYRIX
PFRSQRTV	mmxreg, mmxrm	PENT, 3DNOW, CYRIX

B.1.22 Intel new instructions in ???

MOVBE	reg16, mem16	NEHALEM
MOVBE	reg32, mem32	NEHALEM
MOVBE	reg64, mem64	NEHALEM
MOVBE	mem16, reg16	NEHALEM
MOVBE	mem32, reg32	NEHALEM
MOVBE	mem64, reg64	NEHALEM

B.1.23 Intel AES instructions

AESENC	xmmreg, xmmrm128	SSE, WESTMERE
AESENCLAST	xmmreg, xmmrm128	SSE, WESTMERE
AESDEC	xmmreg, xmmrm128	SSE, WESTMERE
AESDECLAST	xmmreg, xmmrm128	SSE, WESTMERE
AESIMC	xmmreg, xmmrm128	SSE, WESTMERE
AESKEYGENASSIST	xmmreg, xmmrm128, imm8	SSE, WESTMERE

B.1.24 Intel AVX AES instructions

VAESENC	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VAESENCLAST	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VAESDEC	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE

VAESDECLAST	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VAESIMC	xmmreg, xmmrm128	AVX, SANDYBRIDGE
VAESKEYGENASSIST	xmmreg, xmmrm128, imm8	AVX, SANDYBRIDGE

B.1.25 Intel instruction extension based on pub number 319433–030 dated October 2017

VAESEN	ymmreg, ymmreg*, ymmrm256	VAES
VAESENCLAST	ymmreg, ymmreg*, ymmrm256	VAES
VAESDEC	ymmreg, ymmreg*, ymmrm256	VAES
VAESDECLAST	ymmreg, ymmreg*, ymmrm256	VAES
VAESEN	xmmreg, xmmreg*, xmmrm128	AVX512VL, VAES
VAESEN	ymmreg, ymmreg*, ymmrm256	AVX512VL, VAES
VAESENCLAST	xmmreg, xmmreg*, xmmrm128	AVX512VL, VAES
VAESENCLAST	ymmreg, ymmreg*, ymmrm256	AVX512VL, VAES
VAESDEC	xmmreg, xmmreg*, xmmrm128	AVX512VL, VAES
VAESDEC	ymmreg, ymmreg*, ymmrm256	AVX512VL, VAES
VAESDECLAST	xmmreg, xmmreg*, xmmrm128	AVX512VL, VAES
VAESDECLAST	ymmreg, ymmreg*, ymmrm256	AVX512VL, VAES
VAESEN	zmmreg, zmmreg*, zmmrm512	AVX512, VAES
VAESENCLAST	zmmreg, zmmreg*, zmmrm512	AVX512, VAES
VAESDEC	zmmreg, zmmreg*, zmmrm512	AVX512, VAES
VAESDECLAST	zmmreg, zmmreg*, zmmrm512	AVX512, VAES

B.1.26 Intel AVX instructions

VADDPD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VADDPD	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VADDP	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VADDP	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VADDSD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VADDSS	xmmreg, xmmreg*, xmmrm32	AVX, SANDYBRIDGE
VADDSUBPD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VADDSUBPD	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VADDSUBPS	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VADDSUBPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VANDPD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VANDPD	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VANDPS	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VANDPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VANDNPD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VANDNPD	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VANDNPS	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VANDNPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VBLENDPD	xmmreg, xmmreg*, xmmrm128, imm8	AVX, SANDYBRIDGE
VBLENDPD	ymmreg, ymmreg*, ymmrm256, imm8	AVX, SANDYBRIDGE
VBLENDPS	xmmreg, xmmreg*, xmmrm128, imm8	AVX, SANDYBRIDGE
VBLENDPS	ymmreg, ymmreg*, ymmrm256, imm8	AVX, SANDYBRIDGE
VBLENDVPD	xmmreg, xmmreg*, xmmrm128, xmmreg	AVX, SANDYBRIDGE
VBLENDVPD	ymmreg, ymmreg*, ymmrm256, ymmreg	AVX, SANDYBRIDGE
VBLENDVPS	xmmreg, xmmreg*, xmmrm128, xmmreg	AVX, SANDYBRIDGE
VBLENDVPS	ymmreg, ymmreg*, ymmrm256, ymmreg	AVX, SANDYBRIDGE
VBROADCASTSS	xmmreg, mem32	AVX, SANDYBRIDGE
VBROADCASTSS	ymmreg, mem32	AVX, SANDYBRIDGE
VBROADCASTSD	ymmreg, mem64	AVX, SANDYBRIDGE
VBROADCASTF128	ymmreg, mem128	AVX, SANDYBRIDGE

VCMPEQ_OSPD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VCMPEQ_OSPD	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPEQPD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VCMPEQPD	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPLT_OSPD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VCMPLT_OSPD	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPLTDP	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VCMPLTDP	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPLE_OSPD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VCMPLE_OSPD	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPLEPD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VCMPLEPD	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPUNORD_QPD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VCMPUNORD_QPD	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPUNORDPD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VCMPUNORDPD	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPNEQ_UQPD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VCMPNEQ_UQPD	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPNEQPD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VCMPNEQPD	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPNLT_USPD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VCMPNLT_USPD	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPNLTDP	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VCMPNLTDP	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPNLE_USPD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VCMPNLE_USPD	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPNLEPD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VCMPNLEPD	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPORD_QPD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VCMPORD_QPD	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPORDPD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VCMPORDPD	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPEQ_UQPD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VCMPEQ_UQPD	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPNGE_USPD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VCMPNGE_USPD	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPNGEPD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VCMPNGEPD	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPNGT_USPD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VCMPNGT_USPD	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPNGTPD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VCMPNGTPD	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPFALSE_OQPD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VCMPFALSE_OQPD	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPFALSEPD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VCMPFALSEPD	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPNEQ_OQPD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VCMPNEQ_OQPD	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPGE_OSPD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VCMPGE_OSPD	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPGEPD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VCMPGEPD	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPGT_OSPD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VCMPGT_OSPD	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE

172

VCMPUNORDPS	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VCMPUNORDPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPNEQ_UQPS	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VCMPNEQ_UQPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPNEQPS	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VCMPNEQPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPNLT_USPS	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VCMPNLT_USPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPNLTPS	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VCMPNLTPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPNLE_USPS	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VCMPNLE_USPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPNLEPS	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VCMPNLEPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPORD_QPS	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VCMPORD_QPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPORDPS	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VCMPORDPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPEQ_UQPS	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VCMPEQ_UQPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPNGE_USPS	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VCMPNGE_USPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPNGEPS	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VCMPNGEPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPNGT_USPS	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VCMPNGT_USPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPNGTPS	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VCMPNGTPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPFALSE_OQPS	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VCMPFALSE_OQPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPFALSEPS	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VCMPFALSEPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPNEQ_OQPS	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VCMPNEQ_OQPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPGE_OSPS	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VCMPGE_OSPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPGEPS	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VCMPGEPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPGT_OSPS	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VCMPGT_OSPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPGTPS	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VCMPGTPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPTRUE_UQPS	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VCMPTRUE_UQPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPTRUEPS	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VCMPTRUEPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPEQ_OSPS	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VCMPEQ_OSPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPLT_OQPS	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VCMPLT_OQPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPLE_OQPS	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VCMPLE_OQPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VCMPUNORD_SPS	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VCMPUNORD_SPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE

VCMPPNEQ_USPS	xmmreg, xmmreg*, xmmrmm128	AVX, SANDYBRIDGE
VCMPPNEQ_USPS	ymmreg, ymmreg*, ymmrmm256	AVX, SANDYBRIDGE
VCMPPNLT_UQPS	xmmreg, xmmreg*, xmmrmm128	AVX, SANDYBRIDGE
VCMPPNLT_UQPS	ymmreg, ymmreg*, ymmrmm256	AVX, SANDYBRIDGE
VCMPPNLE_UQPS	xmmreg, xmmreg*, xmmrmm128	AVX, SANDYBRIDGE
VCMPPNLE_UQPS	ymmreg, ymmreg*, ymmrmm256	AVX, SANDYBRIDGE
VCMPPORD_SPS	xmmreg, xmmreg*, xmmrmm128	AVX, SANDYBRIDGE
VCMPPORD_SPS	ymmreg, ymmreg*, ymmrmm256	AVX, SANDYBRIDGE
VCMPPPEQ_USPS	xmmreg, xmmreg*, xmmrmm128	AVX, SANDYBRIDGE
VCMPPPEQ_USPS	ymmreg, ymmreg*, ymmrmm256	AVX, SANDYBRIDGE
VCMPPNGE_UQPS	xmmreg, xmmreg*, xmmrmm128	AVX, SANDYBRIDGE
VCMPPNGE_UQPS	ymmreg, ymmreg*, ymmrmm256	AVX, SANDYBRIDGE
VCMPPNGT_UQPS	xmmreg, xmmreg*, xmmrmm128	AVX, SANDYBRIDGE
VCMPPNGT_UQPS	ymmreg, ymmreg*, ymmrmm256	AVX, SANDYBRIDGE
VCMPPFALSE_OSPS	xmmreg, xmmreg*, xmmrmm128	AVX, SANDYBRIDGE
VCMPPFALSE_OSPS	ymmreg, ymmreg*, ymmrmm256	AVX, SANDYBRIDGE
VCMPPNEQ_OSPS	xmmreg, xmmreg*, xmmrmm128	AVX, SANDYBRIDGE
VCMPPNEQ_OSPS	ymmreg, ymmreg*, ymmrmm256	AVX, SANDYBRIDGE
VCMPPGE_OQPS	xmmreg, xmmreg*, xmmrmm128	AVX, SANDYBRIDGE
VCMPPGE_OQPS	ymmreg, ymmreg*, ymmrmm256	AVX, SANDYBRIDGE
VCMPPGT_OQPS	xmmreg, xmmreg*, xmmrmm128	AVX, SANDYBRIDGE
VCMPPGT_OQPS	ymmreg, ymmreg*, ymmrmm256	AVX, SANDYBRIDGE
VCMPPTRUE_USPS	xmmreg, xmmreg*, xmmrmm128	AVX, SANDYBRIDGE
VCMPPTRUE_USPS	ymmreg, ymmreg*, ymmrmm256	AVX, SANDYBRIDGE
VCMPPPS	xmmreg, xmmreg*, xmmrmm128, imm8	AVX, SANDYBRIDGE
VCMPPPS	ymmreg, ymmreg*, ymmrmm256, imm8	AVX, SANDYBRIDGE
VCMPPPEQ_OSSD	xmmreg, xmmreg*, xmmrmm64	AVX, SANDYBRIDGE
VCMPPPEQSD	xmmreg, xmmreg*, xmmrmm64	AVX, SANDYBRIDGE
VCMPLT_OSSD	xmmreg, xmmreg*, xmmrmm64	AVX, SANDYBRIDGE
VCMPLTSD	xmmreg, xmmreg*, xmmrmm64	AVX, SANDYBRIDGE
VCMPPLE_OSSD	xmmreg, xmmreg*, xmmrmm64	AVX, SANDYBRIDGE
VCMPPLESD	xmmreg, xmmreg*, xmmrmm64	AVX, SANDYBRIDGE
VCMPPUNORD_QSD	xmmreg, xmmreg*, xmmrmm64	AVX, SANDYBRIDGE
VCMPPUNORDSD	xmmreg, xmmreg*, xmmrmm64	AVX, SANDYBRIDGE
VCMPPNEQ_UQSD	xmmreg, xmmreg*, xmmrmm64	AVX, SANDYBRIDGE
VCMPPNEQSD	xmmreg, xmmreg*, xmmrmm64	AVX, SANDYBRIDGE
VCMPPNLT_USSD	xmmreg, xmmreg*, xmmrmm64	AVX, SANDYBRIDGE
VCMPPNLTSD	xmmreg, xmmreg*, xmmrmm64	AVX, SANDYBRIDGE
VCMPPNLE_USSD	xmmreg, xmmreg*, xmmrmm64	AVX, SANDYBRIDGE
VCMPPNLESD	xmmreg, xmmreg*, xmmrmm64	AVX, SANDYBRIDGE
VCMPPORD_QSD	xmmreg, xmmreg*, xmmrmm64	AVX, SANDYBRIDGE
VCMPPORDSD	xmmreg, xmmreg*, xmmrmm64	AVX, SANDYBRIDGE
VCMPPPEQ_UQSD	xmmreg, xmmreg*, xmmrmm64	AVX, SANDYBRIDGE
VCMPPNGE_USSD	xmmreg, xmmreg*, xmmrmm64	AVX, SANDYBRIDGE
VCMPPNGESD	xmmreg, xmmreg*, xmmrmm64	AVX, SANDYBRIDGE
VCMPPNGT_USSD	xmmreg, xmmreg*, xmmrmm64	AVX, SANDYBRIDGE
VCMPPNGTSD	xmmreg, xmmreg*, xmmrmm64	AVX, SANDYBRIDGE
VCMPPFALSE_OQSD	xmmreg, xmmreg*, xmmrmm64	AVX, SANDYBRIDGE
VCMPPFALSESD	xmmreg, xmmreg*, xmmrmm64	AVX, SANDYBRIDGE
VCMPPNEQ_OQSD	xmmreg, xmmreg*, xmmrmm64	AVX, SANDYBRIDGE
VCMPPGE_OSSD	xmmreg, xmmreg*, xmmrmm64	AVX, SANDYBRIDGE
VCMPPGESD	xmmreg, xmmreg*, xmmrmm64	AVX, SANDYBRIDGE
VCMPPGT_OSSD	xmmreg, xmmreg*, xmmrmm64	AVX, SANDYBRIDGE
VCMPPGTSD	xmmreg, xmmreg*, xmmrmm64	AVX, SANDYBRIDGE

VCMPTTRUE_UQSD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPTTRUESD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPEQ_OSSD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPLT_OQSD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPL_E_OQSD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMFPUNORD_SSD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMFPNEQ_USSD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMFPNLT_UQSD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMFPNLE_UQSD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMFPORD_SSD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPEQ_USSD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPNGE_UQSD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPNGT_UQSD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMFALSE_OSSD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMFPNEQ_OSSD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMFGE_OQSD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMFGT_OQSD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPTTRUE_USSD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPSD	xmmreg, xmmreg*, xmmrm64, imm8	AVX, SANDYBRIDGE
VCMPEQ_OSSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPEQSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPLT_OSSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPLTSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPL_E_OSSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPLESS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMFPUNORD_QSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMFPUNORDSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMFPNEQ_UQSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMFPNEQSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMFPNLT_USSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMFPNLTSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMFPNLE_USSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMFPNLESS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMFPORD_QSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMFPORDSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPEQ_UQSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPNGE_USSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPNGESS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPNGT_USSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPNGTSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMFALSE_OQSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMFALSESS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMFPNEQ_OQSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMFGE_OSSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMFGESS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMFGT_OSSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMFGTSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPTTRUE_UQSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPTTRUESS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPEQ_OSSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPLT_OQSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPL_E_OQSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMFPUNORD_SSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMFPNEQ_USSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE

VCMPLNT_UQSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPLNE_UQSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPORD_SSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPEQ_USSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPNGE_UQSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPNGT_UQSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPFALSE_OSSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPNEQ_OSSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPGE_OQSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPGT_OQSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPTRUE_USSS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCMPS	xmmreg, xmmreg*, xmmrm64, imm8	AVX, SANDYBRIDGE
VCOMISD	xmmreg, xmmrm64	AVX, SANDYBRIDGE
VCOMISS	xmmreg, xmmrm32	AVX, SANDYBRIDGE
VCVTDQ2PD	xmmreg, xmmrm64	AVX, SANDYBRIDGE
VCVTDQ2PD	ymmreg, xmmrm128	AVX, SANDYBRIDGE
VCVTDQ2PS	xmmreg, xmmrm128	AVX, SANDYBRIDGE
VCVTDQ2PS	ymmreg, ymmrm256	AVX, SANDYBRIDGE
VCVTPD2DQ	xmmreg, xmmreg	AVX, SANDYBRIDGE
VCVTPD2DQ	xmmreg, mem128	AVX, SANDYBRIDGE, SO
VCVTPD2DQ	xmmreg, ymmreg	AVX, SANDYBRIDGE
VCVTPD2DQ	xmmreg, mem256	AVX, SANDYBRIDGE, SY
VCVTPD2PS	xmmreg, xmmreg	AVX, SANDYBRIDGE
VCVTPD2PS	xmmreg, mem128	AVX, SANDYBRIDGE, SO
VCVTPD2PS	xmmreg, ymmreg	AVX, SANDYBRIDGE
VCVTPD2PS	xmmreg, mem256	AVX, SANDYBRIDGE, SY
VCVTPS2DQ	xmmreg, xmmrm128	AVX, SANDYBRIDGE
VCVTPS2DQ	ymmreg, ymmrm256	AVX, SANDYBRIDGE
VCVTPS2PD	xmmreg, xmmrm64	AVX, SANDYBRIDGE
VCVTPS2PD	ymmreg, xmmrm128	AVX, SANDYBRIDGE
VCVTSD2SI	reg32, xmmrm64	AVX, SANDYBRIDGE
VCVTSD2SI	reg64, xmmrm64	AVX, SANDYBRIDGE, LONG
VCVTSD2SS	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VCVTSI2SD	xmmreg, xmmreg*, rm32	AVX, SANDYBRIDGE, SD
VCVTSI2SD	xmmreg, xmmreg*, mem32	AVX, SANDYBRIDGE, ND, SD
VCVTSI2SD	xmmreg, xmmreg*, rm64	AVX, SANDYBRIDGE, LONG
VCVTSI2SS	xmmreg, xmmreg*, rm32	AVX, SANDYBRIDGE, SD
VCVTSI2SS	xmmreg, xmmreg*, mem32	AVX, SANDYBRIDGE, ND, SD
VCVTSI2SS	xmmreg, xmmreg*, rm64	AVX, SANDYBRIDGE, LONG
VCVTSS2SD	xmmreg, xmmreg*, xmmrm32	AVX, SANDYBRIDGE
VCVTSS2SI	reg32, xmmrm32	AVX, SANDYBRIDGE
VCVTSS2SI	reg64, xmmrm32	AVX, SANDYBRIDGE, LONG
VCVTTPD2DQ	xmmreg, xmmreg	AVX, SANDYBRIDGE
VCVTTPD2DQ	xmmreg, mem128	AVX, SANDYBRIDGE, SO
VCVTTPD2DQ	xmmreg, ymmreg	AVX, SANDYBRIDGE
VCVTTPD2DQ	xmmreg, mem256	AVX, SANDYBRIDGE, SY
VCVTTPS2DQ	xmmreg, xmmrm128	AVX, SANDYBRIDGE
VCVTTPS2DQ	ymmreg, ymmrm256	AVX, SANDYBRIDGE
VCVTTS2SI	reg32, xmmrm64	AVX, SANDYBRIDGE
VCVTTS2SI	reg64, xmmrm64	AVX, SANDYBRIDGE, LONG
VCVTSS2SI	reg32, xmmrm32	AVX, SANDYBRIDGE
VCVTSS2SI	reg64, xmmrm32	AVX, SANDYBRIDGE, LONG
VDIVPD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VDIVPD	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE

VDIVPS	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VDIVPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VDIVSD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VDIVSS	xmmreg, xmmreg*, xmmrm32	AVX, SANDYBRIDGE
VDPPD	xmmreg, xmmreg*, xmmrm128, imm8	AVX, SANDYBRIDGE
VDPPS	xmmreg, xmmreg*, xmmrm128, imm8	AVX, SANDYBRIDGE
VDPPS	ymmreg, ymmreg*, ymmrm256, imm8	AVX, SANDYBRIDGE
VEXTRACTF128	xmmrm128, ymmreg, imm8	AVX, SANDYBRIDGE
VEXTRACTPS	rm32, xmmreg, imm8	AVX, SANDYBRIDGE
VHADDPD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VHADDPD	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VHADDPD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VHADDPD	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VHSUBPD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VHSUBPD	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VHSUBPD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VHSUBPD	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VINSERTF128	ymmreg, ymmreg*, xmmrm128, imm8	AVX, SANDYBRIDGE
VINSERTPS	xmmreg, xmmreg*, xmmrm32, imm8	AVX, SANDYBRIDGE
VLDDQU	xmmreg, mem128	AVX, SANDYBRIDGE
VLDQQU	ymmreg, mem256	AVX, SANDYBRIDGE
VLDQQU	ymmreg, mem256	AVX, SANDYBRIDGE
VLDMXCSR	mem32	AVX, SANDYBRIDGE
VMASKMOVDQU	xmmreg, xmmreg	AVX, SANDYBRIDGE
VMASKMOVPS	xmmreg, xmmreg, mem128	AVX, SANDYBRIDGE
VMASKMOVPS	ymmreg, ymmreg, mem256	AVX, SANDYBRIDGE
VMASKMOVPS	mem128, xmmreg, xmmreg	AVX, SANDYBRIDGE, SO
VMASKMOVPS	mem256, ymmreg, ymmreg	AVX, SANDYBRIDGE, SY
VMASKMOVPD	xmmreg, xmmreg, mem128	AVX, SANDYBRIDGE
VMASKMOVPD	ymmreg, ymmreg, mem256	AVX, SANDYBRIDGE
VMASKMOVPD	mem128, xmmreg, xmmreg	AVX, SANDYBRIDGE
VMASKMOVPD	mem256, ymmreg, ymmreg	AVX, SANDYBRIDGE
VMAXPD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VMAXPD	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VMAXPS	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VMAXPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VMAXSD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VMAXSS	xmmreg, xmmreg*, xmmrm32	AVX, SANDYBRIDGE
VMINPD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VMINPD	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VMINPS	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VMINPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VMINSD	xmmreg, xmmreg*, xmmrm64	AVX, SANDYBRIDGE
VMINSS	xmmreg, xmmreg*, xmmrm32	AVX, SANDYBRIDGE
VMOVAPD	xmmreg, xmmrm128	AVX, SANDYBRIDGE
VMOVAPD	xmmrm128, xmmreg	AVX, SANDYBRIDGE
VMOVAPD	ymmreg, ymmrm256	AVX, SANDYBRIDGE
VMOVAPD	ymmrm256, ymmreg	AVX, SANDYBRIDGE
VMOVAPS	xmmreg, xmmrm128	AVX, SANDYBRIDGE
VMOVAPS	xmmrm128, xmmreg	AVX, SANDYBRIDGE
VMOVAPS	ymmreg, ymmrm256	AVX, SANDYBRIDGE
VMOVAPS	ymmrm256, ymmreg	AVX, SANDYBRIDGE
VMOVD	xmmreg, rm32	AVX, SANDYBRIDGE
VMOVD	rm32, xmmreg	AVX, SANDYBRIDGE

VMOVQ	xmmreg, xmmrm64	AVX, SANDYBRIDGE
VMOVQ	xmmrm64, xmmreg	AVX, SANDYBRIDGE
VMOVQ	xmmreg, rm64	AVX, SANDYBRIDGE, LONG
VMOVQ	rm64, xmmreg	AVX, SANDYBRIDGE, LONG
VMOVDDUP	xmmreg, xmmrm64	AVX, SANDYBRIDGE
VMOVDDUP	ymmreg, ymmrm256	AVX, SANDYBRIDGE
VMOVDQA	xmmreg, xmmrm128	AVX, SANDYBRIDGE
VMOVDQA	xmmrm128, xmmreg	AVX, SANDYBRIDGE
VMOVQQA	ymmreg, ymmrm256	AVX, SANDYBRIDGE
VMOVQQA	ymmrm256, ymmreg	AVX, SANDYBRIDGE
VMOVDQA	ymmreg, ymmrm256	AVX, SANDYBRIDGE
VMOVDQA	ymmrm256, ymmreg	AVX, SANDYBRIDGE
VMOVDQU	xmmreg, xmmrm128	AVX, SANDYBRIDGE
VMOVDQU	xmmrm128, xmmreg	AVX, SANDYBRIDGE
VMOVQQU	ymmreg, ymmrm256	AVX, SANDYBRIDGE
VMOVQQU	ymmrm256, ymmreg	AVX, SANDYBRIDGE
VMOVDQU	ymmreg, ymmrm256	AVX, SANDYBRIDGE
VMOVDQU	ymmrm256, ymmreg	AVX, SANDYBRIDGE
VMOVHLPD	xmmreg, xmmreg*, xmmreg	AVX, SANDYBRIDGE
VMOVHPD	xmmreg, xmmreg*, mem64	AVX, SANDYBRIDGE
VMOVHPD	mem64, xmmreg	AVX, SANDYBRIDGE
VMOVHPS	xmmreg, xmmreg*, mem64	AVX, SANDYBRIDGE
VMOVHPS	mem64, xmmreg	AVX, SANDYBRIDGE
VMOVLHPD	xmmreg, xmmreg*, xmmreg	AVX, SANDYBRIDGE
VMOVLHPD	xmmreg, xmmreg*, mem64	AVX, SANDYBRIDGE
VMOVLHPD	mem64, xmmreg	AVX, SANDYBRIDGE
VMOVLPS	xmmreg, xmmreg*, mem64	AVX, SANDYBRIDGE
VMOVLPS	mem64, xmmreg	AVX, SANDYBRIDGE
VMOVMSKPD	reg64, xmmreg	AVX, SANDYBRIDGE, LONG
VMOVMSKPD	reg32, xmmreg	AVX, SANDYBRIDGE
VMOVMSKPD	reg64, ymmreg	AVX, SANDYBRIDGE, LONG
VMOVMSKPD	reg32, ymmreg	AVX, SANDYBRIDGE
VMOVMSKPS	reg64, xmmreg	AVX, SANDYBRIDGE, LONG
VMOVMSKPS	reg32, xmmreg	AVX, SANDYBRIDGE
VMOVMSKPS	reg64, ymmreg	AVX, SANDYBRIDGE, LONG
VMOVMSKPS	reg32, ymmreg	AVX, SANDYBRIDGE
VMOVNTDQ	mem128, xmmreg	AVX, SANDYBRIDGE
VMOVNTQQ	mem256, ymmreg	AVX, SANDYBRIDGE
VMOVNTDQ	mem256, ymmreg	AVX, SANDYBRIDGE
VMOVNTDQA	xmmreg, mem128	AVX, SANDYBRIDGE
VMOVNTPD	mem128, xmmreg	AVX, SANDYBRIDGE
VMOVNTPD	mem256, ymmreg	AVX, SANDYBRIDGE
VMOVNTPS	mem128, xmmreg	AVX, SANDYBRIDGE
VMOVNTPS	mem256, ymmreg	AVX, SANDYBRIDGE
VMOVSD	xmmreg, xmmreg*, xmmreg	AVX, SANDYBRIDGE
VMOVSD	xmmreg, mem64	AVX, SANDYBRIDGE
VMOVSD	xmmreg, xmmreg*, xmmreg	AVX, SANDYBRIDGE
VMOVSD	mem64, xmmreg	AVX, SANDYBRIDGE
VMOVSHDUP	xmmreg, xmmrm128	AVX, SANDYBRIDGE
VMOVSHDUP	ymmreg, ymmrm256	AVX, SANDYBRIDGE
VMOVSLDUP	xmmreg, xmmrm128	AVX, SANDYBRIDGE
VMOVSLDUP	ymmreg, ymmrm256	AVX, SANDYBRIDGE
VMOVSS	xmmreg, xmmreg*, xmmreg	AVX, SANDYBRIDGE
VMOVSS	xmmreg, mem32	AVX, SANDYBRIDGE

VMOVSS	xmmreg, xmmreg*, xmmreg	AVX, SANDYBRIDGE
VMOVSS	mem32, xmmreg	AVX, SANDYBRIDGE
VMOVUPD	xmmreg, xmmrml28	AVX, SANDYBRIDGE
VMOVUPD	xmmrml28, xmmreg	AVX, SANDYBRIDGE
VMOVUPD	ymmreg, ymmrml256	AVX, SANDYBRIDGE
VMOVUPD	ymmrm256, ymmreg	AVX, SANDYBRIDGE
VMOVUPS	xmmreg, xmmrml28	AVX, SANDYBRIDGE
VMOVUPS	xmmrml28, xmmreg	AVX, SANDYBRIDGE
VMOVUPS	ymmreg, ymmrml256	AVX, SANDYBRIDGE
VMOVUPS	ymmrm256, ymmreg	AVX, SANDYBRIDGE
VMPSADBW	xmmreg, xmmreg*, xmmrml28, imm8	AVX, SANDYBRIDGE
VMULPD	xmmreg, xmmreg*, xmmrml28	AVX, SANDYBRIDGE
VMULPD	ymmreg, ymmreg*, ymmrml256	AVX, SANDYBRIDGE
VMULPS	xmmreg, xmmreg*, xmmrml28	AVX, SANDYBRIDGE
VMULPS	ymmreg, ymmreg*, ymmrml256	AVX, SANDYBRIDGE
VMULSD	xmmreg, xmmreg*, xmmrml64	AVX, SANDYBRIDGE
VMULSS	xmmreg, xmmreg*, xmmrml32	AVX, SANDYBRIDGE
VORPD	xmmreg, xmmreg*, xmmrml28	AVX, SANDYBRIDGE
VORPD	ymmreg, ymmreg*, ymmrml256	AVX, SANDYBRIDGE
VORPS	xmmreg, xmmreg*, xmmrml28	AVX, SANDYBRIDGE
VORPS	ymmreg, ymmreg*, ymmrml256	AVX, SANDYBRIDGE
VPABSB	xmmreg, xmmrml28	AVX, SANDYBRIDGE
VPABSW	xmmreg, xmmrml28	AVX, SANDYBRIDGE
VPABSD	xmmreg, xmmrml28	AVX, SANDYBRIDGE
VPACKSSWB	xmmreg, xmmreg*, xmmrml28	AVX, SANDYBRIDGE
VPACKSSDW	xmmreg, xmmreg*, xmmrml28	AVX, SANDYBRIDGE
VPACKUSWB	xmmreg, xmmreg*, xmmrml28	AVX, SANDYBRIDGE
VPACKUSDW	xmmreg, xmmreg*, xmmrml28	AVX, SANDYBRIDGE
VPADDB	xmmreg, xmmreg*, xmmrml28	AVX, SANDYBRIDGE
VPADDW	xmmreg, xmmreg*, xmmrml28	AVX, SANDYBRIDGE
VPADD	xmmreg, xmmreg*, xmmrml28	AVX, SANDYBRIDGE
VPADDQ	xmmreg, xmmreg*, xmmrml28	AVX, SANDYBRIDGE
VPADDSB	xmmreg, xmmreg*, xmmrml28	AVX, SANDYBRIDGE
VPADDSW	xmmreg, xmmreg*, xmmrml28	AVX, SANDYBRIDGE
VPADDUSB	xmmreg, xmmreg*, xmmrml28	AVX, SANDYBRIDGE
VPADDUSW	xmmreg, xmmreg*, xmmrml28	AVX, SANDYBRIDGE
VPALIGNR	xmmreg, xmmreg*, xmmrml28, imm8	AVX, SANDYBRIDGE
VPAND	xmmreg, xmmreg*, xmmrml28	AVX, SANDYBRIDGE
VPANDN	xmmreg, xmmreg*, xmmrml28	AVX, SANDYBRIDGE
VPAVGB	xmmreg, xmmreg*, xmmrml28	AVX, SANDYBRIDGE
VPAVGW	xmmreg, xmmreg*, xmmrml28	AVX, SANDYBRIDGE
VPBLENDVB	xmmreg, xmmreg*, xmmrml28, xmmreg	AVX, SANDYBRIDGE
VPBLENDW	xmmreg, xmmreg*, xmmrml28, imm8	AVX, SANDYBRIDGE
VPCMPESTRI	xmmreg, xmmrml28, imm8	AVX, SANDYBRIDGE
VPCMPESTRM	xmmreg, xmmrml28, imm8	AVX, SANDYBRIDGE
VPCMPISTRI	xmmreg, xmmrml28, imm8	AVX, SANDYBRIDGE
VPCMPISTRM	xmmreg, xmmrml28, imm8	AVX, SANDYBRIDGE
VPCMPEQB	xmmreg, xmmreg*, xmmrml28	AVX, SANDYBRIDGE
VPCMPQW	xmmreg, xmmreg*, xmmrml28	AVX, SANDYBRIDGE
VPCMPQD	xmmreg, xmmreg*, xmmrml28	AVX, SANDYBRIDGE
VPCMPQQ	xmmreg, xmmreg*, xmmrml28	AVX, SANDYBRIDGE
VPCMPGTB	xmmreg, xmmreg*, xmmrml28	AVX, SANDYBRIDGE
VPCMPGTW	xmmreg, xmmreg*, xmmrml28	AVX, SANDYBRIDGE
VPCMPGTD	xmmreg, xmmreg*, xmmrml28	AVX, SANDYBRIDGE

VPCMPGTQ	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPERMILPD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPERMILPD	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VPERMILPD	xmmreg, xmmrm128, imm8	AVX, SANDYBRIDGE
VPERMILPD	ymmreg, ymmrm256, imm8	AVX, SANDYBRIDGE
VPERMILPS	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPERMILPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VPERMILPS	xmmreg, xmmrm128, imm8	AVX, SANDYBRIDGE
VPERMILPS	ymmreg, ymmrm256, imm8	AVX, SANDYBRIDGE
VPERM2F128	ymmreg, ymmreg*, ymmrm256, imm8	AVX, SANDYBRIDGE
VPEXTRB	reg64, xmmreg, imm8	AVX, SANDYBRIDGE, LONG
VPEXTRB	reg32, xmmreg, imm8	AVX, SANDYBRIDGE
VPEXTRB	mem8, xmmreg, imm8	AVX, SANDYBRIDGE
VPEXTRW	reg64, xmmreg, imm8	AVX, SANDYBRIDGE, LONG
VPEXTRW	reg32, xmmreg, imm8	AVX, SANDYBRIDGE
VPEXTRW	reg64, xmmreg, imm8	AVX, SANDYBRIDGE, LONG
VPEXTRW	reg32, xmmreg, imm8	AVX, SANDYBRIDGE
VPEXTRW	mem16, xmmreg, imm8	AVX, SANDYBRIDGE
VPEXTRD	reg64, xmmreg, imm8	AVX, SANDYBRIDGE, LONG
VPEXTRD	rm32, xmmreg, imm8	AVX, SANDYBRIDGE
VPEXTRQ	rm64, xmmreg, imm8	AVX, SANDYBRIDGE, LONG
VPHADDW	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPHADD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPHADDSW	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPHMINPOSUW	xmmreg, xmmrm128	AVX, SANDYBRIDGE
VPHSUBW	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPHSUBD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPHSUBSW	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPINSRB	xmmreg, xmmreg*, mem8, imm8	AVX, SANDYBRIDGE
VPINSRB	xmmreg, xmmreg*, rm8, imm8	AVX, SANDYBRIDGE
VPINSRB	xmmreg, xmmreg*, reg32, imm8	AVX, SANDYBRIDGE
VPINSRW	xmmreg, xmmreg*, mem16, imm8	AVX, SANDYBRIDGE
VPINSRW	xmmreg, xmmreg*, rm16, imm8	AVX, SANDYBRIDGE
VPINSRW	xmmreg, xmmreg*, reg32, imm8	AVX, SANDYBRIDGE
VPINSRD	xmmreg, xmmreg*, mem32, imm8	AVX, SANDYBRIDGE
VPINSRD	xmmreg, xmmreg*, rm32, imm8	AVX, SANDYBRIDGE
VPINSRQ	xmmreg, xmmreg*, mem64, imm8	AVX, SANDYBRIDGE, LONG
VPINSRQ	xmmreg, xmmreg*, rm64, imm8	AVX, SANDYBRIDGE, LONG
VPMADDWD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPMADDUBSW	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPMASXB	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPMASXW	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPMASXD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPMASUB	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPMASUW	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPMASUD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPMINSB	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPMINSW	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPMIND	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPMINUB	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPMINUW	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPMINUD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPMOVMASKB	reg64, xmmreg	AVX, SANDYBRIDGE, LONG
VPMOVMASKB	reg32, xmmreg	AVX, SANDYBRIDGE

VPMOVSBW	xmmreg, xmmrm64	AVX, SANDYBRIDGE
VPMOVXBD	xmmreg, xmmrm32	AVX, SANDYBRIDGE
VPMOVXBQ	xmmreg, xmmrm16	AVX, SANDYBRIDGE
VPMOVXWD	xmmreg, xmmrm64	AVX, SANDYBRIDGE
VPMOVXWQ	xmmreg, xmmrm32	AVX, SANDYBRIDGE
VPMOVXDQ	xmmreg, xmmrm64	AVX, SANDYBRIDGE
VPMOVZXBW	xmmreg, xmmrm64	AVX, SANDYBRIDGE
VPMOVZXBQ	xmmreg, xmmrm32	AVX, SANDYBRIDGE
VPMOVZXBQ	xmmreg, xmmrm16	AVX, SANDYBRIDGE
VPMOVZXWD	xmmreg, xmmrm64	AVX, SANDYBRIDGE
VPMOVZXWQ	xmmreg, xmmrm32	AVX, SANDYBRIDGE
VPMOVZXDQ	xmmreg, xmmrm64	AVX, SANDYBRIDGE
VPMULHUW	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPMULHSW	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPMULHW	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPMULLW	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPMULLD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPMULUDQ	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPMULDQ	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPOR	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPSADBW	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPSHUFB	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPSHUFD	xmmreg, xmmrm128, imm8	AVX, SANDYBRIDGE
VPSHUFHW	xmmreg, xmmrm128, imm8	AVX, SANDYBRIDGE
VPSHUFLW	xmmreg, xmmrm128, imm8	AVX, SANDYBRIDGE
VPSIGNB	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPSIGNW	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPSIGND	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPSLLDQ	xmmreg, xmmreg*, imm8	AVX, SANDYBRIDGE
VPSRLDQ	xmmreg, xmmreg*, imm8	AVX, SANDYBRIDGE
VPSLLW	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPSLLW	xmmreg, xmmreg*, imm8	AVX, SANDYBRIDGE
VPSLLD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPSLLD	xmmreg, xmmreg*, imm8	AVX, SANDYBRIDGE
VPSLLQ	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPSLLQ	xmmreg, xmmreg*, imm8	AVX, SANDYBRIDGE
VPSRAW	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPSRAW	xmmreg, xmmreg*, imm8	AVX, SANDYBRIDGE
VPSRAD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPSRAD	xmmreg, xmmreg*, imm8	AVX, SANDYBRIDGE
VPSRLW	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPSRLW	xmmreg, xmmreg*, imm8	AVX, SANDYBRIDGE
VPSRLD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPSRLD	xmmreg, xmmreg*, imm8	AVX, SANDYBRIDGE
VPSRLQ	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPSRLQ	xmmreg, xmmreg*, imm8	AVX, SANDYBRIDGE
VPTEST	xmmreg, xmmrm128	AVX, SANDYBRIDGE
VPTEST	ymmreg, ymmrm256	AVX, SANDYBRIDGE
VPSUBB	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPSUBW	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPSUBD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPSUBQ	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPSUBSB	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPSUBSW	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE

VPSUBUSB	xmmreg, xmmreg*, xmmrmm128	AVX, SANDYBRIDGE
VPSUBUSW	xmmreg, xmmreg*, xmmrmm128	AVX, SANDYBRIDGE
VPUNPCKHBW	xmmreg, xmmreg*, xmmrmm128	AVX, SANDYBRIDGE
VPUNPCKHWD	xmmreg, xmmreg*, xmmrmm128	AVX, SANDYBRIDGE
VPUNPCKHDQ	xmmreg, xmmreg*, xmmrmm128	AVX, SANDYBRIDGE
VPUNPCKHQDQ	xmmreg, xmmreg*, xmmrmm128	AVX, SANDYBRIDGE
VPUNPCKLBW	xmmreg, xmmreg*, xmmrmm128	AVX, SANDYBRIDGE
VPUNPCKLWD	xmmreg, xmmreg*, xmmrmm128	AVX, SANDYBRIDGE
VPUNPCKLDQ	xmmreg, xmmreg*, xmmrmm128	AVX, SANDYBRIDGE
VPUNPCKLQDQ	xmmreg, xmmreg*, xmmrmm128	AVX, SANDYBRIDGE
VPXOR	xmmreg, xmmreg*, xmmrmm128	AVX, SANDYBRIDGE
VRCPPS	xmmreg, xmmrmm128	AVX, SANDYBRIDGE
VRCPPS	ymmreg, ymmrmm256	AVX, SANDYBRIDGE
VRCPS	xmmreg, xmmreg*, xmmrmm32	AVX, SANDYBRIDGE
VRSQRTPS	xmmreg, xmmrmm128	AVX, SANDYBRIDGE
VRSQRTPS	ymmreg, ymmrmm256	AVX, SANDYBRIDGE
VRSQRTSS	xmmreg, xmmreg*, xmmrmm32	AVX, SANDYBRIDGE
VROUNDPD	xmmreg, xmmrmm128, imm8	AVX, SANDYBRIDGE
VROUNDPD	ymmreg, ymmrmm256, imm8	AVX, SANDYBRIDGE
VROUNDPS	xmmreg, xmmrmm128, imm8	AVX, SANDYBRIDGE
VROUNDPS	ymmreg, ymmrmm256, imm8	AVX, SANDYBRIDGE
VROUNDSD	xmmreg, xmmreg*, xmmrmm64, imm8	AVX, SANDYBRIDGE
VROUNDSS	xmmreg, xmmreg*, xmmrmm32, imm8	AVX, SANDYBRIDGE
VSHUFPD	xmmreg, xmmreg*, xmmrmm128, imm8	AVX, SANDYBRIDGE
VSHUFPD	ymmreg, ymmreg*, ymmrmm256, imm8	AVX, SANDYBRIDGE
VSHUFPS	xmmreg, xmmreg*, xmmrmm128, imm8	AVX, SANDYBRIDGE
VSHUFPS	ymmreg, ymmreg*, ymmrmm256, imm8	AVX, SANDYBRIDGE
VSQRTPD	xmmreg, xmmrmm128	AVX, SANDYBRIDGE
VSQRTPD	ymmreg, ymmrmm256	AVX, SANDYBRIDGE
VSQRTPS	xmmreg, xmmrmm128	AVX, SANDYBRIDGE
VSQRTPS	ymmreg, ymmrmm256	AVX, SANDYBRIDGE
VSQRTSD	xmmreg, xmmreg*, xmmrmm64	AVX, SANDYBRIDGE
VSQRTSS	xmmreg, xmmreg*, xmmrmm32	AVX, SANDYBRIDGE
VSTMXCSR	mem32	AVX, SANDYBRIDGE
VSUBPD	xmmreg, xmmreg*, xmmrmm128	AVX, SANDYBRIDGE
VSUBPD	ymmreg, ymmreg*, ymmrmm256	AVX, SANDYBRIDGE
VSUBPS	xmmreg, xmmreg*, xmmrmm128	AVX, SANDYBRIDGE
VSUBPS	ymmreg, ymmreg*, ymmrmm256	AVX, SANDYBRIDGE
VSUBSD	xmmreg, xmmreg*, xmmrmm64	AVX, SANDYBRIDGE
VSUBSS	xmmreg, xmmreg*, xmmrmm32	AVX, SANDYBRIDGE
VTESTPS	xmmreg, xmmrmm128	AVX, SANDYBRIDGE
VTESTPS	ymmreg, ymmrmm256	AVX, SANDYBRIDGE
VTESTPD	xmmreg, xmmrmm128	AVX, SANDYBRIDGE
VTESTPD	ymmreg, ymmrmm256	AVX, SANDYBRIDGE
VUCOMISD	xmmreg, xmmrmm64	AVX, SANDYBRIDGE
VUCOMISS	xmmreg, xmmrmm32	AVX, SANDYBRIDGE
VUNPCKHPD	xmmreg, xmmreg*, xmmrmm128	AVX, SANDYBRIDGE
VUNPCKHPD	ymmreg, ymmreg*, ymmrmm256	AVX, SANDYBRIDGE
VUNPCKHPS	xmmreg, xmmreg*, xmmrmm128	AVX, SANDYBRIDGE
VUNPCKHPS	ymmreg, ymmreg*, ymmrmm256	AVX, SANDYBRIDGE
VUNPCKLPD	xmmreg, xmmreg*, xmmrmm128	AVX, SANDYBRIDGE
VUNPCKLPD	ymmreg, ymmreg*, ymmrmm256	AVX, SANDYBRIDGE
VUNPCKLPS	xmmreg, xmmreg*, xmmrmm128	AVX, SANDYBRIDGE
VUNPCKLPS	ymmreg, ymmreg*, ymmrmm256	AVX, SANDYBRIDGE

VXORPD	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VXORPD	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VXORPS	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VXORPS	ymmreg, ymmreg*, ymmrm256	AVX, SANDYBRIDGE
VZEROALL		AVX, SANDYBRIDGE
VZERoupper		AVX, SANDYBRIDGE

B.1.27 Intel Carry–Less Multiplication instructions (CLMUL)

PCLMULLQLQDQ	xmmreg, xmmrm128	SSE, WESTMERE
PCLMULHQLQDQ	xmmreg, xmmrm128	SSE, WESTMERE
PCLMULLQHQQDQ	xmmreg, xmmrm128	SSE, WESTMERE
PCLMULHQQDQ	xmmreg, xmmrm128	SSE, WESTMERE
PCLMULQDQ	xmmreg, xmmrm128, imm8	SSE, WESTMERE

B.1.28 Intel AVX Carry–Less Multiplication instructions (CLMUL)

VPCLMULLQLQDQ	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPCLMULHQLQDQ	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPCLMULLQHQQDQ	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPCLMULHQQDQ	xmmreg, xmmreg*, xmmrm128	AVX, SANDYBRIDGE
VPCLMULQDQ	xmmreg, xmmreg*, xmmrm128, imm8	AVX, SANDYBRIDGE
VPCLMULLQLQDQ	ymmreg, ymmreg*, ymmrm256	VPCLMULQDQ
VPCLMULHQLQDQ	ymmreg, ymmreg*, ymmrm256	VPCLMULQDQ
VPCLMULLQHQQDQ	ymmreg, ymmreg*, ymmrm256	VPCLMULQDQ
VPCLMULHQQDQ	ymmreg, ymmreg*, ymmrm256	VPCLMULQDQ
VPCLMULQDQ	ymmreg, ymmreg*, ymmrm256, imm8	VPCLMULQDQ
VPCLMULLQLQDQ	xmmreg, xmmreg*, xmmrm128	AVX512VL, VPCLMULQDQ
VPCLMULHQLQDQ	xmmreg, xmmreg*, xmmrm128	AVX512VL, VPCLMULQDQ
VPCLMULLQHQQDQ	xmmreg, xmmreg*, xmmrm128	AVX512VL, VPCLMULQDQ
VPCLMULHQQDQ	xmmreg, xmmreg*, xmmrm128	AVX512VL, VPCLMULQDQ
VPCLMULQDQ	xmmreg, xmmreg*, xmmrm128, imm8	AVX512VL, VPCLMULQDQ
VPCLMULLQLQDQ	ymmreg, ymmreg*, ymmrm256	AVX512VL, VPCLMULQDQ
VPCLMULHQLQDQ	ymmreg, ymmreg*, ymmrm256	AVX512VL, VPCLMULQDQ
VPCLMULLQHQQDQ	ymmreg, ymmreg*, ymmrm256	AVX512VL, VPCLMULQDQ
VPCLMULHQQDQ	ymmreg, ymmreg*, ymmrm256	AVX512VL, VPCLMULQDQ
VPCLMULQDQ	ymmreg, ymmreg*, ymmrm256, imm8	AVX512VL, VPCLMULQDQ
VPCLMULLQLQDQ	zmmreg, zmmreg*, zmmrm512	AVX512, VPCLMULQDQ
VPCLMULHQLQDQ	zmmreg, zmmreg*, zmmrm512	AVX512, VPCLMULQDQ
VPCLMULLQHQQDQ	zmmreg, zmmreg*, zmmrm512	AVX512, VPCLMULQDQ
VPCLMULHQQDQ	zmmreg, zmmreg*, zmmrm512	AVX512, VPCLMULQDQ
VPCLMULQDQ	zmmreg, zmmreg*, zmmrm512, imm8	AVX512, VPCLMULQDQ

B.1.29 Intel Fused Multiply–Add instructions (FMA)

VFMAADD132PS	xmmreg, xmmreg, xmmrm128	FMA
VFMAADD132PS	ymmreg, ymmreg, ymmrm256	FMA
VFMAADD132PD	xmmreg, xmmreg, xmmrm128	FMA
VFMAADD132PD	ymmreg, ymmreg, ymmrm256	FMA
VFMAADD312PS	xmmreg, xmmreg, xmmrm128	FMA
VFMAADD312PS	ymmreg, ymmreg, ymmrm256	FMA
VFMAADD312PD	xmmreg, xmmreg, xmmrm128	FMA
VFMAADD312PD	ymmreg, ymmreg, ymmrm256	FMA
VFMAADD213PS	xmmreg, xmmreg, xmmrm128	FMA
VFMAADD213PS	ymmreg, ymmreg, ymmrm256	FMA
VFMAADD213PD	xmmreg, xmmreg, xmmrm128	FMA

VFMADD213PD	ymmreg, ymmreg, ymmrm256	FMA
VFMADD123PS	xmmreg, xmmreg, xmmrm128	FMA
VFMADD123PS	ymmreg, ymmreg, ymmrm256	FMA
VFMADD123PD	xmmreg, xmmreg, xmmrm128	FMA
VFMADD123PD	ymmreg, ymmreg, ymmrm256	FMA
VFMADD231PS	xmmreg, xmmreg, xmmrm128	FMA
VFMADD231PS	ymmreg, ymmreg, ymmrm256	FMA
VFMADD231PD	xmmreg, xmmreg, xmmrm128	FMA
VFMADD231PD	ymmreg, ymmreg, ymmrm256	FMA
VFMADD321PS	xmmreg, xmmreg, xmmrm128	FMA
VFMADD321PS	ymmreg, ymmreg, ymmrm256	FMA
VFMADD321PD	xmmreg, xmmreg, xmmrm128	FMA
VFMADD321PD	ymmreg, ymmreg, ymmrm256	FMA
VFMADDSUB132PS	xmmreg, xmmreg, xmmrm128	FMA
VFMADDSUB132PS	ymmreg, ymmreg, ymmrm256	FMA
VFMADDSUB132PD	xmmreg, xmmreg, xmmrm128	FMA
VFMADDSUB132PD	ymmreg, ymmreg, ymmrm256	FMA
VFMADDSUB312PS	xmmreg, xmmreg, xmmrm128	FMA
VFMADDSUB312PS	ymmreg, ymmreg, ymmrm256	FMA
VFMADDSUB312PD	xmmreg, xmmreg, xmmrm128	FMA
VFMADDSUB312PD	ymmreg, ymmreg, ymmrm256	FMA
VFMADDSUB213PS	xmmreg, xmmreg, xmmrm128	FMA
VFMADDSUB213PS	ymmreg, ymmreg, ymmrm256	FMA
VFMADDSUB213PD	xmmreg, xmmreg, xmmrm128	FMA
VFMADDSUB213PD	ymmreg, ymmreg, ymmrm256	FMA
VFMADDSUB123PS	xmmreg, xmmreg, xmmrm128	FMA
VFMADDSUB123PS	ymmreg, ymmreg, ymmrm256	FMA
VFMADDSUB123PD	xmmreg, xmmreg, xmmrm128	FMA
VFMADDSUB123PD	ymmreg, ymmreg, ymmrm256	FMA
VFMADDSUB231PS	xmmreg, xmmreg, xmmrm128	FMA
VFMADDSUB231PS	ymmreg, ymmreg, ymmrm256	FMA
VFMADDSUB231PD	xmmreg, xmmreg, xmmrm128	FMA
VFMADDSUB231PD	ymmreg, ymmreg, ymmrm256	FMA
VFMADDSUB321PS	xmmreg, xmmreg, xmmrm128	FMA
VFMADDSUB321PS	ymmreg, ymmreg, ymmrm256	FMA
VFMADDSUB321PD	xmmreg, xmmreg, xmmrm128	FMA
VFMADDSUB321PD	ymmreg, ymmreg, ymmrm256	FMA
VFMSUB132PS	xmmreg, xmmreg, xmmrm128	FMA
VFMSUB132PS	ymmreg, ymmreg, ymmrm256	FMA
VFMSUB132PD	xmmreg, xmmreg, xmmrm128	FMA
VFMSUB132PD	ymmreg, ymmreg, ymmrm256	FMA
VFMSUB312PS	xmmreg, xmmreg, xmmrm128	FMA
VFMSUB312PS	ymmreg, ymmreg, ymmrm256	FMA
VFMSUB312PD	xmmreg, xmmreg, xmmrm128	FMA
VFMSUB312PD	ymmreg, ymmreg, ymmrm256	FMA
VFMSUB213PS	xmmreg, xmmreg, xmmrm128	FMA
VFMSUB213PS	ymmreg, ymmreg, ymmrm256	FMA
VFMSUB213PD	xmmreg, xmmreg, xmmrm128	FMA
VFMSUB213PD	ymmreg, ymmreg, ymmrm256	FMA
VFMSUB123PS	xmmreg, xmmreg, xmmrm128	FMA
VFMSUB123PS	ymmreg, ymmreg, ymmrm256	FMA
VFMSUB123PD	xmmreg, xmmreg, xmmrm128	FMA
VFMSUB123PD	ymmreg, ymmreg, ymmrm256	FMA
VFMSUB231PS	xmmreg, xmmreg, xmmrm128	FMA

VFMSUB231PS	ymmreg, ymmreg, ymmrm256	FMA
VFMSUB231PD	xmmreg, xmmreg, xmmrm128	FMA
VFMSUB231PD	ymmreg, ymmreg, ymmrm256	FMA
VFMSUB321PS	xmmreg, xmmreg, xmmrm128	FMA
VFMSUB321PS	ymmreg, ymmreg, ymmrm256	FMA
VFMSUB321PD	xmmreg, xmmreg, xmmrm128	FMA
VFMSUB321PD	ymmreg, ymmreg, ymmrm256	FMA
VFMSUBADD132PS	xmmreg, xmmreg, xmmrm128	FMA
VFMSUBADD132PS	ymmreg, ymmreg, ymmrm256	FMA
VFMSUBADD132PD	xmmreg, xmmreg, xmmrm128	FMA
VFMSUBADD132PD	ymmreg, ymmreg, ymmrm256	FMA
VFMSUBADD312PS	xmmreg, xmmreg, xmmrm128	FMA
VFMSUBADD312PS	ymmreg, ymmreg, ymmrm256	FMA
VFMSUBADD312PD	xmmreg, xmmreg, xmmrm128	FMA
VFMSUBADD312PD	ymmreg, ymmreg, ymmrm256	FMA
VFMSUBADD213PS	xmmreg, xmmreg, xmmrm128	FMA
VFMSUBADD213PS	ymmreg, ymmreg, ymmrm256	FMA
VFMSUBADD213PD	xmmreg, xmmreg, xmmrm128	FMA
VFMSUBADD213PD	ymmreg, ymmreg, ymmrm256	FMA
VFMSUBADD123PS	xmmreg, xmmreg, xmmrm128	FMA
VFMSUBADD123PS	ymmreg, ymmreg, ymmrm256	FMA
VFMSUBADD123PD	xmmreg, xmmreg, xmmrm128	FMA
VFMSUBADD123PD	ymmreg, ymmreg, ymmrm256	FMA
VFMSUBADD231PS	xmmreg, xmmreg, xmmrm128	FMA
VFMSUBADD231PS	ymmreg, ymmreg, ymmrm256	FMA
VFMSUBADD231PD	xmmreg, xmmreg, xmmrm128	FMA
VFMSUBADD231PD	ymmreg, ymmreg, ymmrm256	FMA
VFMSUBADD321PS	xmmreg, xmmreg, xmmrm128	FMA
VFMSUBADD321PS	ymmreg, ymmreg, ymmrm256	FMA
VFMSUBADD321PD	xmmreg, xmmreg, xmmrm128	FMA
VFMSUBADD321PD	ymmreg, ymmreg, ymmrm256	FMA
VFNMADD132PS	xmmreg, xmmreg, xmmrm128	FMA
VFNMADD132PS	ymmreg, ymmreg, ymmrm256	FMA
VFNMADD132PD	xmmreg, xmmreg, xmmrm128	FMA
VFNMADD132PD	ymmreg, ymmreg, ymmrm256	FMA
VFNMADD312PS	xmmreg, xmmreg, xmmrm128	FMA
VFNMADD312PS	ymmreg, ymmreg, ymmrm256	FMA
VFNMADD312PD	xmmreg, xmmreg, xmmrm128	FMA
VFNMADD312PD	ymmreg, ymmreg, ymmrm256	FMA
VFNMADD213PS	xmmreg, xmmreg, xmmrm128	FMA
VFNMADD213PS	ymmreg, ymmreg, ymmrm256	FMA
VFNMADD213PD	xmmreg, xmmreg, xmmrm128	FMA
VFNMADD213PD	ymmreg, ymmreg, ymmrm256	FMA
VFNMADD123PS	xmmreg, xmmreg, xmmrm128	FMA
VFNMADD123PS	ymmreg, ymmreg, ymmrm256	FMA
VFNMADD123PD	xmmreg, xmmreg, xmmrm128	FMA
VFNMADD123PD	ymmreg, ymmreg, ymmrm256	FMA
VFNMADD231PS	xmmreg, xmmreg, xmmrm128	FMA
VFNMADD231PS	ymmreg, ymmreg, ymmrm256	FMA
VFNMADD231PD	xmmreg, xmmreg, xmmrm128	FMA
VFNMADD231PD	ymmreg, ymmreg, ymmrm256	FMA
VFNMADD321PS	xmmreg, xmmreg, xmmrm128	FMA
VFNMADD321PS	ymmreg, ymmreg, ymmrm256	FMA
VFNMADD321PD	xmmreg, xmmreg, xmmrm128	FMA

VFNMADD321PD	ymmreg, ymmreg, ymmrm256	FMA
VFNMSUB132PS	xmmreg, xmmreg, xmmrm128	FMA
VFNMSUB132PS	ymmreg, ymmreg, ymmrm256	FMA
VFNMSUB132PD	xmmreg, xmmreg, xmmrm128	FMA
VFNMSUB132PD	ymmreg, ymmreg, ymmrm256	FMA
VFNMSUB312PS	xmmreg, xmmreg, xmmrm128	FMA
VFNMSUB312PS	ymmreg, ymmreg, ymmrm256	FMA
VFNMSUB312PD	xmmreg, xmmreg, xmmrm128	FMA
VFNMSUB312PD	ymmreg, ymmreg, ymmrm256	FMA
VFNMSUB213PS	xmmreg, xmmreg, xmmrm128	FMA
VFNMSUB213PS	ymmreg, ymmreg, ymmrm256	FMA
VFNMSUB213PD	xmmreg, xmmreg, xmmrm128	FMA
VFNMSUB213PD	ymmreg, ymmreg, ymmrm256	FMA
VFNMSUB123PS	xmmreg, xmmreg, xmmrm128	FMA
VFNMSUB123PS	ymmreg, ymmreg, ymmrm256	FMA
VFNMSUB123PD	xmmreg, xmmreg, xmmrm128	FMA
VFNMSUB123PD	ymmreg, ymmreg, ymmrm256	FMA
VFNMSUB231PS	xmmreg, xmmreg, xmmrm128	FMA
VFNMSUB231PS	ymmreg, ymmreg, ymmrm256	FMA
VFNMSUB231PD	xmmreg, xmmreg, xmmrm128	FMA
VFNMSUB231PD	ymmreg, ymmreg, ymmrm256	FMA
VFNMSUB321PS	xmmreg, xmmreg, xmmrm128	FMA
VFNMSUB321PS	ymmreg, ymmreg, ymmrm256	FMA
VFNMSUB321PD	xmmreg, xmmreg, xmmrm128	FMA
VFNMSUB321PD	ymmreg, ymmreg, ymmrm256	FMA
VFMADD132SS	xmmreg, xmmreg, xmmrm32	FMA
VFMADD132SD	xmmreg, xmmreg, xmmrm64	FMA
VFMADD312SS	xmmreg, xmmreg, xmmrm32	FMA
VFMADD312SD	xmmreg, xmmreg, xmmrm64	FMA
VFMADD213SS	xmmreg, xmmreg, xmmrm32	FMA
VFMADD213SD	xmmreg, xmmreg, xmmrm64	FMA
VFMADD123SS	xmmreg, xmmreg, xmmrm32	FMA
VFMADD123SD	xmmreg, xmmreg, xmmrm64	FMA
VFMADD231SS	xmmreg, xmmreg, xmmrm32	FMA
VFMADD231SD	xmmreg, xmmreg, xmmrm64	FMA
VFMADD321SS	xmmreg, xmmreg, xmmrm32	FMA
VFMADD321SD	xmmreg, xmmreg, xmmrm64	FMA
VFMSUB132SS	xmmreg, xmmreg, xmmrm32	FMA
VFMSUB132SD	xmmreg, xmmreg, xmmrm64	FMA
VFMSUB312SS	xmmreg, xmmreg, xmmrm32	FMA
VFMSUB312SD	xmmreg, xmmreg, xmmrm64	FMA
VFMSUB213SS	xmmreg, xmmreg, xmmrm32	FMA
VFMSUB213SD	xmmreg, xmmreg, xmmrm64	FMA
VFMSUB123SS	xmmreg, xmmreg, xmmrm32	FMA
VFMSUB123SD	xmmreg, xmmreg, xmmrm64	FMA
VFMSUB231SS	xmmreg, xmmreg, xmmrm32	FMA
VFMSUB231SD	xmmreg, xmmreg, xmmrm64	FMA
VFMSUB321SS	xmmreg, xmmreg, xmmrm32	FMA
VFMSUB321SD	xmmreg, xmmreg, xmmrm64	FMA
VFNMADD132SS	xmmreg, xmmreg, xmmrm32	FMA
VFNMADD132SD	xmmreg, xmmreg, xmmrm64	FMA
VFNMADD312SS	xmmreg, xmmreg, xmmrm32	FMA
VFNMADD312SD	xmmreg, xmmreg, xmmrm64	FMA
VFNMADD213SS	xmmreg, xmmreg, xmmrm32	FMA

VFNMADD213SD	xmmreg, xmmreg, xmmrmm64	FMA
VFNMADD123SS	xmmreg, xmmreg, xmmrmm32	FMA
VFNMADD123SD	xmmreg, xmmreg, xmmrmm64	FMA
VFNMADD231SS	xmmreg, xmmreg, xmmrmm32	FMA
VFNMADD231SD	xmmreg, xmmreg, xmmrmm64	FMA
VFNMADD321SS	xmmreg, xmmreg, xmmrmm32	FMA
VFNMADD321SD	xmmreg, xmmreg, xmmrmm64	FMA
VFNMSUB132SS	xmmreg, xmmreg, xmmrmm32	FMA
VFNMSUB132SD	xmmreg, xmmreg, xmmrmm64	FMA
VFNMSUB312SS	xmmreg, xmmreg, xmmrmm32	FMA
VFNMSUB312SD	xmmreg, xmmreg, xmmrmm64	FMA
VFNMSUB213SS	xmmreg, xmmreg, xmmrmm32	FMA
VFNMSUB213SD	xmmreg, xmmreg, xmmrmm64	FMA
VFNMSUB123SS	xmmreg, xmmreg, xmmrmm32	FMA
VFNMSUB123SD	xmmreg, xmmreg, xmmrmm64	FMA
VFNMSUB231SS	xmmreg, xmmreg, xmmrmm32	FMA
VFNMSUB231SD	xmmreg, xmmreg, xmmrmm64	FMA
VFNMSUB321SS	xmmreg, xmmreg, xmmrmm32	FMA
VFNMSUB321SD	xmmreg, xmmreg, xmmrmm64	FMA

B.1.30 Intel post-32 nm processor instructions

RDFSBASE	reg32	LONG
RDFSBASE	reg64	LONG
RDGSBASE	reg32	LONG
RDGSBASE	reg64	LONG
RDRAND	reg16	
RDRAND	reg32	
RDRAND	reg64	LONG
WRFSBASE	reg32	LONG
WRFSBASE	reg64	LONG
WRGSBASE	reg32	LONG
WRGSBASE	reg64	LONG
VCVTPH2PS	ymmreg, xmmrmm128	AVX
VCVTPH2PS	xmmreg, xmmrmm64	AVX
VCVTPS2PH	xmmrmm128, ymmreg, imm8	AVX
VCVTPS2PH	xmmrmm64, xmmreg, imm8	AVX
ADCX	reg32, rmm32	
ADCX	reg64, rmm64	LONG
ADOX	reg32, rmm32	
ADOX	reg64, rmm64	LONG
RDSEED	reg16	
RDSEED	reg32	
RDSEED	reg64	LONG
CLAC		PRIV
STAC		PRIV

B.1.31 VIA (Centaur) security instructions

XSTORE	PENT, CYRIX
XCRYPTECB	PENT, CYRIX
XCRYPTCBC	PENT, CYRIX
XCRYPTCTR	PENT, CYRIX
XCRYPTCFB	PENT, CYRIX
XCRYPTOFB	PENT, CYRIX

MONTMUL	PENT, CYRIX
XSHA1	PENT, CYRIX
XSHA256	PENT, CYRIX

B.1.32 AMD Lightweight Profiling (LWP) instructions

LLWPCB	reg32	AMD, 386
LLWPCB	reg64	AMD, X64
SLWPCB	reg32	AMD, 386
SLWPCB	reg64	AMD, X64
LWPVAL	reg32, rm32, imm32	AMD, 386
LWPVAL	reg64, rm32, imm32	AMD, X64
LWPINS	reg32, rm32, imm32	AMD, 386
LWPINS	reg64, rm32, imm32	AMD, X64

B.1.33 AMD XOP and FMA4 instructions (SSE5)

VFMADDPD	xmmreg, xmmreg*, xmmrm128, xmmreg	AMD, SSE5
VFMADDPD	ymmreg, ymmreg*, ymmrm256, ymmreg	AMD, SSE5
VFMADDPD	xmmreg, xmmreg*, xmmreg, xmmrm128	AMD, SSE5
VFMADDPD	ymmreg, ymmreg*, ymmreg, ymmrm256	AMD, SSE5
VFMADDPS	xmmreg, xmmreg*, xmmrm128, xmmreg	AMD, SSE5
VFMADDPS	ymmreg, ymmreg*, ymmrm256, ymmreg	AMD, SSE5
VFMADDPS	xmmreg, xmmreg*, xmmreg, xmmrm128	AMD, SSE5
VFMADDPS	ymmreg, ymmreg*, ymmreg, ymmrm256	AMD, SSE5
VFMADDSD	xmmreg, xmmreg*, xmmrm64, xmmreg	AMD, SSE5
VFMADDSD	xmmreg, xmmreg*, xmmreg, xmmrm64	AMD, SSE5
VFMADDSS	xmmreg, xmmreg*, xmmrm32, xmmreg	AMD, SSE5
VFMADDSS	xmmreg, xmmreg*, xmmreg, xmmrm32	AMD, SSE5
VFMADDSUBPD	xmmreg, xmmreg*, xmmrm128, xmmreg	AMD, SSE5
VFMADDSUBPD	ymmreg, ymmreg*, ymmrm256, ymmreg	AMD, SSE5
VFMADDSUBPD	xmmreg, xmmreg*, xmmreg, xmmrm128	AMD, SSE5
VFMADDSUBPD	ymmreg, ymmreg*, ymmreg, ymmrm256	AMD, SSE5
VFMADDSUBPS	xmmreg, xmmreg*, xmmrm128, xmmreg	AMD, SSE5
VFMADDSUBPS	ymmreg, ymmreg*, ymmrm256, ymmreg	AMD, SSE5
VFMADDSUBPS	xmmreg, xmmreg*, xmmreg, xmmrm128	AMD, SSE5
VFMADDSUBPS	ymmreg, ymmreg*, ymmreg, ymmrm256	AMD, SSE5
VFMSUBADDPD	xmmreg, xmmreg*, xmmrm128, xmmreg	AMD, SSE5
VFMSUBADDPD	ymmreg, ymmreg*, ymmrm256, ymmreg	AMD, SSE5
VFMSUBADDPD	xmmreg, xmmreg*, xmmreg, xmmrm128	AMD, SSE5
VFMSUBADDPD	ymmreg, ymmreg*, ymmreg, ymmrm256	AMD, SSE5
VFMSUBADDPS	xmmreg, xmmreg*, xmmrm128, xmmreg	AMD, SSE5
VFMSUBADDPS	ymmreg, ymmreg*, ymmrm256, ymmreg	AMD, SSE5
VFMSUBADDPS	xmmreg, xmmreg*, xmmreg, xmmrm128	AMD, SSE5
VFMSUBADDPS	ymmreg, ymmreg*, ymmreg, ymmrm256	AMD, SSE5
VFMSUBPD	xmmreg, xmmreg*, xmmrm128, xmmreg	AMD, SSE5
VFMSUBPD	ymmreg, ymmreg*, ymmrm256, ymmreg	AMD, SSE5
VFMSUBPD	xmmreg, xmmreg*, xmmreg, xmmrm128	AMD, SSE5
VFMSUBPD	ymmreg, ymmreg*, ymmreg, ymmrm256	AMD, SSE5
VFMSUBPS	xmmreg, xmmreg*, xmmrm128, xmmreg	AMD, SSE5
VFMSUBPS	ymmreg, ymmreg*, ymmrm256, ymmreg	AMD, SSE5
VFMSUBPS	xmmreg, xmmreg*, xmmreg, xmmrm128	AMD, SSE5
VFMSUBPS	ymmreg, ymmreg*, ymmreg, ymmrm256	AMD, SSE5
VFMSUBSD	xmmreg, xmmreg*, xmmrm64, xmmreg	AMD, SSE5
VFMSUBSD	xmmreg, xmmreg*, xmmreg, xmmrm64	AMD, SSE5

VFMSSUBSS	xmmreg,xmmreg*,xmmrm32,xmmreg AMD,SSE5
VFMSUBSS	xmmreg,xmmreg*,xmmreg,xmmrm32 AMD,SSE5
VFNMADDPD	xmmreg,xmmreg*,xmmrm128,xmmreg AMD,SSE5
VFNMADDPD	yymmreg,yymmreg*,yymrm256,yymmreg AMD,SSE5
VFNMADDPD	xmmreg,xmmreg*,xmmreg,xmmrm128 AMD,SSE5
VFNMADDPD	yymmreg,yymmreg*,yymmreg,yymrm256 AMD,SSE5
VFNMADDPS	xmmreg,xmmreg*,xmmrm128,xmmreg AMD,SSE5
VFNMADDPS	yymmreg,yymmreg*,yymrm256,yymmreg AMD,SSE5
VFNMADDPS	xmmreg,xmmreg*,xmmreg,xmmrm128 AMD,SSE5
VFNMADDPS	yymmreg,yymmreg*,yymmreg,yymrm256 AMD,SSE5
VFNMADDSD	xmmreg,xmmreg*,xmmrm64,xmmreg AMD,SSE5
VFNMADDSD	xmmreg,xmmreg*,xmmreg,xmmrm64 AMD,SSE5
VFNMADDSS	xmmreg,xmmreg*,xmmrm32,xmmreg AMD,SSE5
VFNMADDSS	xmmreg,xmmreg*,xmmreg,xmmrm32 AMD,SSE5
VFNMSUBPD	xmmreg,xmmreg*,xmmrm128,xmmreg AMD,SSE5
VFNMSUBPD	yymmreg,yymmreg*,yymrm256,yymmreg AMD,SSE5
VFNMSUBPD	xmmreg,xmmreg*,xmmreg,xmmrm128 AMD,SSE5
VFNMSUBPD	yymmreg,yymmreg*,yymmreg,yymrm256 AMD,SSE5
VFNMSUBPS	xmmreg,xmmreg*,xmmrm128,xmmreg AMD,SSE5
VFNMSUBPS	yymmreg,yymmreg*,yymrm256,yymmreg AMD,SSE5
VFNMSUBPS	xmmreg,xmmreg*,xmmreg,xmmrm128 AMD,SSE5
VFNMSUBPS	yymmreg,yymmreg*,yymmreg,yymrm256 AMD,SSE5
VFNMSUBSD	xmmreg,xmmreg*,xmmrm64,xmmreg AMD,SSE5
VFNMSUBSD	xmmreg,xmmreg*,xmmreg,xmmrm64 AMD,SSE5
VFNMSUBSS	xmmreg,xmmreg*,xmmrm32,xmmreg AMD,SSE5
VFNMSUBSS	xmmreg,xmmreg*,xmmreg,xmmrm32 AMD,SSE5
VFRCZPD	xmmreg,xmmrm128*AMD,SSE5
VFRCZPD	yymmreg,yymrm256*AMD,SSE5
VFRCZPS	xmmreg,xmmrm128*AMD,SSE5
VFRCZPS	yymmreg,yymrm256*AMD,SSE5
VFRCZSD	xmmreg,xmmrm64*AMD,SSE5
VFRCZSS	xmmreg,xmmrm32*AMD,SSE5
VPCMOV	xmmreg,xmmreg*,xmmrm128,xmmreg AMD,SSE5
VPCMOV	yymmreg,yymmreg*,yymrm256,yymmreg AMD,SSE5
VPCMOV	xmmreg,xmmreg*,xmmreg,xmmrm128 AMD,SSE5
VPCMOV	yymmreg,yymmreg*,yymmreg,yymrm256 AMD,SSE5
VPCOMB	xmmreg,xmmreg*,xmmrm128,imm8 AMD,SSE5
VPCOMD	xmmreg,xmmreg*,xmmrm128,imm8 AMD,SSE5
VPCOMQ	xmmreg,xmmreg*,xmmrm128,imm8 AMD,SSE5
VPCOMUB	xmmreg,xmmreg*,xmmrm128,imm8 AMD,SSE5
VPCOMUD	xmmreg,xmmreg*,xmmrm128,imm8 AMD,SSE5
VPCOMUQ	xmmreg,xmmreg*,xmmrm128,imm8 AMD,SSE5
VPCOMUW	xmmreg,xmmreg*,xmmrm128,imm8 AMD,SSE5
VPCOMW	xmmreg,xmmreg*,xmmrm128,imm8 AMD,SSE5
VPHADDBD	xmmreg,xmmrm128*AMD,SSE5
VPHADDBQ	xmmreg,xmmrm128*AMD,SSE5
VPHADDBW	xmmreg,xmmrm128*AMD,SSE5
VPHADDQ	xmmreg,xmmrm128*AMD,SSE5
VPHADDUBD	xmmreg,xmmrm128*AMD,SSE5
VPHADDUBQ	xmmreg,xmmrm128*AMD,SSE5
VPHADDUBW	xmmreg,xmmrm128*AMD,SSE5
VPHADDUDQ	xmmreg,xmmrm128*AMD,SSE5
VPHADDUWD	xmmreg,xmmrm128*AMD,SSE5
VPHADDUWQ	xmmreg,xmmrm128*AMD,SSE5

VPHADDWD	xmmreg, xmmrm128*	AMD, SSE5
VPHADDWQ	xmmreg, xmmrm128*	AMD, SSE5
VPHSUBBW	xmmreg, xmmrm128*	AMD, SSE5
VPHSUBDQ	xmmreg, xmmrm128*	AMD, SSE5
VPHSUBWD	xmmreg, xmmrm128*	AMD, SSE5
VPMACSDDD	xmmreg, xmmreg*, xmmrm128, xmmreg	AMD, SSE5
VPMACSDQH	xmmreg, xmmreg*, xmmrm128, xmmreg	AMD, SSE5
VPMACSDQL	xmmreg, xmmreg*, xmmrm128, xmmreg	AMD, SSE5
VPMACSSDD	xmmreg, xmmreg*, xmmrm128, xmmreg	AMD, SSE5
VPMACSSDQH	xmmreg, xmmreg*, xmmrm128, xmmreg	AMD, SSE5
VPMACSSDQL	xmmreg, xmmreg*, xmmrm128, xmmreg	AMD, SSE5
VPMACSSWD	xmmreg, xmmreg*, xmmrm128, xmmreg	AMD, SSE5
VPMACSSWW	xmmreg, xmmreg*, xmmrm128, xmmreg	AMD, SSE5
VPMACSWD	xmmreg, xmmreg*, xmmrm128, xmmreg	AMD, SSE5
VPMACSWW	xmmreg, xmmreg*, xmmrm128, xmmreg	AMD, SSE5
VPMADCSSWD	xmmreg, xmmreg*, xmmrm128, xmmreg	AMD, SSE5
VPMADCSWD	xmmreg, xmmreg*, xmmrm128, xmmreg	AMD, SSE5
VPPERM	xmmreg, xmmreg*, xmmreg, xmmrm128	AMD, SSE5
VPPERM	xmmreg, xmmreg*, xmmrm128, xmmreg	AMD, SSE5
VPROTB	xmmreg, xmmrm128*, xmmreg	AMD, SSE5
VPROTB	xmmreg, xmmreg*, xmmrm128	AMD, SSE5
VPROTB	xmmreg, xmmrm128*, imm8	AMD, SSE5
VPROTD	xmmreg, xmmrm128*, xmmreg	AMD, SSE5
VPROTD	xmmreg, xmmreg*, xmmrm128	AMD, SSE5
VPROTD	xmmreg, xmmrm128*, imm8	AMD, SSE5
VPROTQ	xmmreg, xmmrm128*, xmmreg	AMD, SSE5
VPROTQ	xmmreg, xmmreg*, xmmrm128	AMD, SSE5
VPROTQ	xmmreg, xmmrm128*, imm8	AMD, SSE5
VPROTW	xmmreg, xmmrm128*, xmmreg	AMD, SSE5
VPROTW	xmmreg, xmmreg*, xmmrm128	AMD, SSE5
VPROTW	xmmreg, xmmrm128*, imm8	AMD, SSE5
VPSHAB	xmmreg, xmmrm128*, xmmreg	AMD, SSE5
VPSHAB	xmmreg, xmmreg*, xmmrm128	AMD, SSE5
VPSHAD	xmmreg, xmmrm128*, xmmreg	AMD, SSE5
VPSHAD	xmmreg, xmmreg*, xmmrm128	AMD, SSE5
VPSHAQ	xmmreg, xmmrm128*, xmmreg	AMD, SSE5
VPSHAQ	xmmreg, xmmreg*, xmmrm128	AMD, SSE5
VPSHAW	xmmreg, xmmrm128*, xmmreg	AMD, SSE5
VPSHAW	xmmreg, xmmreg*, xmmrm128	AMD, SSE5
VPSHLB	xmmreg, xmmrm128*, xmmreg	AMD, SSE5
VPSHLB	xmmreg, xmmreg*, xmmrm128	AMD, SSE5
VPSHLD	xmmreg, xmmrm128*, xmmreg	AMD, SSE5
VPSHLD	xmmreg, xmmreg*, xmmrm128	AMD, SSE5
VPSHLQ	xmmreg, xmmrm128*, xmmreg	AMD, SSE5
VPSHLQ	xmmreg, xmmreg*, xmmrm128	AMD, SSE5
VPSHLW	xmmreg, xmmrm128*, xmmreg	AMD, SSE5
VPSHLW	xmmreg, xmmreg*, xmmrm128	AMD, SSE5

B.1.34 Intel AVX2 instructions

VMPSADBW	ymmreg, ymmreg*, ymmrm256, imm8	AVX2
VPABSB	ymmreg, ymmrm256	AVX2
VPABSW	ymmreg, ymmrm256	AVX2
VPABSD	ymmreg, ymmrm256	AVX2

VPACKSSWB	ymmreg, ymmreg*, ymmrm256	AVX2
VPACKSSDW	ymmreg, ymmreg*, ymmrm256	AVX2
VPACKUSDW	ymmreg, ymmreg*, ymmrm256	AVX2
VPACKUSWB	ymmreg, ymmreg*, ymmrm256	AVX2
VPADDB	ymmreg, ymmreg*, ymmrm256	AVX2
VPADDW	ymmreg, ymmreg*, ymmrm256	AVX2
VPADDD	ymmreg, ymmreg*, ymmrm256	AVX2
VPADDQ	ymmreg, ymmreg*, ymmrm256	AVX2
VPADDSB	ymmreg, ymmreg*, ymmrm256	AVX2
VPADDSW	ymmreg, ymmreg*, ymmrm256	AVX2
VPADDUSB	ymmreg, ymmreg*, ymmrm256	AVX2
VPADDUSW	ymmreg, ymmreg*, ymmrm256	AVX2
VPALIGNR	ymmreg, ymmreg*, ymmrm256, imm8	AVX2
VPAND	ymmreg, ymmreg*, ymmrm256	AVX2
VPANDN	ymmreg, ymmreg*, ymmrm256	AVX2
VPAVGB	ymmreg, ymmreg*, ymmrm256	AVX2
VPAVGW	ymmreg, ymmreg*, ymmrm256	AVX2
VPBLENDVB	ymmreg, ymmreg*, ymmrm256, ymmreg	AVX2
VPBLENDW	ymmreg, ymmreg*, ymmrm256, imm8	AVX2
VPCMPQB	ymmreg, ymmreg*, ymmrm256	AVX2
VPCMPQW	ymmreg, ymmreg*, ymmrm256	AVX2
VPCMPQD	ymmreg, ymmreg*, ymmrm256	AVX2
VPCMPQQ	ymmreg, ymmreg*, ymmrm256	AVX2
VPCMPGTB	ymmreg, ymmreg*, ymmrm256	AVX2
VPCMPGTW	ymmreg, ymmreg*, ymmrm256	AVX2
VPCMPGTD	ymmreg, ymmreg*, ymmrm256	AVX2
VPCMPGTQ	ymmreg, ymmreg*, ymmrm256	AVX2
VPHADDW	ymmreg, ymmreg*, ymmrm256	AVX2
VPHADDD	ymmreg, ymmreg*, ymmrm256	AVX2
VPHADDSW	ymmreg, ymmreg*, ymmrm256	AVX2
VPHSUBW	ymmreg, ymmreg*, ymmrm256	AVX2
VPHSUBD	ymmreg, ymmreg*, ymmrm256	AVX2
VPHSUBSW	ymmreg, ymmreg*, ymmrm256	AVX2
VPMADDUSBW	ymmreg, ymmreg*, ymmrm256	AVX2
VPMADDWD	ymmreg, ymmreg*, ymmrm256	AVX2
VPMASB	ymmreg, ymmreg*, ymmrm256	AVX2
VPMASW	ymmreg, ymmreg*, ymmrm256	AVX2
VPMASD	ymmreg, ymmreg*, ymmrm256	AVX2
VPMASUB	ymmreg, ymmreg*, ymmrm256	AVX2
VPMASUW	ymmreg, ymmreg*, ymmrm256	AVX2
VPMASUD	ymmreg, ymmreg*, ymmrm256	AVX2
VPMINSB	ymmreg, ymmreg*, ymmrm256	AVX2
VPMINSW	ymmreg, ymmreg*, ymmrm256	AVX2
VPMIND	ymmreg, ymmreg*, ymmrm256	AVX2
VPMINUB	ymmreg, ymmreg*, ymmrm256	AVX2
VPMINUW	ymmreg, ymmreg*, ymmrm256	AVX2
VPMINUD	ymmreg, ymmreg*, ymmrm256	AVX2
VPMOVMASKB	reg32, ymmreg	AVX2
VPMOVMASKB	reg64, ymmreg	AVX2
VPMOVSXWB	ymmreg, xmmrm128	AVX2
VPMOVSXBD	ymmreg, mem64	AVX2
VPMOVSXBD	ymmreg, xmmreg	AVX2
VPMOVSXBQ	ymmreg, mem32	AVX2
VPMOVSXBQ	ymmreg, xmmreg	AVX2

VPMOVSXWD	ymmreg, xmmrm128	AVX2
VPMOVSXWQ	ymmreg, mem64	AVX2
VPMOVSXWQ	ymmreg, xmmreg	AVX2
VPMOVXSDQ	ymmreg, xmmrm128	AVX2
VPMOVZXBW	ymmreg, xmmrm128	AVX2
VPMOVZXBQ	ymmreg, mem64	AVX2
VPMOVZXBQ	ymmreg, xmmreg	AVX2
VPMOVZXBQ	ymmreg, mem32	AVX2
VPMOVZXBQ	ymmreg, xmmreg	AVX2
VPMOVZXWD	ymmreg, xmmrm128	AVX2
VPMOVZXWQ	ymmreg, mem64	AVX2
VPMOVZXWQ	ymmreg, xmmreg	AVX2
VPMOVZXDQ	ymmreg, xmmrm128	AVX2
VPMULDQ	ymmreg, ymmreg*, ymmrm256	AVX2
VPMULHSW	ymmreg, ymmreg*, ymmrm256	AVX2
VPMULHUW	ymmreg, ymmreg*, ymmrm256	AVX2
VPMULHW	ymmreg, ymmreg*, ymmrm256	AVX2
VPMULLW	ymmreg, ymmreg*, ymmrm256	AVX2
VPMULLD	ymmreg, ymmreg*, ymmrm256	AVX2
VPMULUDQ	ymmreg, ymmreg*, ymmrm256	AVX2
VPOR	ymmreg, ymmreg*, ymmrm256	AVX2
VPSADBQ	ymmreg, ymmreg*, ymmrm256	AVX2
VPSHUFQ	ymmreg, ymmreg*, ymmrm256	AVX2
VPSHUFQ	ymmreg, ymmrm256, imm8	AVX2
VPSHUFHW	ymmreg, ymmrm256, imm8	AVX2
VPSHUFHW	ymmreg, ymmrm256, imm8	AVX2
VPSIGNB	ymmreg, ymmreg*, ymmrm256	AVX2
VPSIGNW	ymmreg, ymmreg*, ymmrm256	AVX2
VPSIGND	ymmreg, ymmreg*, ymmrm256	AVX2
VPSLLDQ	ymmreg, ymmreg*, imm8	AVX2
VPSLLW	ymmreg, ymmreg*, xmmrm128	AVX2
VPSLLW	ymmreg, ymmreg*, imm8	AVX2
VPSLLD	ymmreg, ymmreg*, xmmrm128	AVX2
VPSLLD	ymmreg, ymmreg*, imm8	AVX2
VPSLLQ	ymmreg, ymmreg*, xmmrm128	AVX2
VPSLLQ	ymmreg, ymmreg*, imm8	AVX2
VPSRAW	ymmreg, ymmreg*, xmmrm128	AVX2
VPSRAW	ymmreg, ymmreg*, imm8	AVX2
VPSRAD	ymmreg, ymmreg*, xmmrm128	AVX2
VPSRAD	ymmreg, ymmreg*, imm8	AVX2
VPSRLDQ	ymmreg, ymmreg*, imm8	AVX2
VPSRLW	ymmreg, ymmreg*, xmmrm128	AVX2
VPSRLW	ymmreg, ymmreg*, imm8	AVX2
VPSRLD	ymmreg, ymmreg*, xmmrm128	AVX2
VPSRLD	ymmreg, ymmreg*, imm8	AVX2
VPSRLQ	ymmreg, ymmreg*, xmmrm128	AVX2
VPSRLQ	ymmreg, ymmreg*, imm8	AVX2
VPSUBB	ymmreg, ymmreg*, ymmrm256	AVX2
VPSUBW	ymmreg, ymmreg*, ymmrm256	AVX2
VPSUBD	ymmreg, ymmreg*, ymmrm256	AVX2
VPSUBQ	ymmreg, ymmreg*, ymmrm256	AVX2
VPSUBSB	ymmreg, ymmreg*, ymmrm256	AVX2
VPSUBSW	ymmreg, ymmreg*, ymmrm256	AVX2
VPSUBUSB	ymmreg, ymmreg*, ymmrm256	AVX2

VPSUBUSW	ymmreg, ymmreg*, ymmrm256	AVX2
VPUNPCKHBW	ymmreg, ymmreg*, ymmrm256	AVX2
VPUNPCKHWD	ymmreg, ymmreg*, ymmrm256	AVX2
VPUNPCKHDQ	ymmreg, ymmreg*, ymmrm256	AVX2
VPUNPCKHQDQ	ymmreg, ymmreg*, ymmrm256	AVX2
VPUNPCKLBW	ymmreg, ymmreg*, ymmrm256	AVX2
VPUNPCKLWD	ymmreg, ymmreg*, ymmrm256	AVX2
VPUNPCKLDQ	ymmreg, ymmreg*, ymmrm256	AVX2
VPUNPCKLQDQ	ymmreg, ymmreg*, ymmrm256	AVX2
VPXOR	ymmreg, ymmreg*, ymmrm256	AVX2
VMOVNTDQA	ymmreg, mem256	AVX2
VBROADCASTSS	xmmreg, xmmreg	AVX2
VBROADCASTSS	ymmreg, xmmreg	AVX2
VBROADCASTSD	ymmreg, xmmreg	AVX2
VBROADCASTI128	ymmreg, mem128	AVX2
VPBLENDQ	xmmreg, xmmreg*, xmmrm128, imm8	AVX2
VPBLENDQ	ymmreg, ymmreg*, ymmrm256, imm8	AVX2
VPBROADCASTB	xmmreg, mem8	AVX2
VPBROADCASTB	xmmreg, xmmreg	AVX2
VPBROADCASTB	ymmreg, mem8	AVX2
VPBROADCASTB	ymmreg, xmmreg	AVX2
VPBROADCASTW	xmmreg, mem16	AVX2
VPBROADCASTW	xmmreg, xmmreg	AVX2
VPBROADCASTW	ymmreg, mem16	AVX2
VPBROADCASTW	ymmreg, xmmreg	AVX2
VPBROADCASTD	xmmreg, mem32	AVX2
VPBROADCASTD	xmmreg, xmmreg	AVX2
VPBROADCASTD	ymmreg, mem32	AVX2
VPBROADCASTD	ymmreg, xmmreg	AVX2
VPBROADCASTQ	xmmreg, mem64	AVX2
VPBROADCASTQ	xmmreg, xmmreg	AVX2
VPBROADCASTQ	ymmreg, mem64	AVX2
VPBROADCASTQ	ymmreg, xmmreg	AVX2
PPERMD	ymmreg, ymmreg*, ymmrm256	AVX2
PPERMPD	ymmreg, ymmrm256, imm8	AVX2
PPERMPS	ymmreg, ymmreg*, ymmrm256	AVX2
PPERMQ	ymmreg, ymmrm256, imm8	AVX2
PPERM2I128	ymmreg, ymmreg*, ymmrm256, imm8	AVX2
VEEXTRACTI128	xmmrm128, ymmreg, imm8	AVX2
VINSERTI128	ymmreg, ymmreg*, xmmrm128, imm8	AVX2
VPMASKMOVD	xmmreg, xmmreg*, mem128	AVX2
VPMASKMOVD	ymmreg, ymmreg*, mem256	AVX2
VPMASKMOVQ	xmmreg, xmmreg*, mem128	AVX2
VPMASKMOVQ	ymmreg, ymmreg*, mem256	AVX2
VPMASKMOVD	mem128, xmmreg*, xmmreg	AVX2
VPMASKMOVD	mem256, ymmreg*, ymmreg	AVX2
VPMASKMOVQ	mem128, xmmreg*, xmmreg	AVX2
VPMASKMOVQ	mem256, ymmreg*, ymmreg	AVX2
VPSLLVD	xmmreg, xmmreg*, xmmrm128	AVX2
VPSLLVQ	xmmreg, xmmreg*, xmmrm128	AVX2
VPSLLVD	ymmreg, ymmreg*, ymmrm256	AVX2
VPSLLVQ	ymmreg, ymmreg*, ymmrm256	AVX2
VPSRAVD	xmmreg, xmmreg*, xmmrm128	AVX2
VPSRAVD	ymmreg, ymmreg*, ymmrm256	AVX2

VPSRLVD	xmmreg, xmmreg*, xmmrm128	AVX2
VPSRLVQ	xmmreg, xmmreg*, xmmrm128	AVX2
VPSRLVD	ymmreg, ymmreg*, ymmrm256	AVX2
VPSRLVQ	ymmreg, ymmreg*, ymmrm256	AVX2
VGATHERDPD	xmmreg, xmem64, xmmreg	AVX2
VGATHERQPD	xmmreg, xmem64, xmmreg	AVX2
VGATHERDPD	ymmreg, xmem64, ymmreg	AVX2
VGATHERQPD	ymmreg, ymem64, ymmreg	AVX2
VGATHERDPS	xmmreg, xmem32, xmmreg	AVX2
VGATHERQPS	xmmreg, xmem32, xmmreg	AVX2
VGATHERDPS	ymmreg, ymem32, ymmreg	AVX2
VGATHERQPS	xmmreg, ymem32, xmmreg	AVX2
VPGATHERDD	xmmreg, xmem32, xmmreg	AVX2
VPGATHERQD	xmmreg, xmem32, xmmreg	AVX2
VPGATHERDD	ymmreg, ymem32, ymmreg	AVX2
VPGATHERQD	xmmreg, ymem32, xmmreg	AVX2
VPGATHERDQ	xmmreg, xmem64, xmmreg	AVX2
VPGATHERQQ	xmmreg, xmem64, xmmreg	AVX2
VPGATHERDQ	ymmreg, xmem64, ymmreg	AVX2
VPGATHERQQ	ymmreg, ymem64, ymmreg	AVX2

B.1.35 Intel Transactional Synchronization Extensions (TSX)

XABORT	imm	RTM
XABORT	imm8	RTM
XBEGIN	imm	RTM
XBEGIN	imm near	RTM, ND
XBEGIN	imm16	RTM, NOLONG
XBEGIN	imm16 near	RTM, NOLONG, ND
XBEGIN	imm32	RTM, NOLONG
XBEGIN	imm32 near	RTM, NOLONG, ND
XBEGIN	imm64	RTM, LONG
XBEGIN	imm64 near	RTM, LONG, ND
XEND		RTM
XTEST		HLE, RTM

B.1.36 Intel BMI1 and BMI2 instructions, AMD TBM instructions

ANDN	reg32, reg32, rm32	BMI1
ANDN	reg64, reg64, rm64	LONG, BMI1
BEXTR	reg32, rm32, reg32	BMI1
BEXTR	reg64, rm64, reg64	LONG, BMI1
BEXTR	reg32, rm32, imm32	TBM
BEXTR	reg64, rm64, imm32	LONG, TBM
BLCI	reg32, rm32	TBM
BLCI	reg64, rm64	LONG, TBM
BLCIC	reg32, rm32	TBM
BLCIC	reg64, rm64	LONG, TBM
BLSI	reg32, rm32	BMI1
BLSI	reg64, rm64	LONG, BMI1
BLSIC	reg32, rm32	TBM
BLSIC	reg64, rm64	LONG, TBM
BLCFILL	reg32, rm32	TBM
BLCFILL	reg64, rm64	LONG, TBM
BLSFILL	reg32, rm32	TBM

BLSFILL	reg64, rm64	LONG, TBM
BLCMSK	reg32, rm32	TBM
BLCMSK	reg64, rm64	LONG, TBM
BLSMSK	reg32, rm32	BMI1
BLSMSK	reg64, rm64	LONG, BMI1
BLSR	reg32, rm32	BMI1
BLSR	reg64, rm64	LONG, BMI1
BLCS	reg32, rm32	TBM
BLCS	reg64, rm64	LONG, TBM
BZHI	reg32, rm32, reg32	BMI2
BZHI	reg64, rm64, reg64	LONG, BMI2
MULX	reg32, reg32, rm32	BMI2
MULX	reg64, reg64, rm64	LONG, BMI2
PDEP	reg32, reg32, rm32	BMI2
PDEP	reg64, reg64, rm64	LONG, BMI2
PEXT	reg32, reg32, rm32	BMI2
PEXT	reg64, reg64, rm64	LONG, BMI2
RORX	reg32, rm32, imm8	BMI2
RORX	reg64, rm64, imm8	LONG, BMI2
SARX	reg32, rm32, reg32	BMI2
SARX	reg64, rm64, reg64	LONG, BMI2
SHLX	reg32, rm32, reg32	BMI2
SHLX	reg64, rm64, reg64	LONG, BMI2
SHRX	reg32, rm32, reg32	BMI2
SHRX	reg64, rm64, reg64	LONG, BMI2
TZCNT	reg16, rm16	BMI1
TZCNT	reg32, rm32	BMI1
TZCNT	reg64, rm64	LONG, BMI1
TZMSK	reg32, rm32	TBM
TZMSK	reg64, rm64	LONG, TBM
T1MSKC	reg32, rm32	TBM
T1MSKC	reg64, rm64	LONG, TBM
PREFETCHWT1	mem8	PREFETCHWT1

B.1.37 Intel Memory Protection Extensions (MPX)

BNDMK	bndreg, mem	MPX, MIB
BNDCL	bndreg, mem	MPX
BNDCL	bndreg, reg32	MPX, NO LONG
BNDCL	bndreg, reg64	MPX, LONG
BNDU	bndreg, mem	MPX
BNDU	bndreg, reg32	MPX, NO LONG
BNDU	bndreg, reg64	MPX, LONG
BNDN	bndreg, mem	MPX
BNDN	bndreg, reg32	MPX, NO LONG
BNDN	bndreg, reg64	MPX, LONG
BNDMOV	bndreg, bndreg	MPX
BNDMOV	bndreg, mem	MPX
BNDMOV	bndreg, bndreg	MPX
BNDMOV	mem, bndreg	MPX
BNDLDX	bndreg, mem	MPX, MIB
BNDLDX	bndreg, mem, reg32	MPX, MIB, NO LONG
BNDLDX	bndreg, mem, reg64	MPX, MIB, LONG
BNDSTX	mem, bndreg	MPX, MIB

BNDSTX	mem, reg32, bndreg	MPX, MIB, NOLONG
BNDSTX	mem, reg64, bndreg	MPX, MIB, LONG
BNDSTX	mem, bndreg, reg32	MPX, MIB, NOLONG
BNDSTX	mem, bndreg, reg64	MPX, MIB, LONG

B.1.38 Intel SHA acceleration instructions

SHA1MSG1	xmmreg, xmmrml28	SHA
SHA1MSG2	xmmreg, xmmrml28	SHA
SHA1NEXTE	xmmreg, xmmrml28	SHA
SHA1RND\$4	xmmreg, xmmrml28, imm8	SHA
SHA256MSG1	xmmreg, xmmrml28	SHA
SHA256MSG2	xmmreg, xmmrml28	SHA
SHA256RND\$2	xmmreg, xmmrml28, xmm0	SHA
SHA256RND\$2	xmmreg, xmmrml28	SHA

B.1.39 AVX–512 mask register instructions

KADDB	kreg, kreg, kreg
KADDD	kreg, kreg, kreg
KADDQ	kreg, kreg, kreg
KADDW	kreg, kreg, kreg
KANDB	kreg, kreg, kreg
KANDD	kreg, kreg, kreg
KANDNB	kreg, kreg, kreg
KANDND	kreg, kreg, kreg
KANDNQ	kreg, kreg, kreg
KANDNW	kreg, kreg, kreg
KANDQ	kreg, kreg, kreg
KANDW	kreg, kreg, kreg
KMOVB	kreg, krm8
KMOVB	mem8, kreg
KMOVB	kreg, reg32
KMOVB	reg32, kreg
KMOVD	kreg, krm32
KMOVD	mem32, kreg
KMOVD	kreg, reg32
KMOVD	reg32, kreg
KMOVQ	kreg, krm64
KMOVQ	mem64, kreg
KMOVQ	kreg, reg64
KMOVQ	reg64, kreg
KMOVW	kreg, krm16
KMOVW	mem16, kreg
KMOVW	kreg, reg32
KMOVW	reg32, kreg
KNOTB	kreg, kreg
KNOTD	kreg, kreg
KNOTQ	kreg, kreg
KNOTW	kreg, kreg
KORB	kreg, kreg, kreg
KORD	kreg, kreg, kreg
KORQ	kreg, kreg, kreg
KORTESTB	kreg, kreg
KORTESTD	kreg, kreg

KORTESTQ	kreg, kreg
KORTESTW	kreg, kreg
KORW	kreg, kreg, kreg
KSHIFTLB	kreg, kreg, imm8
KSHIFTLD	kreg, kreg, imm8
KSHIFTLQ	kreg, kreg, imm8
KSHIFTLW	kreg, kreg, imm8
KSHIFTRB	kreg, kreg, imm8
KSHIFTRD	kreg, kreg, imm8
KSHIFTRQ	kreg, kreg, imm8
KSHIFTRW	kreg, kreg, imm8
KTESTB	kreg, kreg
KTESTD	kreg, kreg
KTESTQ	kreg, kreg
KTESTW	kreg, kreg
KUNPCKBW	kreg, kreg, kreg
KUNPCKDQ	kreg, kreg, kreg
KUNPCKWD	kreg, kreg, kreg
KXNORB	kreg, kreg, kreg
KXNORD	kreg, kreg, kreg
KXNORQ	kreg, kreg, kreg
KXNORW	kreg, kreg, kreg
KXORB	kreg, kreg, kreg
KXORD	kreg, kreg, kreg
KXORQ	kreg, kreg, kreg
KXORW	kreg, kreg, kreg

B.1.40 AVX–512 instructions

VADDPD	xmmreg mask z, xmmreg*, xmmrm128	b64 AVX512VL
VADDPD	ymmreg mask z, ymmreg*, ymmrm256	b64 AVX512VL
VADDPD	zmmreg mask z, zmmreg*, zmmrm512	b64 er AVX512
VADDPS	xmmreg mask z, xmmreg*, xmmrm128	b32 AVX512VL
VADDPS	ymmreg mask z, ymmreg*, ymmrm256	b32 AVX512VL
VADDPS	zmmreg mask z, zmmreg*, zmmrm512	b32 er AVX512
VADDSD	xmmreg mask z, xmmreg*, xmmrm64	er AVX512
VADDSS	xmmreg mask z, xmmreg*, xmmrm32	er AVX512
VALIGND	xmmreg mask z, xmmreg*, xmmrm128	b32, imm8 AVX512VL
VALIGND	ymmreg mask z, ymmreg*, ymmrm256	b32, imm8 AVX512VL
VALIGND	zmmreg mask z, zmmreg*, zmmrm512	b32, imm8 AVX512
VALIGNQ	xmmreg mask z, xmmreg*, xmmrm128	b64, imm8 AVX512VL
VALIGNQ	ymmreg mask z, ymmreg*, ymmrm256	b64, imm8 AVX512VL
VALIGNQ	zmmreg mask z, zmmreg*, zmmrm512	b64, imm8 AVX512
VANDNPD	xmmreg mask z, xmmreg*, xmmrm128	b64 AVX512VL/DQ
VANDNPD	ymmreg mask z, ymmreg*, ymmrm256	b64 AVX512VL/DQ
VANDNPD	zmmreg mask z, zmmreg*, zmmrm512	b64 AVX512DQ
VANDNPS	xmmreg mask z, xmmreg*, xmmrm128	b32 AVX512VL/DQ
VANDNPS	ymmreg mask z, ymmreg*, ymmrm256	b32 AVX512VL/DQ
VANDNPS	zmmreg mask z, zmmreg*, zmmrm512	b32 AVX512DQ
VANDPD	xmmreg mask z, xmmreg*, xmmrm128	b64 AVX512VL/DQ
VANDPD	ymmreg mask z, ymmreg*, ymmrm256	b64 AVX512VL/DQ
VANDPD	zmmreg mask z, zmmreg*, zmmrm512	b64 AVX512DQ
VANDPS	xmmreg mask z, xmmreg*, xmmrm128	b32 AVX512VL/DQ
VANDPS	ymmreg mask z, ymmreg*, ymmrm256	b32 AVX512VL/DQ

VANDPS	zmmreg	mask	z, zmmreg*, zmmrm512	b32 AVX512DQ
VBLENDMPD	xmmreg	mask	z, xmmreg, xmmrm128	b64 AVX512VL
VBLENDMPD	ymmreg	mask	z, ymmreg, ymmrm256	b64 AVX512VL
VBLENDMPD	zmmreg	mask	z, zmmreg, zmmrm512	b64 AVX512
VBLENDMPS	xmmreg	mask	z, xmmreg, xmmrm128	b32 AVX512VL
VBLENDMPS	ymmreg	mask	z, ymmreg, ymmrm256	b32 AVX512VL
VBLENDMPS	zmmreg	mask	z, zmmreg, zmmrm512	b32 AVX512
VBROADCASTF32X2	ymmreg	mask	z, xmmrm64	AVX512VL/DQ
VBROADCASTF32X2	zmmreg	mask	z, xmmrm64	AVX512DQ
VBROADCASTF32X4	ymmreg	mask	z, mem128	AVX512VL
VBROADCASTF32X4	zmmreg	mask	z, mem128	AVX512
VBROADCASTF32X8	zmmreg	mask	z, mem256	AVX512DQ
VBROADCASTF64X2	ymmreg	mask	z, mem128	AVX512VL/DQ
VBROADCASTF64X2	zmmreg	mask	z, mem128	AVX512DQ
VBROADCASTF64X4	zmmreg	mask	z, mem256	AVX512
VBROADCASTI32X2	xmmreg	mask	z, xmmrm64	AVX512VL/DQ
VBROADCASTI32X2	ymmreg	mask	z, xmmrm64	AVX512VL/DQ
VBROADCASTI32X2	zmmreg	mask	z, xmmrm64	AVX512DQ
VBROADCASTI32X4	ymmreg	mask	z, mem128	AVX512VL
VBROADCASTI32X4	zmmreg	mask	z, mem128	AVX512
VBROADCASTI32X8	zmmreg	mask	z, mem256	AVX512DQ
VBROADCASTI64X2	ymmreg	mask	z, mem128	AVX512VL/DQ
VBROADCASTI64X2	zmmreg	mask	z, mem128	AVX512DQ
VBROADCASTI64X4	zmmreg	mask	z, mem256	AVX512
VBROADCASTSD	ymmreg	mask	z, mem64	AVX512VL
VBROADCASTSD	zmmreg	mask	z, mem64	AVX512
VBROADCASTSD	ymmreg	mask	z, xmmreg	AVX512VL
VBROADCASTSD	zmmreg	mask	z, xmmreg	AVX512
VBROADCASTSS	xmmreg	mask	z, mem32	AVX512VL
VBROADCASTSS	ymmreg	mask	z, mem32	AVX512VL
VBROADCASTSS	zmmreg	mask	z, mem32	AVX512
VBROADCASTSS	xmmreg	mask	z, xmmreg	AVX512VL
VBROADCASTSS	ymmreg	mask	z, xmmreg	AVX512VL
VBROADCASTSS	zmmreg	mask	z, xmmreg	AVX512
VCMPPD	kreg	mask, xmmreg, xmmrm128	b64, imm8	AVX512VL
VCMPPD	kreg	mask, ymmreg, ymmrm256	b64, imm8	AVX512VL
VCMPPD	kreg	mask, zmmreg, zmmrm512	b64 sae, imm8	AVX512
VCMPPS	kreg	mask, xmmreg, xmmrm128	b32, imm8	AVX512VL
VCMPPS	kreg	mask, ymmreg, ymmrm256	b32, imm8	AVX512VL
VCMPPS	kreg	mask, zmmreg, zmmrm512	b32 sae, imm8	AVX512
VCMPSD	kreg	mask, xmmreg, xmmrm64	sae, imm8	AVX512
VCMPS	kreg	mask, xmmreg, xmmrm32	sae, imm8	AVX512
VCOMISD	xmmreg, xmmrm64	sae		AVX512
VCOMISS	xmmreg, xmmrm32	sae		AVX512
VCOMPRESSPD	mem128	mask, xmmreg		AVX512VL
VCOMPRESSPD	mem256	mask, ymmreg		AVX512VL
VCOMPRESSPD	mem512	mask, zmmreg		AVX512
VCOMPRESSPD	xmmreg	mask	z, xmmreg	AVX512VL
VCOMPRESSPD	ymmreg	mask	z, ymmreg	AVX512VL
VCOMPRESSPD	zmmreg	mask	z, zmmreg	AVX512
VCOMPRESSPS	mem128	mask, xmmreg		AVX512VL
VCOMPRESSPS	mem256	mask, ymmreg		AVX512VL
VCOMPRESSPS	mem512	mask, zmmreg		AVX512
VCOMPRESSPS	xmmreg	mask	z, xmmreg	AVX512VL

VCOMPRESSPS	ymmreg	mask	z,ymmreg	AVX512VL
VCOMPRESSPS	zmmreg	mask	z,zmmreg	AVX512
VCVTDQ2PD	xmmreg	mask	z,xmmrmm64	b32 AVX512VL
VCVTDQ2PD	ymmreg	mask	z,xmmrmm128	b32 AVX512VL
VCVTDQ2PD	zmmreg	mask	z,ymmrm256	b32 er AVX512
VCVTDQ2PS	xmmreg	mask	z,xmmrmm128	b32 AVX512VL
VCVTDQ2PS	ymmreg	mask	z,ymmrm256	b32 AVX512VL
VCVTDQ2PS	zmmreg	mask	z,zmmrm512	b32 er AVX512
VCVTPD2DQ	xmmreg	mask	z,xmmrmm128	b64 AVX512VL
VCVTPD2DQ	xmmreg	mask	z,ymmrm256	b64 AVX512VL
VCVTPD2DQ	ymmreg	mask	z,zmmrm512	b64 er AVX512
VCVTPD2PS	xmmreg	mask	z,xmmrmm128	b64 AVX512VL
VCVTPD2PS	xmmreg	mask	z,ymmrm256	b64 AVX512VL
VCVTPD2PS	ymmreg	mask	z,zmmrm512	b64 er AVX512
VCVTPD2QQ	xmmreg	mask	z,xmmrmm128	b64 AVX512VL/DQ
VCVTPD2QQ	ymmreg	mask	z,ymmrm256	b64 AVX512VL/DQ
VCVTPD2QQ	zmmreg	mask	z,zmmrm512	b64 er AVX512DQ
VCVTPD2UDQ	xmmreg	mask	z,xmmrmm128	b64 AVX512VL
VCVTPD2UDQ	xmmreg	mask	z,ymmrm256	b64 AVX512VL
VCVTPD2UDQ	ymmreg	mask	z,zmmrm512	b64 er AVX512
VCVTPD2UQQ	xmmreg	mask	z,xmmrmm128	b64 AVX512VL/DQ
VCVTPD2UQQ	ymmreg	mask	z,ymmrm256	b64 AVX512VL/DQ
VCVTPD2UQQ	zmmreg	mask	z,zmmrm512	b64 er AVX512DQ
VCVTPH2PS	xmmreg	mask	z,xmmrmm64	AVX512VL
VCVTPH2PS	ymmreg	mask	z,xmmrmm128	AVX512VL
VCVTPH2PS	zmmreg	mask	z,ymmrm256	sae AVX512
VCVTPS2DQ	xmmreg	mask	z,xmmrmm128	b32 AVX512VL
VCVTPS2DQ	ymmreg	mask	z,ymmrm256	b32 AVX512VL
VCVTPS2DQ	zmmreg	mask	z,zmmrm512	b32 er AVX512
VCVTPS2PD	xmmreg	mask	z,xmmrmm64	b32 AVX512VL
VCVTPS2PD	ymmreg	mask	z,xmmrmm128	b32 AVX512VL
VCVTPS2PD	zmmreg	mask	z,ymmrm256	b32 sae AVX512
VCVTPS2PH	xmmreg	mask	z,xmmreg,imm8	AVX512VL
VCVTPS2PH	xmmreg	mask	z,ymmreg,imm8	AVX512VL
VCVTPS2PH	ymmreg	mask	z,zmmreg sae,imm8	AVX512
VCVTPS2PH	mem64	mask,xmmreg,imm8		AVX512VL
VCVTPS2PH	mem128	mask,ymmreg,imm8		AVX512VL
VCVTPS2PH	mem256	mask,zmmreg sae,imm8		AVX512
VCVTPS2QQ	xmmreg	mask	z,xmmrmm64	b32 AVX512VL/DQ
VCVTPS2QQ	ymmreg	mask	z,xmmrmm128	b32 AVX512VL/DQ
VCVTPS2QQ	zmmreg	mask	z,ymmrm256	b32 er AVX512DQ
VCVTPS2UDQ	xmmreg	mask	z,xmmrmm128	b32 AVX512VL
VCVTPS2UDQ	ymmreg	mask	z,ymmrm256	b32 AVX512VL
VCVTPS2UDQ	zmmreg	mask	z,zmmrm512	b32 er AVX512
VCVTPS2UQQ	xmmreg	mask	z,xmmrmm64	b32 AVX512VL/DQ
VCVTPS2UQQ	ymmreg	mask	z,xmmrmm128	b32 AVX512VL/DQ
VCVTPS2UQQ	zmmreg	mask	z,ymmrm256	b32 er AVX512DQ
VCVTQQ2PD	xmmreg	mask	z,xmmrmm128	b64 AVX512VL/DQ
VCVTQQ2PD	ymmreg	mask	z,ymmrm256	b64 AVX512VL/DQ
VCVTQQ2PD	zmmreg	mask	z,zmmrm512	b64 er AVX512DQ
VCVTQQ2PS	xmmreg	mask	z,xmmrmm128	b64 AVX512VL/DQ
VCVTQQ2PS	xmmreg	mask	z,ymmrm256	b64 AVX512VL/DQ
VCVTQQ2PS	ymmreg	mask	z,zmmrm512	b64 er AVX512DQ
VCVTSD2SI	reg32,xmmrmm64	er		AVX512

VCVTSD2SI	reg64, xmmrm64	er	AVX512
VCVTSD2SS	xmmreg mask z, xmmreg, xmmrm64	er	AVX512
VCVTSD2USI	reg32, xmmrm64	er	AVX512
VCVTSD2USI	reg64, xmmrm64	er	AVX512
VCVTSI2SD	xmmreg, xmmreg	er, rm32	AVX512
VCVTSI2SD	xmmreg, xmmreg	er, rm64	AVX512
VCVTSI2SS	xmmreg, xmmreg	er, rm32	AVX512
VCVTSI2SS	xmmreg, xmmreg	er, rm64	AVX512
VCVTSS2SD	xmmreg mask z, xmmreg, xmmrm32	sae	AVX512
VCVTSS2SI	reg32, xmmrm32	er	AVX512
VCVTSS2SI	reg64, xmmrm32	er	AVX512
VCVTSS2USI	reg32, xmmrm32	er	AVX512
VCVTSS2USI	reg64, xmmrm32	er	AVX512
VCVTTPD2DQ	xmmreg mask z, xmmrm128	b64	AVX512VL
VCVTTPD2DQ	xmmreg mask z, ymmrm256	b64	AVX512VL
VCVTTPD2DQ	ymmreg mask z, zmmrm512	b64 sae	AVX512
VCVTTPD2QQ	xmmreg mask z, xmmrm128	b64	AVX512VL/DQ
VCVTTPD2QQ	ymmreg mask z, ymmrm256	b64	AVX512VL/DQ
VCVTTPD2QQ	zmmreg mask z, zmmrm512	b64 sae	AVX512DQ
VCVTTPD2UDQ	xmmreg mask z, xmmrm128	b64	AVX512VL
VCVTTPD2UDQ	xmmreg mask z, ymmrm256	b64	AVX512VL
VCVTTPD2UDQ	ymmreg mask z, zmmrm512	b64 sae	AVX512
VCVTTPD2UQQ	xmmreg mask z, xmmrm128	b64	AVX512VL/DQ
VCVTTPD2UQQ	ymmreg mask z, ymmrm256	b64	AVX512VL/DQ
VCVTTPD2UQQ	zmmreg mask z, zmmrm512	b64 sae	AVX512DQ
VCVTTPS2DQ	xmmreg mask z, xmmrm128	b32	AVX512VL
VCVTTPS2DQ	ymmreg mask z, ymmrm256	b32	AVX512VL
VCVTTPS2DQ	zmmreg mask z, zmmrm512	b32 sae	AVX512
VCVTTPS2QQ	xmmreg mask z, xmmrm64	b32	AVX512VL/DQ
VCVTTPS2QQ	ymmreg mask z, xmmrm128	b32	AVX512VL/DQ
VCVTTPS2QQ	zmmreg mask z, ymmrm256	b32 sae	AVX512DQ
VCVTTPS2UDQ	xmmreg mask z, xmmrm128	b32	AVX512VL
VCVTTPS2UDQ	ymmreg mask z, ymmrm256	b32	AVX512VL
VCVTTPS2UDQ	zmmreg mask z, zmmrm512	b32 sae	AVX512
VCVTTPS2UQQ	xmmreg mask z, xmmrm64	b32	AVX512VL/DQ
VCVTTPS2UQQ	ymmreg mask z, xmmrm128	b32	AVX512VL/DQ
VCVTTPS2UQQ	zmmreg mask z, ymmrm256	b32 sae	AVX512DQ
VCVTTS2SI	reg32, xmmrm64	sae	AVX512
VCVTTS2SI	reg64, xmmrm64	sae	AVX512
VCVTTS2USI	reg32, xmmrm64	sae	AVX512
VCVTTS2USI	reg64, xmmrm64	sae	AVX512
VCVTSS2SI	reg32, xmmrm32	sae	AVX512
VCVTSS2SI	reg64, xmmrm32	sae	AVX512
VCVTSS2USI	reg32, xmmrm32	sae	AVX512
VCVTSS2USI	reg64, xmmrm32	sae	AVX512
VCVTUDQ2PD	xmmreg mask z, xmmrm64	b32	AVX512VL
VCVTUDQ2PD	ymmreg mask z, xmmrm128	b32	AVX512VL
VCVTUDQ2PD	zmmreg mask z, ymmrm256	b32 er	AVX512
VCVTUDQ2PS	xmmreg mask z, xmmrm128	b32	AVX512VL
VCVTUDQ2PS	ymmreg mask z, ymmrm256	b32	AVX512VL
VCVTUDQ2PS	zmmreg mask z, zmmrm512	b32 er	AVX512
VCVTUQQ2PD	xmmreg mask z, xmmrm128	b64	AVX512VL/DQ
VCVTUQQ2PD	ymmreg mask z, ymmrm256	b64	AVX512VL/DQ
VCVTUQQ2PD	zmmreg mask z, zmmrm512	b64 er	AVX512DQ

VCVTUQQ2PS	xmmreg	mask	z, xmmrm128	b64	AVX512VL/DQ
VCVTUQQ2PS	xmmreg	mask	z, ymmrm256	b64	AVX512VL/DQ
VCVTUQQ2PS	ymmreg	mask	z, zmmrm512	b64	er AVX512DQ
VCVTUSI2SD	xmmreg, xmmreg	er, rm32			AVX512
VCVTUSI2SD	xmmreg, xmmreg	er, rm64			AVX512
VCVTUSI2SS	xmmreg, xmmreg	er, rm32			AVX512
VCVTUSI2SS	xmmreg, xmmreg	er, rm64			AVX512
VDBPSADBW	xmmreg	mask	z, xmmreg*, xmmrm128, imm8		AVX512VL/BW
VDBPSADBW	ymmreg	mask	z, ymmreg*, ymmrm256, imm8		AVX512VL/BW
VDBPSADBW	zmmreg	mask	z, zmmreg*, zmmrm512, imm8		AVX512BW
VDIVPD	xmmreg	mask	z, xmmreg*, xmmrm128	b64	AVX512VL
VDIVPD	ymmreg	mask	z, ymmreg*, ymmrm256	b64	AVX512VL
VDIVPD	zmmreg	mask	z, zmmreg*, zmmrm512	b64	er AVX512
VDIVPS	xmmreg	mask	z, xmmreg*, xmmrm128	b32	AVX512VL
VDIVPS	ymmreg	mask	z, ymmreg*, ymmrm256	b32	AVX512VL
VDIVPS	zmmreg	mask	z, zmmreg*, zmmrm512	b32	er AVX512
VDIVSD	xmmreg	mask	z, xmmreg*, xmmrm64	er	AVX512
VDIVSS	xmmreg	mask	z, xmmreg*, xmmrm32	er	AVX512
VEXP2PD	zmmreg	mask	z, zmmrm512	b64	sae AVX512ER
VEXP2PS	zmmreg	mask	z, zmmrm512	b32	sae AVX512ER
VEXPANDPD	xmmreg	mask	z, mem128		AVX512VL
VEXPANDPD	ymmreg	mask	z, mem256		AVX512VL
VEXPANDPD	zmmreg	mask	z, mem512		AVX512
VEXPANDPD	xmmreg	mask	z, xmmreg		AVX512VL
VEXPANDPD	ymmreg	mask	z, ymmreg		AVX512VL
VEXPANDPD	zmmreg	mask	z, zmmreg		AVX512
VEXPANDPS	xmmreg	mask	z, mem128		AVX512VL
VEXPANDPS	ymmreg	mask	z, mem256		AVX512VL
VEXPANDPS	zmmreg	mask	z, mem512		AVX512
VEXPANDPS	xmmreg	mask	z, xmmreg		AVX512VL
VEXPANDPS	ymmreg	mask	z, ymmreg		AVX512VL
VEXPANDPS	zmmreg	mask	z, zmmreg		AVX512
VEXTRACTF32X4	xmmreg	mask	z, ymmreg, imm8		AVX512VL
VEXTRACTF32X4	xmmreg	mask	z, zmmreg, imm8		AVX512
VEXTRACTF32X4	mem128	mask, ymmreg, imm8			AVX512VL
VEXTRACTF32X4	mem128	mask, zmmreg, imm8			AVX512
VEXTRACTF32X8	ymmreg	mask	z, zmmreg, imm8		AVX512DQ
VEXTRACTF32X8	mem256	mask, zmmreg, imm8			AVX512DQ
VEXTRACTF64X2	xmmreg	mask	z, ymmreg, imm8		AVX512VL/DQ
VEXTRACTF64X2	xmmreg	mask	z, zmmreg, imm8		AVX512DQ
VEXTRACTF64X2	mem128	mask, ymmreg, imm8			AVX512VL/DQ
VEXTRACTF64X2	mem128	mask, zmmreg, imm8			AVX512DQ
VEXTRACTF64X4	ymmreg	mask	z, zmmreg, imm8		AVX512
VEXTRACTF64X4	mem256	mask, zmmreg, imm8			AVX512
VEXTRACTI32X4	xmmreg	mask	z, ymmreg, imm8		AVX512VL
VEXTRACTI32X4	xmmreg	mask	z, zmmreg, imm8		AVX512
VEXTRACTI32X4	mem128	mask, ymmreg, imm8			AVX512VL
VEXTRACTI32X4	mem128	mask, zmmreg, imm8			AVX512
VEXTRACTI32X8	ymmreg	mask	z, zmmreg, imm8		AVX512DQ
VEXTRACTI32X8	mem256	mask, zmmreg, imm8			AVX512DQ
VEXTRACTI64X2	xmmreg	mask	z, ymmreg, imm8		AVX512VL/DQ
VEXTRACTI64X2	xmmreg	mask	z, zmmreg, imm8		AVX512DQ
VEXTRACTI64X2	mem128	mask, ymmreg, imm8			AVX512VL/DQ
VEXTRACTI64X2	mem128	mask, zmmreg, imm8			AVX512DQ

VEEXTRACTI64X4	ymmreg	mask	z, zmmreg, imm8	AVX512
VEEXTRACTI64X4	mem256	mask	zmmreg, imm8	AVX512
VEEXTRACTPS	reg32, xmmreg		imm8	AVX512
VEEXTRACTPS	reg64, xmmreg		imm8	AVX512
VEEXTRACTPS	mem32, xmmreg		imm8	AVX512
VFIXUPIMMPD	xmmreg	mask	z, xmmreg*, xmmrm128	b64, imm8 AVX512VL
VFIXUPIMMPD	ymmreg	mask	z, ymmreg*, ymmrm256	b64, imm8 AVX512VL
VFIXUPIMMPD	zmmreg	mask	z, zmmreg*, zmmrm512	b64 sae, imm8 AVX512
VFIXUPIMMPS	xmmreg	mask	z, xmmreg*, xmmrm128	b32, imm8 AVX512VL
VFIXUPIMMPS	ymmreg	mask	z, ymmreg*, ymmrm256	b32, imm8 AVX512VL
VFIXUPIMMPS	zmmreg	mask	z, zmmreg*, zmmrm512	b32 sae, imm8 AVX512
VFIXUPIMMSD	xmmreg	mask	z, xmmreg*, xmmrm64	sae, imm8 AVX512
VFIXUPIMMSS	xmmreg	mask	z, xmmreg*, xmmrm32	sae, imm8 AVX512
VFMADD132PD	xmmreg	mask	z, xmmreg, xmmrm128	b64 AVX512VL
VFMADD132PD	ymmreg	mask	z, ymmreg, ymmrm256	b64 AVX512VL
VFMADD132PD	zmmreg	mask	z, zmmreg, zmmrm512	b64 er AVX512
VFMADD132PS	xmmreg	mask	z, xmmreg, xmmrm128	b32 AVX512VL
VFMADD132PS	ymmreg	mask	z, ymmreg, ymmrm256	b32 AVX512VL
VFMADD132PS	zmmreg	mask	z, zmmreg, zmmrm512	b32 er AVX512
VFMADD132SD	xmmreg	mask	z, xmmreg, xmmrm64	er AVX512
VFMADD132SS	xmmreg	mask	z, xmmreg, xmmrm32	er AVX512
VFMADD213PD	xmmreg	mask	z, xmmreg, xmmrm128	b64 AVX512VL
VFMADD213PD	ymmreg	mask	z, ymmreg, ymmrm256	b64 AVX512VL
VFMADD213PD	zmmreg	mask	z, zmmreg, zmmrm512	b64 er AVX512
VFMADD213PS	xmmreg	mask	z, xmmreg, xmmrm128	b32 AVX512VL
VFMADD213PS	ymmreg	mask	z, ymmreg, ymmrm256	b32 AVX512VL
VFMADD213PS	zmmreg	mask	z, zmmreg, zmmrm512	b32 er AVX512
VFMADD213SD	xmmreg	mask	z, xmmreg, xmmrm64	er AVX512
VFMADD213SS	xmmreg	mask	z, xmmreg, xmmrm32	er AVX512
VFMADD231PD	xmmreg	mask	z, xmmreg, xmmrm128	b64 AVX512VL
VFMADD231PD	ymmreg	mask	z, ymmreg, ymmrm256	b64 AVX512VL
VFMADD231PD	zmmreg	mask	z, zmmreg, zmmrm512	b64 er AVX512
VFMADD231PS	xmmreg	mask	z, xmmreg, xmmrm128	b32 AVX512VL
VFMADD231PS	ymmreg	mask	z, ymmreg, ymmrm256	b32 AVX512VL
VFMADD231PS	zmmreg	mask	z, zmmreg, zmmrm512	b32 er AVX512
VFMADD231SD	xmmreg	mask	z, xmmreg, xmmrm64	er AVX512
VFMADD231SS	xmmreg	mask	z, xmmreg, xmmrm32	er AVX512
VFMADDSUB132PD	xmmreg	mask	z, xmmreg, xmmrm128	b64 AVX512VL
VFMADDSUB132PD	ymmreg	mask	z, ymmreg, ymmrm256	b64 AVX512VL
VFMADDSUB132PD	zmmreg	mask	z, zmmreg, zmmrm512	b64 er AVX512
VFMADDSUB132PS	xmmreg	mask	z, xmmreg, xmmrm128	b32 AVX512VL
VFMADDSUB132PS	ymmreg	mask	z, ymmreg, ymmrm256	b32 AVX512VL
VFMADDSUB132PS	zmmreg	mask	z, zmmreg, zmmrm512	b32 er AVX512
VFMADDSUB213PD	xmmreg	mask	z, xmmreg, xmmrm128	b64 AVX512VL
VFMADDSUB213PD	ymmreg	mask	z, ymmreg, ymmrm256	b64 AVX512VL
VFMADDSUB213PD	zmmreg	mask	z, zmmreg, zmmrm512	b64 er AVX512
VFMADDSUB213PS	xmmreg	mask	z, xmmreg, xmmrm128	b32 AVX512VL
VFMADDSUB213PS	ymmreg	mask	z, ymmreg, ymmrm256	b32 AVX512VL
VFMADDSUB213PS	zmmreg	mask	z, zmmreg, zmmrm512	b32 er AVX512
VFMADDSUB231PD	xmmreg	mask	z, xmmreg, xmmrm128	b64 AVX512VL
VFMADDSUB231PD	ymmreg	mask	z, ymmreg, ymmrm256	b64 AVX512VL
VFMADDSUB231PD	zmmreg	mask	z, zmmreg, zmmrm512	b64 er AVX512
VFMADDSUB231PS	xmmreg	mask	z, xmmreg, xmmrm128	b32 AVX512VL
VFMADDSUB231PS	ymmreg	mask	z, ymmreg, ymmrm256	b32 AVX512VL

VFMADDSUB231PS	zmmreg	mask	z, zmmreg, zmmrm512	b32	er AVX512
VFMSUB132PD	xmmreg	mask	z, xmmreg, xmmrm128	b64	AVX512VL
VFMSUB132PD	ymmreg	mask	z, ymmreg, ymmrm256	b64	AVX512VL
VFMSUB132PD	zmmreg	mask	z, zmmreg, zmmrm512	b64	er AVX512
VFMSUB132PS	xmmreg	mask	z, xmmreg, xmmrm128	b32	AVX512VL
VFMSUB132PS	ymmreg	mask	z, ymmreg, ymmrm256	b32	AVX512VL
VFMSUB132PS	zmmreg	mask	z, zmmreg, zmmrm512	b32	er AVX512
VFMSUB132SD	xmmreg	mask	z, xmmreg, xmmrm64	er	AVX512
VFMSUB132SS	xmmreg	mask	z, xmmreg, xmmrm32	er	AVX512
VFMSUB213PD	xmmreg	mask	z, xmmreg, xmmrm128	b64	AVX512VL
VFMSUB213PD	ymmreg	mask	z, ymmreg, ymmrm256	b64	AVX512VL
VFMSUB213PD	zmmreg	mask	z, zmmreg, zmmrm512	b64	er AVX512
VFMSUB213PS	xmmreg	mask	z, xmmreg, xmmrm128	b32	AVX512VL
VFMSUB213PS	ymmreg	mask	z, ymmreg, ymmrm256	b32	AVX512VL
VFMSUB213PS	zmmreg	mask	z, zmmreg, zmmrm512	b32	er AVX512
VFMSUB213SD	xmmreg	mask	z, xmmreg, xmmrm64	er	AVX512
VFMSUB213SS	xmmreg	mask	z, xmmreg, xmmrm32	er	AVX512
VFMSUB231PD	xmmreg	mask	z, xmmreg, xmmrm128	b64	AVX512VL
VFMSUB231PD	ymmreg	mask	z, ymmreg, ymmrm256	b64	AVX512VL
VFMSUB231PD	zmmreg	mask	z, zmmreg, zmmrm512	b64	er AVX512
VFMSUB231PS	xmmreg	mask	z, xmmreg, xmmrm128	b32	AVX512VL
VFMSUB231PS	ymmreg	mask	z, ymmreg, ymmrm256	b32	AVX512VL
VFMSUB231PS	zmmreg	mask	z, zmmreg, zmmrm512	b32	er AVX512
VFMSUB231SD	xmmreg	mask	z, xmmreg, xmmrm64	er	AVX512
VFMSUB231SS	xmmreg	mask	z, xmmreg, xmmrm32	er	AVX512
VFMSUBADD132PD	xmmreg	mask	z, xmmreg, xmmrm128	b64	AVX512VL
VFMSUBADD132PD	ymmreg	mask	z, ymmreg, ymmrm256	b64	AVX512VL
VFMSUBADD132PD	zmmreg	mask	z, zmmreg, zmmrm512	b64	er AVX512
VFMSUBADD132PS	xmmreg	mask	z, xmmreg, xmmrm128	b32	AVX512VL
VFMSUBADD132PS	ymmreg	mask	z, ymmreg, ymmrm256	b32	AVX512VL
VFMSUBADD132PS	zmmreg	mask	z, zmmreg, zmmrm512	b32	er AVX512
VFMSUBADD213PD	xmmreg	mask	z, xmmreg, xmmrm128	b64	AVX512VL
VFMSUBADD213PD	ymmreg	mask	z, ymmreg, ymmrm256	b64	AVX512VL
VFMSUBADD213PD	zmmreg	mask	z, zmmreg, zmmrm512	b64	er AVX512
VFMSUBADD213PS	xmmreg	mask	z, xmmreg, xmmrm128	b32	AVX512VL
VFMSUBADD213PS	ymmreg	mask	z, ymmreg, ymmrm256	b32	AVX512VL
VFMSUBADD213PS	zmmreg	mask	z, zmmreg, zmmrm512	b32	er AVX512
VFMSUBADD231PD	xmmreg	mask	z, xmmreg, xmmrm128	b64	AVX512VL
VFMSUBADD231PD	ymmreg	mask	z, ymmreg, ymmrm256	b64	AVX512VL
VFMSUBADD231PD	zmmreg	mask	z, zmmreg, zmmrm512	b64	er AVX512
VFMSUBADD231PS	xmmreg	mask	z, xmmreg, xmmrm128	b32	AVX512VL
VFMSUBADD231PS	ymmreg	mask	z, ymmreg, ymmrm256	b32	AVX512VL
VFMSUBADD231PS	zmmreg	mask	z, zmmreg, zmmrm512	b32	er AVX512
VFNMADD132PD	xmmreg	mask	z, xmmreg, xmmrm128	b64	AVX512VL
VFNMADD132PD	ymmreg	mask	z, ymmreg, ymmrm256	b64	AVX512VL
VFNMADD132PD	zmmreg	mask	z, zmmreg, zmmrm512	b64	er AVX512
VFNMADD132PS	xmmreg	mask	z, xmmreg, xmmrm128	b32	AVX512VL
VFNMADD132PS	ymmreg	mask	z, ymmreg, ymmrm256	b32	AVX512VL
VFNMADD132PS	zmmreg	mask	z, zmmreg, zmmrm512	b32	er AVX512
VFNMADD132SD	xmmreg	mask	z, xmmreg, xmmrm64	er	AVX512
VFNMADD132SS	xmmreg	mask	z, xmmreg, xmmrm32	er	AVX512
VFNMADD213PD	xmmreg	mask	z, xmmreg, xmmrm128	b64	AVX512VL
VFNMADD213PD	ymmreg	mask	z, ymmreg, ymmrm256	b64	AVX512VL
VFNMADD213PD	zmmreg	mask	z, zmmreg, zmmrm512	b64	er AVX512

VFNMADD213PS	xmmreg	mask	z, xmmreg, xmmr128	b32	AVX512VL		
VFNMADD213PS	ymmreg	mask	z, ymmreg, ymmr256	b32	AVX512VL		
VFNMADD213PS	zmmreg	mask	z, zmmreg, zmmr512	b32	er AVX512		
VFNMADD213SD	xmmreg	mask	z, xmmreg, xmmr64	er	AVX512		
VFNMADD213SS	xmmreg	mask	z, xmmreg, xmmr32	er	AVX512		
VFNMADD231PD	xmmreg	mask	z, xmmreg, xmmr128	b64	AVX512VL		
VFNMADD231PD	ymmreg	mask	z, ymmreg, ymmr256	b64	AVX512VL		
VFNMADD231PD	zmmreg	mask	z, zmmreg, zmmr512	b64	er AVX512		
VFNMADD231PS	xmmreg	mask	z, xmmreg, xmmr128	b32	AVX512VL		
VFNMADD231PS	ymmreg	mask	z, ymmreg, ymmr256	b32	AVX512VL		
VFNMADD231PS	zmmreg	mask	z, zmmreg, zmmr512	b32	er AVX512		
VFNMADD231SD	xmmreg	mask	z, xmmreg, xmmr64	er	AVX512		
VFNMADD231SS	xmmreg	mask	z, xmmreg, xmmr32	er	AVX512		
VFNMSUB132PD	xmmreg	mask	z, xmmreg, xmmr128	b64	AVX512VL		
VFNMSUB132PD	ymmreg	mask	z, ymmreg, ymmr256	b64	AVX512VL		
VFNMSUB132PD	zmmreg	mask	z, zmmreg, zmmr512	b64	er AVX512		
VFNMSUB132PS	xmmreg	mask	z, xmmreg, xmmr128	b32	AVX512VL		
VFNMSUB132PS	ymmreg	mask	z, ymmreg, ymmr256	b32	AVX512VL		
VFNMSUB132PS	zmmreg	mask	z, zmmreg, zmmr512	b32	er AVX512		
VFNMSUB132SD	xmmreg	mask	z, xmmreg, xmmr64	er	AVX512		
VFNMSUB132SS	xmmreg	mask	z, xmmreg, xmmr32	er	AVX512		
VFNMSUB213PD	xmmreg	mask	z, xmmreg, xmmr128	b64	AVX512VL		
VFNMSUB213PD	ymmreg	mask	z, ymmreg, ymmr256	b64	AVX512VL		
VFNMSUB213PD	zmmreg	mask	z, zmmreg, zmmr512	b64	er AVX512		
VFNMSUB213PS	xmmreg	mask	z, xmmreg, xmmr128	b32	AVX512VL		
VFNMSUB213PS	ymmreg	mask	z, ymmreg, ymmr256	b32	AVX512VL		
VFNMSUB213PS	zmmreg	mask	z, zmmreg, zmmr512	b32	er AVX512		
VFNMSUB213SD	xmmreg	mask	z, xmmreg, xmmr64	er	AVX512		
VFNMSUB213SS	xmmreg	mask	z, xmmreg, xmmr32	er	AVX512		
VFNMSUB231PD	xmmreg	mask	z, xmmreg, xmmr128	b64	AVX512VL		
VFNMSUB231PD	ymmreg	mask	z, ymmreg, ymmr256	b64	AVX512VL		
VFNMSUB231PD	zmmreg	mask	z, zmmreg, zmmr512	b64	er AVX512		
VFNMSUB231PS	xmmreg	mask	z, xmmreg, xmmr128	b32	AVX512VL		
VFNMSUB231PS	ymmreg	mask	z, ymmreg, ymmr256	b32	AVX512VL		
VFNMSUB231PS	zmmreg	mask	z, zmmreg, zmmr512	b32	er AVX512		
VFNMSUB231SD	xmmreg	mask	z, xmmreg, xmmr64	er	AVX512		
VFNMSUB231SS	xmmreg	mask	z, xmmreg, xmmr32	er	AVX512		
VFPCLASSPD	kreg	mask, xmmr128	b64, imm8	AVX512VL/DQ			
VFPCLASSPD	kreg	mask, ymmr256	b64, imm8	AVX512VL/DQ			
VFPCLASSPD	kreg	mask, zmmr512	b64, imm8	AVX512DQ			
VFPCLASSPS	kreg	mask, xmmr128	b32, imm8	AVX512VL/DQ			
VFPCLASSPS	kreg	mask, ymmr256	b32, imm8	AVX512VL/DQ			
VFPCLASSPS	kreg	mask, zmmr512	b32, imm8	AVX512DQ			
VFPCLASSSD	kreg	mask, xmmr64, imm8	AVX512DQ				
VFPCLASSSS	kreg	mask, xmmr32, imm8	AVX512DQ				
VGATHERDPD	xmmreg	mask, xmem64	AVX512VL				
VGATHERDPD	ymmreg	mask, xmem64	AVX512VL				
VGATHERDPD	zmmreg	mask, ymem64	AVX512				
VGATHERDPS	xmmreg	mask, xmem32	AVX512VL				
VGATHERDPS	ymmreg	mask, ymem32	AVX512VL				
VGATHERDPS	zmmreg	mask, zmem32	AVX512				
VGATHERPF0DPD	ymem64	mask	AVX512PF				
VGATHERPF0DPS	zmem32	mask	AVX512PF				
VGATHERPF0QPD	zmem64	mask	AVX512PF				

VGATHERPF0QPS	zmem32	mask		AVX512PF
VGATHERPF1DPD	ymem64	mask		AVX512PF
VGATHERPF1DPS	zmem32	mask		AVX512PF
VGATHERPF1QPD	zmem64	mask		AVX512PF
VGATHERPF1QPS	zmem32	mask		AVX512PF
VGATHERQPD	xmmreg	mask, xmem64		AVX512VL
VGATHERQPD	ymmreg	mask, ymem64		AVX512VL
VGATHERQPD	zmmreg	mask, zmem64		AVX512
VGATHERQPS	xmmreg	mask, xmem32		AVX512VL
VGATHERQPS	xmmreg	mask, ymem32		AVX512VL
VGATHERQPS	ymmreg	mask, zmem32		AVX512
VGETEXPPD	xmmreg	mask	z, xmmrmm128	b64 AVX512VL
VGETEXPPD	ymmreg	mask	z, ymmrmm256	b64 AVX512VL
VGETEXPPD	zmmreg	mask	z, zmmrmm512	b64 sae AVX512
VGETEXPPS	xmmreg	mask	z, xmmrmm128	b32 AVX512VL
VGETEXPPS	ymmreg	mask	z, ymmrmm256	b32 AVX512VL
VGETEXPPS	zmmreg	mask	z, zmmrmm512	b32 sae AVX512
VGETEXPSD	xmmreg	mask	z, xmmreg, xmmrmm64	sae AVX512
VGETEXPSS	xmmreg	mask	z, xmmreg, xmmrmm32	sae AVX512
VGETMANTPD	xmmreg	mask	z, xmmrmm128	b64, imm8 AVX512VL
VGETMANTPD	ymmreg	mask	z, ymmrmm256	b64, imm8 AVX512VL
VGETMANTPD	zmmreg	mask	z, zmmrmm512	b64 sae, imm8 AVX512
VGETMANTPS	xmmreg	mask	z, xmmrmm128	b32, imm8 AVX512VL
VGETMANTPS	ymmreg	mask	z, ymmrmm256	b32, imm8 AVX512VL
VGETMANTPS	zmmreg	mask	z, zmmrmm512	b32 sae, imm8 AVX512
VGETMANTSD	xmmreg	mask	z, xmmreg, xmmrmm64	sae, imm8 AVX512
VGETMANTSS	xmmreg	mask	z, xmmreg, xmmrmm32	sae, imm8 AVX512
VINSERTF32X4	ymmreg	mask	z, ymmreg*, xmmrmm128, imm8	AVX512VL
VINSERTF32X4	zmmreg	mask	z, zmmreg*, xmmrmm128, imm8	AVX512
VINSERTF32X8	zmmreg	mask	z, zmmreg*, ymmrmm256, imm8	AVX512DQ
VINSERTF64X2	ymmreg	mask	z, ymmreg*, xmmrmm128, imm8	AVX512VL/DQ
VINSERTF64X2	zmmreg	mask	z, zmmreg*, xmmrmm128, imm8	AVX512DQ
VINSERTF64X4	zmmreg	mask	z, zmmreg*, ymmrmm256, imm8	AVX512
VINSERTI32X4	ymmreg	mask	z, ymmreg*, xmmrmm128, imm8	AVX512VL
VINSERTI32X4	zmmreg	mask	z, zmmreg*, xmmrmm128, imm8	AVX512
VINSERTI32X8	zmmreg	mask	z, zmmreg*, ymmrmm256, imm8	AVX512DQ
VINSERTI64X2	ymmreg	mask	z, ymmreg*, xmmrmm128, imm8	AVX512VL/DQ
VINSERTI64X2	zmmreg	mask	z, zmmreg*, xmmrmm128, imm8	AVX512DQ
VINSERTI64X4	zmmreg	mask	z, zmmreg*, ymmrmm256, imm8	AVX512
VINSERTPS	xmmreg	mask	z, xmmreg*, xmmrmm32, imm8	AVX512
VMAXPD	xmmreg	mask	z, xmmreg*, xmmrmm128	b64 AVX512VL
VMAXPD	ymmreg	mask	z, ymmreg*, ymmrmm256	b64 AVX512VL
VMAXPD	zmmreg	mask	z, zmmreg*, zmmrmm512	b64 sae AVX512
VMAXPS	xmmreg	mask	z, xmmreg*, xmmrmm128	b32 AVX512VL
VMAXPS	ymmreg	mask	z, ymmreg*, ymmrmm256	b32 AVX512VL
VMAXPS	zmmreg	mask	z, zmmreg*, zmmrmm512	b32 sae AVX512
VMAXSD	xmmreg	mask	z, xmmreg*, xmmrmm64	sae AVX512
VMAXSS	xmmreg	mask	z, xmmreg*, xmmrmm32	sae AVX512
VMINPD	xmmreg	mask	z, xmmreg*, xmmrmm128	b64 AVX512VL
VMINPD	ymmreg	mask	z, ymmreg*, ymmrmm256	b64 AVX512VL
VMINPD	zmmreg	mask	z, zmmreg*, zmmrmm512	b64 sae AVX512
VMINPS	xmmreg	mask	z, xmmreg*, xmmrmm128	b32 AVX512VL
VMINPS	ymmreg	mask	z, ymmreg*, ymmrmm256	b32 AVX512VL
VMINPS	zmmreg	mask	z, zmmreg*, zmmrmm512	b32 sae AVX512

VMINSD	xmmreg	mask	z, xmmreg*, xmmrm64	sae AVX512
VMINSS	xmmreg	mask	z, xmmreg*, xmmrm32	sae AVX512
VMOVAPD	xmmreg	mask	z, xmmrm128	AVX512VL
VMOVAPD	ymmreg	mask	z, ymmrm256	AVX512VL
VMOVAPD	zmmreg	mask	z, zmmrm512	AVX512
VMOVAPD	xmmreg	mask	z, xmmreg	AVX512VL
VMOVAPD	ymmreg	mask	z, ymmreg	AVX512VL
VMOVAPD	zmmreg	mask	z, zmmreg	AVX512
VMOVAPD	mem128	mask, xmmreg		AVX512VL
VMOVAPD	mem256	mask, ymmreg		AVX512VL
VMOVAPD	mem512	mask, zmmreg		AVX512
VMOVAPS	xmmreg	mask	z, xmmrm128	AVX512VL
VMOVAPS	ymmreg	mask	z, ymmrm256	AVX512VL
VMOVAPS	zmmreg	mask	z, zmmrm512	AVX512
VMOVAPS	xmmreg	mask	z, xmmreg	AVX512VL
VMOVAPS	ymmreg	mask	z, ymmreg	AVX512VL
VMOVAPS	zmmreg	mask	z, zmmreg	AVX512
VMOVAPS	mem128	mask, xmmreg		AVX512VL
VMOVAPS	mem256	mask, ymmreg		AVX512VL
VMOVAPS	mem512	mask, zmmreg		AVX512
VMOVD	xmmreg, rm32			AVX512
VMOVD	rm32, xmmreg			AVX512
VMOVDDUP	xmmreg	mask	z, xmmrm64	AVX512VL
VMOVDDUP	ymmreg	mask	z, ymmrm256	AVX512VL
VMOVDDUP	zmmreg	mask	z, zmmrm512	AVX512
VMOVDQA32	xmmreg	mask	z, xmmrm128	AVX512VL
VMOVDQA32	ymmreg	mask	z, ymmrm256	AVX512VL
VMOVDQA32	zmmreg	mask	z, zmmrm512	AVX512
VMOVDQA32	xmmrm128	mask	z, xmmreg	AVX512VL
VMOVDQA32	ymmrm256	mask	z, ymmreg	AVX512VL
VMOVDQA32	zmmrm512	mask	z, zmmreg	AVX512
VMOVDQA64	xmmreg	mask	z, xmmrm128	AVX512VL
VMOVDQA64	ymmreg	mask	z, ymmrm256	AVX512VL
VMOVDQA64	zmmreg	mask	z, zmmrm512	AVX512
VMOVDQA64	xmmrm128	mask	z, xmmreg	AVX512VL
VMOVDQA64	ymmrm256	mask	z, ymmreg	AVX512VL
VMOVDQA64	zmmrm512	mask	z, zmmreg	AVX512
VMOVDQU16	xmmreg	mask	z, xmmrm128	AVX512VL/BW
VMOVDQU16	ymmreg	mask	z, ymmrm256	AVX512VL/BW
VMOVDQU16	zmmreg	mask	z, zmmrm512	AVX512BW
VMOVDQU16	xmmrm128	mask	z, xmmreg	AVX512VL/BW
VMOVDQU16	ymmrm256	mask	z, ymmreg	AVX512VL/BW
VMOVDQU16	zmmrm512	mask	z, zmmreg	AVX512BW
VMOVDQU32	xmmreg	mask	z, xmmrm128	AVX512VL
VMOVDQU32	ymmreg	mask	z, ymmrm256	AVX512VL
VMOVDQU32	zmmreg	mask	z, zmmrm512	AVX512
VMOVDQU32	xmmrm128	mask	z, xmmreg	AVX512VL
VMOVDQU32	ymmrm256	mask	z, ymmreg	AVX512VL
VMOVDQU32	zmmrm512	mask	z, zmmreg	AVX512
VMOVDQU64	xmmreg	mask	z, xmmrm128	AVX512VL
VMOVDQU64	ymmreg	mask	z, ymmrm256	AVX512VL
VMOVDQU64	zmmreg	mask	z, zmmrm512	AVX512
VMOVDQU64	xmmrm128	mask	z, xmmreg	AVX512VL
VMOVDQU64	ymmrm256	mask	z, ymmreg	AVX512VL

VMOVDQU64	zmmrm512 mask z, zmmreg	AVX512
VMOVDQU8	xmmreg mask z, xmmrm128	AVX512VL/BW
VMOVDQU8	ymmreg mask z, ymmrm256	AVX512VL/BW
VMOVDQU8	zmmreg mask z, zmmrm512	AVX512BW
VMOVDQU8	xmmrm128 mask z, xmmreg	AVX512VL/BW
VMOVDQU8	ymmrm256 mask z, ymmreg	AVX512VL/BW
VMOVDQU8	zmmrm512 mask z, zmmreg	AVX512BW
VMOVHLPS	xmmreg, xmmreg*, xmmreg	AVX512
VMOVHPD	xmmreg, xmmreg*, mem64	AVX512
VMOVHPD	mem64, xmmreg	AVX512
VMOVHPS	xmmreg, xmmreg*, mem64	AVX512
VMOVHPS	mem64, xmmreg	AVX512
VMOVLHPS	xmmreg, xmmreg*, xmmreg	AVX512
VMOVLPD	xmmreg, xmmreg*, mem64	AVX512
VMOVLPD	mem64, xmmreg	AVX512
VMOVLPS	xmmreg, xmmreg*, mem64	AVX512
VMOVLPS	mem64, xmmreg	AVX512
VMOVNTDQ	mem128, xmmreg	AVX512VL
VMOVNTDQ	mem256, ymmreg	AVX512VL
VMOVNTDQ	mem512, zmmreg	AVX512
VMOVNTDQA	xmmreg, mem128	AVX512VL
VMOVNTDQA	ymmreg, mem256	AVX512VL
VMOVNTDQA	zmmreg, mem512	AVX512
VMOVNTPD	mem128, xmmreg	AVX512VL
VMOVNTPD	mem256, ymmreg	AVX512VL
VMOVNTPD	mem512, zmmreg	AVX512
VMOVNTPS	mem128, xmmreg	AVX512VL
VMOVNTPS	mem256, ymmreg	AVX512VL
VMOVNTPS	mem512, zmmreg	AVX512
VMOVQ	xmmreg, rm64	AVX512
VMOVQ	rm64, xmmreg	AVX512
VMOVQ	xmmreg, xmmrm64	AVX512
VMOVQ	xmmrm64, xmmreg	AVX512
VMOVSD	xmmreg mask z, mem64	AVX512
VMOVSD	mem64 mask, xmmreg	AVX512
VMOVSD	xmmreg mask z, xmmreg*, xmmreg	AVX512
VMOVSD	xmmreg mask z, xmmreg*, xmmreg	AVX512
VMOVSHDUP	xmmreg mask z, xmmrm128	AVX512VL
VMOVSHDUP	ymmreg mask z, ymmrm256	AVX512VL
VMOVSHDUP	zmmreg mask z, zmmrm512	AVX512
VMOVSLDUP	xmmreg mask z, xmmrm128	AVX512VL
VMOVSLDUP	ymmreg mask z, ymmrm256	AVX512VL
VMOVSLDUP	zmmreg mask z, zmmrm512	AVX512
VMOVSS	xmmreg mask z, mem32	AVX512
VMOVSS	mem32 mask, xmmreg	AVX512
VMOVSS	xmmreg mask z, xmmreg*, xmmreg	AVX512
VMOVSS	xmmreg mask z, xmmreg*, xmmreg	AVX512
VMOVUPD	xmmreg mask z, xmmrm128	AVX512VL
VMOVUPD	ymmreg mask z, ymmrm256	AVX512VL
VMOVUPD	zmmreg mask z, zmmrm512	AVX512
VMOVUPD	xmmreg mask z, xmmreg	AVX512VL
VMOVUPD	ymmreg mask z, ymmreg	AVX512VL
VMOVUPD	zmmreg mask z, zmmreg	AVX512
VMOVUPD	mem128 mask, xmmreg	AVX512VL

VMOVUPD	mem256	mask, ymmreg	AVX512VL
VMOVUPD	mem512	mask, zmmreg	AVX512
VMOVUPS	xmmreg	mask z, xmmrmm128	AVX512VL
VMOVUPS	ymmreg	mask z, ymmrmm256	AVX512VL
VMOVUPS	zmmreg	mask z, zmmrmm512	AVX512
VMOVUPS	xmmreg	mask z, xmmreg	AVX512VL
VMOVUPS	ymmreg	mask z, ymmreg	AVX512VL
VMOVUPS	zmmreg	mask z, zmmreg	AVX512
VMOVUPS	mem128	mask, xmmreg	AVX512VL
VMOVUPS	mem256	mask, ymmreg	AVX512VL
VMOVUPS	mem512	mask, zmmreg	AVX512
VMULPD	xmmreg	mask z, xmmreg*, xmmrmm128	b64 AVX512VL
VMULPD	ymmreg	mask z, ymmreg*, ymmrmm256	b64 AVX512VL
VMULPD	zmmreg	mask z, zmmreg*, zmmrmm512	b64 er AVX512
VMULPS	xmmreg	mask z, xmmreg*, xmmrmm128	b32 AVX512VL
VMULPS	ymmreg	mask z, ymmreg*, ymmrmm256	b32 AVX512VL
VMULPS	zmmreg	mask z, zmmreg*, zmmrmm512	b32 er AVX512
VMULSD	xmmreg	mask z, xmmreg*, xmmrmm64	er AVX512
VMULSS	xmmreg	mask z, xmmreg*, xmmrmm32	er AVX512
VORPD	xmmreg	mask z, xmmreg*, xmmrmm128	b64 AVX512VL/DQ
VORPD	ymmreg	mask z, ymmreg*, ymmrmm256	b64 AVX512VL/DQ
VORPD	zmmreg	mask z, zmmreg*, zmmrmm512	b64 AVX512DQ
VORPS	xmmreg	mask z, xmmreg*, xmmrmm128	b32 AVX512VL/DQ
VORPS	ymmreg	mask z, ymmreg*, ymmrmm256	b32 AVX512VL/DQ
VORPS	zmmreg	mask z, zmmreg*, zmmrmm512	b32 AVX512DQ
VPABSB	xmmreg	mask z, xmmrmm128	AVX512VL/BW
VPABSB	ymmreg	mask z, ymmrmm256	AVX512VL/BW
VPABSB	zmmreg	mask z, zmmrmm512	AVX512BW
VPABSD	xmmreg	mask z, xmmrmm128	b32 AVX512VL
VPABSD	ymmreg	mask z, ymmrmm256	b32 AVX512VL
VPABSD	zmmreg	mask z, zmmrmm512	b32 AVX512
VPABSQ	xmmreg	mask z, xmmrmm128	b64 AVX512VL
VPABSQ	ymmreg	mask z, ymmrmm256	b64 AVX512VL
VPABSQ	zmmreg	mask z, zmmrmm512	b64 AVX512
VPABSW	xmmreg	mask z, xmmrmm128	AVX512VL/BW
VPABSW	ymmreg	mask z, ymmrmm256	AVX512VL/BW
VPABSW	zmmreg	mask z, zmmrmm512	AVX512BW
VPACKSSDW	xmmreg	mask z, xmmreg*, xmmrmm128	b32 AVX512VL/BW
VPACKSSDW	ymmreg	mask z, ymmreg*, ymmrmm256	b32 AVX512VL/BW
VPACKSSDW	zmmreg	mask z, zmmreg*, zmmrmm512	b32 AVX512BW
VPACKSSWB	xmmreg	mask z, xmmreg*, xmmrmm128	AVX512VL/BW
VPACKSSWB	ymmreg	mask z, ymmreg*, ymmrmm256	AVX512VL/BW
VPACKSSWB	zmmreg	mask z, zmmreg*, zmmrmm512	AVX512BW
VPACKUSDW	xmmreg	mask z, xmmreg*, xmmrmm128	b32 AVX512VL/BW
VPACKUSDW	ymmreg	mask z, ymmreg*, ymmrmm256	b32 AVX512VL/BW
VPACKUSDW	zmmreg	mask z, zmmreg*, zmmrmm512	b32 AVX512BW
VPACKUSWB	xmmreg	mask z, xmmreg*, xmmrmm128	AVX512VL/BW
VPACKUSWB	ymmreg	mask z, ymmreg*, ymmrmm256	AVX512VL/BW
VPACKUSWB	zmmreg	mask z, zmmreg*, zmmrmm512	AVX512BW
VPADDB	xmmreg	mask z, xmmreg*, xmmrmm128	AVX512VL/BW
VPADDB	ymmreg	mask z, ymmreg*, ymmrmm256	AVX512VL/BW
VPADDB	zmmreg	mask z, zmmreg*, zmmrmm512	AVX512BW
VPADDD	xmmreg	mask z, xmmreg*, xmmrmm128	b32 AVX512VL
VPADDD	ymmreg	mask z, ymmreg*, ymmrmm256	b32 AVX512VL

VPADD	zmmreg	mask	z, zmmreg*, zmmrm512	b32 AVX512
VPADDQ	xmmreg	mask	z, xmmreg*, xmmrm128	b64 AVX512VL
VPADDQ	ymmreg	mask	z, ymmreg*, ymmrm256	b64 AVX512VL
VPADDQ	zmmreg	mask	z, zmmreg*, zmmrm512	b64 AVX512
VPADDSB	xmmreg	mask	z, xmmreg*, xmmrm128	AVX512VL/BW
VPADDSB	ymmreg	mask	z, ymmreg*, ymmrm256	AVX512VL/BW
VPADDSB	zmmreg	mask	z, zmmreg*, zmmrm512	AVX512BW
VPADDSW	xmmreg	mask	z, xmmreg*, xmmrm128	AVX512VL/BW
VPADDSW	ymmreg	mask	z, ymmreg*, ymmrm256	AVX512VL/BW
VPADDSW	zmmreg	mask	z, zmmreg*, zmmrm512	AVX512BW
VPADDUSB	xmmreg	mask	z, xmmreg*, xmmrm128	AVX512VL/BW
VPADDUSB	ymmreg	mask	z, ymmreg*, ymmrm256	AVX512VL/BW
VPADDUSB	zmmreg	mask	z, zmmreg*, zmmrm512	AVX512BW
VPADDUSW	xmmreg	mask	z, xmmreg*, xmmrm128	AVX512VL/BW
VPADDUSW	ymmreg	mask	z, ymmreg*, ymmrm256	AVX512VL/BW
VPADDUSW	zmmreg	mask	z, zmmreg*, zmmrm512	AVX512BW
VPADDW	xmmreg	mask	z, xmmreg*, xmmrm128	AVX512VL/BW
VPADDW	ymmreg	mask	z, ymmreg*, ymmrm256	AVX512VL/BW
VPADDW	zmmreg	mask	z, zmmreg*, zmmrm512	AVX512BW
VPALIGNR	xmmreg	mask	z, xmmreg*, xmmrm128, imm8	AVX512VL/BW
VPALIGNR	ymmreg	mask	z, ymmreg*, ymmrm256, imm8	AVX512VL/BW
VPALIGNR	zmmreg	mask	z, zmmreg*, zmmrm512, imm8	AVX512BW
VPAND	xmmreg	mask	z, xmmreg*, xmmrm128	b32 AVX512VL
VPAND	ymmreg	mask	z, ymmreg*, ymmrm256	b32 AVX512VL
VPAND	zmmreg	mask	z, zmmreg*, zmmrm512	b32 AVX512
VPANDND	xmmreg	mask	z, xmmreg*, xmmrm128	b32 AVX512VL
VPANDND	ymmreg	mask	z, ymmreg*, ymmrm256	b32 AVX512VL
VPANDND	zmmreg	mask	z, zmmreg*, zmmrm512	b32 AVX512
VPANDNQ	xmmreg	mask	z, xmmreg*, xmmrm128	b64 AVX512VL
VPANDNQ	ymmreg	mask	z, ymmreg*, ymmrm256	b64 AVX512VL
VPANDNQ	zmmreg	mask	z, zmmreg*, zmmrm512	b64 AVX512
VPANDQ	xmmreg	mask	z, xmmreg*, xmmrm128	b64 AVX512VL
VPANDQ	ymmreg	mask	z, ymmreg*, ymmrm256	b64 AVX512VL
VPANDQ	zmmreg	mask	z, zmmreg*, zmmrm512	b64 AVX512
VPAVGB	xmmreg	mask	z, xmmreg*, xmmrm128	AVX512VL/BW
VPAVGB	ymmreg	mask	z, ymmreg*, ymmrm256	AVX512VL/BW
VPAVGB	zmmreg	mask	z, zmmreg*, zmmrm512	AVX512BW
VPAVGW	xmmreg	mask	z, xmmreg*, xmmrm128	AVX512VL/BW
VPAVGW	ymmreg	mask	z, ymmreg*, ymmrm256	AVX512VL/BW
VPAVGW	zmmreg	mask	z, zmmreg*, zmmrm512	AVX512BW
VPBLENDMB	xmmreg	mask	z, xmmreg*, xmmrm128	AVX512VL/BW
VPBLENDMB	ymmreg	mask	z, ymmreg*, ymmrm256	AVX512VL/BW
VPBLENDMB	zmmreg	mask	z, zmmreg*, zmmrm512	AVX512BW
VPBLENDMD	xmmreg	mask	z, xmmreg*, xmmrm128	b32 AVX512VL
VPBLENDMD	ymmreg	mask	z, ymmreg*, ymmrm256	b32 AVX512VL
VPBLENDMD	zmmreg	mask	z, zmmreg*, zmmrm512	b32 AVX512
VPBLENDMQ	xmmreg	mask	z, xmmreg*, xmmrm128	b64 AVX512VL
VPBLENDMQ	ymmreg	mask	z, ymmreg*, ymmrm256	b64 AVX512VL
VPBLENDMQ	zmmreg	mask	z, zmmreg*, zmmrm512	b64 AVX512
VPBLENDMW	xmmreg	mask	z, xmmreg*, xmmrm128	AVX512VL/BW
VPBLENDMW	ymmreg	mask	z, ymmreg*, ymmrm256	AVX512VL/BW
VPBLENDMW	zmmreg	mask	z, zmmreg*, zmmrm512	AVX512BW
VPBROADCASTB	xmmreg	mask	z, xmmrm8	AVX512VL/BW
VPBROADCASTB	ymmreg	mask	z, xmmrm8	AVX512VL/BW

VPBROADCASTB	zmmreg	mask	z, xmmrm8	AVX512BW
VPBROADCASTB	xmmreg	mask	z, reg8	AVX512VL/BW
VPBROADCASTB	xmmreg	mask	z, reg16	AVX512VL/BW
VPBROADCASTB	xmmreg	mask	z, reg32	AVX512VL/BW
VPBROADCASTB	xmmreg	mask	z, reg64	AVX512VL/BW
VPBROADCASTB	ymmreg	mask	z, reg8	AVX512VL/BW
VPBROADCASTB	ymmreg	mask	z, reg16	AVX512VL/BW
VPBROADCASTB	ymmreg	mask	z, reg32	AVX512VL/BW
VPBROADCASTB	ymmreg	mask	z, reg64	AVX512VL/BW
VPBROADCASTB	zmmreg	mask	z, reg8	AVX512BW
VPBROADCASTB	zmmreg	mask	z, reg16	AVX512BW
VPBROADCASTB	zmmreg	mask	z, reg32	AVX512BW
VPBROADCASTB	zmmreg	mask	z, reg64	AVX512BW
VPBROADCASTD	xmmreg	mask	z, mem32	AVX512VL
VPBROADCASTD	ymmreg	mask	z, mem32	AVX512VL
VPBROADCASTD	zmmreg	mask	z, mem32	AVX512
VPBROADCASTD	xmmreg	mask	z, xmmreg	AVX512VL
VPBROADCASTD	ymmreg	mask	z, xmmreg	AVX512VL
VPBROADCASTD	zmmreg	mask	z, xmmreg	AVX512
VPBROADCASTD	xmmreg	mask	z, reg32	AVX512VL
VPBROADCASTD	ymmreg	mask	z, reg32	AVX512VL
VPBROADCASTD	zmmreg	mask	z, reg32	AVX512
VPBROADCASTMB2Q	xmmreg, kreg			AVX512VL/CD
VPBROADCASTMB2Q	ymmreg, kreg			AVX512VL/CD
VPBROADCASTMB2Q	zmmreg, kreg			AVX512CD
VPBROADCASTMW2D	xmmreg, kreg			AVX512VL/CD
VPBROADCASTMW2D	ymmreg, kreg			AVX512VL/CD
VPBROADCASTMW2D	zmmreg, kreg			AVX512CD
VPBROADCASTQ	xmmreg	mask	z, mem64	AVX512VL
VPBROADCASTQ	ymmreg	mask	z, mem64	AVX512VL
VPBROADCASTQ	zmmreg	mask	z, mem64	AVX512
VPBROADCASTQ	xmmreg	mask	z, xmmreg	AVX512VL
VPBROADCASTQ	ymmreg	mask	z, xmmreg	AVX512VL
VPBROADCASTQ	zmmreg	mask	z, xmmreg	AVX512
VPBROADCASTQ	xmmreg	mask	z, reg64	AVX512VL
VPBROADCASTQ	ymmreg	mask	z, reg64	AVX512VL
VPBROADCASTQ	zmmreg	mask	z, reg64	AVX512
VPBROADCASTW	xmmreg	mask	z, xmmrm16	AVX512VL/BW
VPBROADCASTW	ymmreg	mask	z, xmmrm16	AVX512VL/BW
VPBROADCASTW	zmmreg	mask	z, xmmrm16	AVX512BW
VPBROADCASTW	xmmreg	mask	z, reg16	AVX512VL/BW
VPBROADCASTW	xmmreg	mask	z, reg32	AVX512VL/BW
VPBROADCASTW	xmmreg	mask	z, reg64	AVX512VL/BW
VPBROADCASTW	ymmreg	mask	z, reg16	AVX512VL/BW
VPBROADCASTW	ymmreg	mask	z, reg32	AVX512VL/BW
VPBROADCASTW	ymmreg	mask	z, reg64	AVX512VL/BW
VPBROADCASTW	zmmreg	mask	z, reg16	AVX512BW
VPBROADCASTW	zmmreg	mask	z, reg32	AVX512BW
VPBROADCASTW	zmmreg	mask	z, reg64	AVX512BW
VPCMPB	kreg	mask, xmmreg, xmmrm128, imm8		AVX512VL/BW
VPCMPB	kreg	mask, ymmreg, ymmrm256, imm8		AVX512VL/BW
VPCMPB	kreg	mask, zmmreg, zmmrm512, imm8		AVX512BW
VPCMPD	kreg	mask, xmmreg, xmmrm128, b32, imm8		AVX512VL
VPCMPD	kreg	mask, ymmreg, ymmrm256, b32, imm8		AVX512VL

VPCMPD	kreg	mask, zmmreg, zmmrm512	b32, imm8 AVX512
VPCMPEQB	kreg	mask, xmmreg, xmmrm128	AVX512VL/BW
VPCMPEQB	kreg	mask, ymmreg, ymmrm256	AVX512VL/BW
VPCMPEQB	kreg	mask, zmmreg, zmmrm512	AVX512BW
VPCMPEQD	kreg	mask, xmmreg, xmmrm128	b32 AVX512VL
VPCMPEQD	kreg	mask, ymmreg, ymmrm256	b32 AVX512VL
VPCMPEQD	kreg	mask, zmmreg, zmmrm512	b32 AVX512
VPCMPEQQ	kreg	mask, xmmreg, xmmrm128	b64 AVX512VL
VPCMPEQQ	kreg	mask, ymmreg, ymmrm256	b64 AVX512VL
VPCMPEQQ	kreg	mask, zmmreg, zmmrm512	b64 AVX512
VPCMPEQW	kreg	mask, xmmreg, xmmrm128	AVX512VL/BW
VPCMPEQW	kreg	mask, ymmreg, ymmrm256	AVX512VL/BW
VPCMPEQW	kreg	mask, zmmreg, zmmrm512	AVX512BW
VPCMPGTB	kreg	mask, xmmreg, xmmrm128	AVX512VL/BW
VPCMPGTB	kreg	mask, ymmreg, ymmrm256	AVX512VL/BW
VPCMPGTB	kreg	mask, zmmreg, zmmrm512	AVX512BW
VPCMPGTD	kreg	mask, xmmreg, xmmrm128	b32 AVX512VL
VPCMPGTD	kreg	mask, ymmreg, ymmrm256	b32 AVX512VL
VPCMPGTD	kreg	mask, zmmreg, zmmrm512	b32 AVX512
VPCMPGTQ	kreg	mask, xmmreg, xmmrm128	b64 AVX512VL
VPCMPGTQ	kreg	mask, ymmreg, ymmrm256	b64 AVX512VL
VPCMPGTQ	kreg	mask, zmmreg, zmmrm512	b64 AVX512
VPCMPGTW	kreg	mask, xmmreg, xmmrm128	AVX512VL/BW
VPCMPGTW	kreg	mask, ymmreg, ymmrm256	AVX512VL/BW
VPCMPGTW	kreg	mask, zmmreg, zmmrm512	AVX512BW
VPCMPQ	kreg	mask, xmmreg, xmmrm128	b64, imm8 AVX512VL
VPCMPQ	kreg	mask, ymmreg, ymmrm256	b64, imm8 AVX512VL
VPCMPQ	kreg	mask, zmmreg, zmmrm512	b64, imm8 AVX512
VPCMPUB	kreg	mask, xmmreg, xmmrm128, imm8	AVX512VL/BW
VPCMPUB	kreg	mask, ymmreg, ymmrm256, imm8	AVX512VL/BW
VPCMPUB	kreg	mask, zmmreg, zmmrm512, imm8	AVX512BW
VPCMPUD	kreg	mask, xmmreg, xmmrm128	b32, imm8 AVX512VL
VPCMPUD	kreg	mask, ymmreg, ymmrm256	b32, imm8 AVX512VL
VPCMPUD	kreg	mask, zmmreg, zmmrm512	b32, imm8 AVX512
VPCMPUQ	kreg	mask, xmmreg, xmmrm128	b64, imm8 AVX512VL
VPCMPUQ	kreg	mask, ymmreg, ymmrm256	b64, imm8 AVX512VL
VPCMPUQ	kreg	mask, zmmreg, zmmrm512	b64, imm8 AVX512
VPCMPUW	kreg	mask, xmmreg, xmmrm128, imm8	AVX512VL/BW
VPCMPUW	kreg	mask, ymmreg, ymmrm256, imm8	AVX512VL/BW
VPCMPUW	kreg	mask, zmmreg, zmmrm512, imm8	AVX512BW
VPCMPW	kreg	mask, xmmreg, xmmrm128, imm8	AVX512VL/BW
VPCMPW	kreg	mask, ymmreg, ymmrm256, imm8	AVX512VL/BW
VPCMPW	kreg	mask, zmmreg, zmmrm512, imm8	AVX512BW
VPCOMPRESSD	mem128	mask, xmmreg	AVX512VL
VPCOMPRESSD	mem256	mask, ymmreg	AVX512VL
VPCOMPRESSD	mem512	mask, zmmreg	AVX512
VPCOMPRESSD	xmmreg	mask z, xmmreg	AVX512VL
VPCOMPRESSD	ymmreg	mask z, ymmreg	AVX512VL
VPCOMPRESSD	zmmreg	mask z, zmmreg	AVX512
VPCOMPRESSQ	mem128	mask, xmmreg	AVX512VL
VPCOMPRESSQ	mem256	mask, ymmreg	AVX512VL
VPCOMPRESSQ	mem512	mask, zmmreg	AVX512
VPCOMPRESSQ	xmmreg	mask z, xmmreg	AVX512VL
VPCOMPRESSQ	ymmreg	mask z, ymmreg	AVX512VL

VPCOMPRESSQ	zmmreg	mask	z, zmmreg	AVX512
VPCONFLICTD	xmmreg	mask	z, xmmrmm128	b32 AVX512VL/CD
VPCONFLICTD	ymmreg	mask	z, ymmrmm256	b32 AVX512VL/CD
VPCONFLICTD	zmmreg	mask	z, zmmrmm512	b32 AVX512CD
VPCONFLICTQ	xmmreg	mask	z, xmmrmm128	b64 AVX512VL/CD
VPCONFLICTQ	ymmreg	mask	z, ymmrmm256	b64 AVX512VL/CD
VPCONFLICTQ	zmmreg	mask	z, zmmrmm512	b64 AVX512CD
VPERMB	xmmreg	mask	z, xmmreg*, xmmrmm128	AVX512VL/VBMI
VPERMB	ymmreg	mask	z, ymmreg*, ymmrmm256	AVX512VL/VBMI
VPERMB	zmmreg	mask	z, zmmreg*, zmmrmm512	AVX512VBMI
VPERMD	ymmreg	mask	z, ymmreg*, ymmrmm256	b32 AVX512VL
VPERMD	zmmreg	mask	z, zmmreg*, zmmrmm512	b32 AVX512
VPERMI2B	xmmreg	mask	z, xmmreg, xmmrmm128	AVX512VL/VBMI
VPERMI2B	ymmreg	mask	z, ymmreg, ymmrmm256	AVX512VL/VBMI
VPERMI2B	zmmreg	mask	z, zmmreg, zmmrmm512	AVX512VBMI
VPERMI2D	xmmreg	mask	z, xmmreg, xmmrmm128	b32 AVX512VL
VPERMI2D	ymmreg	mask	z, ymmreg, ymmrmm256	b32 AVX512VL
VPERMI2D	zmmreg	mask	z, zmmreg, zmmrmm512	b32 AVX512
VPERMI2PD	xmmreg	mask	z, xmmreg, xmmrmm128	b64 AVX512VL
VPERMI2PD	ymmreg	mask	z, ymmreg, ymmrmm256	b64 AVX512VL
VPERMI2PD	zmmreg	mask	z, zmmreg, zmmrmm512	b64 AVX512
VPERMI2PS	xmmreg	mask	z, xmmreg, xmmrmm128	b32 AVX512VL
VPERMI2PS	ymmreg	mask	z, ymmreg, ymmrmm256	b32 AVX512VL
VPERMI2PS	zmmreg	mask	z, zmmreg, zmmrmm512	b32 AVX512
VPERMI2Q	xmmreg	mask	z, xmmreg, xmmrmm128	b64 AVX512VL
VPERMI2Q	ymmreg	mask	z, ymmreg, ymmrmm256	b64 AVX512VL
VPERMI2Q	zmmreg	mask	z, zmmreg, zmmrmm512	b64 AVX512
VPERMI2W	xmmreg	mask	z, xmmreg, xmmrmm128	AVX512VL/BW
VPERMI2W	ymmreg	mask	z, ymmreg, ymmrmm256	AVX512VL/BW
VPERMI2W	zmmreg	mask	z, zmmreg, zmmrmm512	AVX512BW
VPERMILPD	xmmreg	mask	z, xmmrmm128	b64, imm8 AVX512VL
VPERMILPD	ymmreg	mask	z, ymmrmm256	b64, imm8 AVX512VL
VPERMILPD	zmmreg	mask	z, zmmrmm512	b64, imm8 AVX512
VPERMILPD	xmmreg	mask	z, xmmreg*, xmmrmm128	b64 AVX512VL
VPERMILPD	ymmreg	mask	z, ymmreg*, ymmrmm256	b64 AVX512VL
VPERMILPD	zmmreg	mask	z, zmmreg*, zmmrmm512	b64 AVX512
VPERMILPS	xmmreg	mask	z, xmmrmm128	b32, imm8 AVX512VL
VPERMILPS	ymmreg	mask	z, ymmrmm256	b32, imm8 AVX512VL
VPERMILPS	zmmreg	mask	z, zmmrmm512	b32, imm8 AVX512
VPERMILPS	xmmreg	mask	z, xmmreg*, xmmrmm128	b32 AVX512VL
VPERMILPS	ymmreg	mask	z, ymmreg*, ymmrmm256	b32 AVX512VL
VPERMILPS	zmmreg	mask	z, zmmreg*, zmmrmm512	b32 AVX512
VPERMPD	ymmreg	mask	z, ymmrmm256	b64, imm8 AVX512VL
VPERMPD	zmmreg	mask	z, zmmrmm512	b64, imm8 AVX512
VPERMPD	ymmreg	mask	z, ymmreg*, ymmrmm256	b64 AVX512VL
VPERMPD	zmmreg	mask	z, zmmreg*, zmmrmm512	b64 AVX512
VPERMPS	ymmreg	mask	z, ymmreg*, ymmrmm256	b32 AVX512VL
VPERMPS	zmmreg	mask	z, zmmreg*, zmmrmm512	b32 AVX512
VPERMQ	ymmreg	mask	z, ymmrmm256	b64, imm8 AVX512VL
VPERMQ	zmmreg	mask	z, zmmrmm512	b64, imm8 AVX512
VPERMQ	ymmreg	mask	z, ymmreg*, ymmrmm256	b64 AVX512VL
VPERMQ	zmmreg	mask	z, zmmreg*, zmmrmm512	b64 AVX512
VPERMT2B	xmmreg	mask	z, xmmreg, xmmrmm128	AVX512VL/VBMI
VPERMT2B	ymmreg	mask	z, ymmreg, ymmrmm256	AVX512VL/VBMI

VPERMT2B	zmmreg	mask	z, zmmreg, zmmrm512	AVX512VBMI
VPERMT2D	xmmreg	mask	z, xmmreg, xmmrm128	b32 AVX512VL
VPERMT2D	ymmreg	mask	z, ymmreg, ymmrm256	b32 AVX512VL
VPERMT2D	zmmreg	mask	z, zmmreg, zmmrm512	b32 AVX512
VPERMT2PD	xmmreg	mask	z, xmmreg, xmmrm128	b64 AVX512VL
VPERMT2PD	ymmreg	mask	z, ymmreg, ymmrm256	b64 AVX512VL
VPERMT2PD	zmmreg	mask	z, zmmreg, zmmrm512	b64 AVX512
VPERMT2PS	xmmreg	mask	z, xmmreg, xmmrm128	b32 AVX512VL
VPERMT2PS	ymmreg	mask	z, ymmreg, ymmrm256	b32 AVX512VL
VPERMT2PS	zmmreg	mask	z, zmmreg, zmmrm512	b32 AVX512
VPERMT2Q	xmmreg	mask	z, xmmreg, xmmrm128	b64 AVX512VL
VPERMT2Q	ymmreg	mask	z, ymmreg, ymmrm256	b64 AVX512VL
VPERMT2Q	zmmreg	mask	z, zmmreg, zmmrm512	b64 AVX512
VPERMT2W	xmmreg	mask	z, xmmreg, xmmrm128	AVX512VL/BW
VPERMT2W	ymmreg	mask	z, ymmreg, ymmrm256	AVX512VL/BW
VPERMT2W	zmmreg	mask	z, zmmreg, zmmrm512	AVX512BW
VPERMW	xmmreg	mask	z, xmmreg*, xmmrm128	AVX512VL/BW
VPERMW	ymmreg	mask	z, ymmreg*, ymmrm256	AVX512VL/BW
VPERMW	zmmreg	mask	z, zmmreg*, zmmrm512	AVX512BW
VPEXPANDD	xmmreg	mask	z, mem128	AVX512VL
VPEXPANDD	ymmreg	mask	z, mem256	AVX512VL
VPEXPANDD	zmmreg	mask	z, mem512	AVX512
VPEXPANDD	xmmreg	mask	z, xmmreg	AVX512VL
VPEXPANDD	ymmreg	mask	z, ymmreg	AVX512VL
VPEXPANDD	zmmreg	mask	z, zmmreg	AVX512
VPEXPANDQ	xmmreg	mask	z, mem128	AVX512VL
VPEXPANDQ	ymmreg	mask	z, mem256	AVX512VL
VPEXPANDQ	zmmreg	mask	z, mem512	AVX512
VPEXPANDQ	xmmreg	mask	z, xmmreg	AVX512VL
VPEXPANDQ	ymmreg	mask	z, ymmreg	AVX512VL
VPEXPANDQ	zmmreg	mask	z, zmmreg	AVX512
VPEXTRB	reg8, xmmreg, imm8			AVX512BW
VPEXTRB	reg16, xmmreg, imm8			AVX512BW
VPEXTRB	reg32, xmmreg, imm8			AVX512BW
VPEXTRB	reg64, xmmreg, imm8			AVX512BW
VPEXTRB	mem8, xmmreg, imm8			AVX512BW
VPEXTRD	rm32, xmmreg, imm8			AVX512DQ
VPEXTRQ	rm64, xmmreg, imm8			AVX512DQ
VPEXTRW	reg16, xmmreg, imm8			AVX512BW
VPEXTRW	reg32, xmmreg, imm8			AVX512BW
VPEXTRW	reg64, xmmreg, imm8			AVX512BW
VPEXTRW	mem16, xmmreg, imm8			AVX512BW
VPEXTRW	reg16, xmmreg, imm8			AVX512BW
VPEXTRW	reg32, xmmreg, imm8			AVX512BW
VPEXTRW	reg64, xmmreg, imm8			AVX512BW
VPGATHERDD	xmmreg	mask, xmem32		AVX512VL
VPGATHERDD	ymmreg	mask, ymem32		AVX512VL
VPGATHERDD	zmmreg	mask, zmem32		AVX512
VPGATHERDQ	xmmreg	mask, xmem64		AVX512VL
VPGATHERDQ	ymmreg	mask, ymem64		AVX512VL
VPGATHERDQ	zmmreg	mask, ymem64		AVX512
VPGATHERQD	xmmreg	mask, xmem32		AVX512VL
VPGATHERQD	xmmreg	mask, ymem32		AVX512VL
VPGATHERQD	ymmreg	mask, zmem32		AVX512

VPGATHERQQ	xmmreg	mask, xmem64	AVX512VL
VPGATHERQQ	ymmreg	mask, ymem64	AVX512VL
VPGATHERQQ	zmmreg	mask, zmem64	AVX512
VPINSRB	xmmreg, xmmreg*	reg32, imm8	AVX512BW
VPINSRB	xmmreg, xmmreg*	mem8, imm8	AVX512BW
VPINSRD	xmmreg, xmmreg*	rm32, imm8	AVX512DQ
VPINSRQ	xmmreg, xmmreg*	rm64, imm8	AVX512DQ
VPINSRW	xmmreg, xmmreg*	reg32, imm8	AVX512BW
VPINSRW	xmmreg, xmmreg*	mem16, imm8	AVX512BW
VPLZCNTD	xmmreg	mask z, xmmrmm128	b32 AVX512VL/CD
VPLZCNTD	ymmreg	mask z, ymmrmm256	b32 AVX512VL/CD
VPLZCNTD	zmmreg	mask z, zmmrmm512	b32 AVX512CD
VPLZCNTQ	xmmreg	mask z, xmmrmm128	b64 AVX512VL/CD
VPLZCNTQ	ymmreg	mask z, ymmrmm256	b64 AVX512VL/CD
VPLZCNTQ	zmmreg	mask z, zmmrmm512	b64 AVX512CD
VPMADD52HUQ	xmmreg	mask z, xmmreg, xmmrmm128	b64 AVX512VL/IFMA
VPMADD52HUQ	ymmreg	mask z, ymmreg, ymmrmm256	b64 AVX512VL/IFMA
VPMADD52HUQ	zmmreg	mask z, zmmreg, zmmrmm512	b64 AVX512IFMA
VPMADD52LUQ	xmmreg	mask z, xmmreg, xmmrmm128	b64 AVX512VL/IFMA
VPMADD52LUQ	ymmreg	mask z, ymmreg, ymmrmm256	b64 AVX512VL/IFMA
VPMADD52LUQ	zmmreg	mask z, zmmreg, zmmrmm512	b64 AVX512IFMA
VPMADDUBSW	xmmreg	mask z, xmmreg*, xmmrmm128	AVX512VL/BW
VPMADDUBSW	ymmreg	mask z, ymmreg*, ymmrmm256	AVX512VL/BW
VPMADDUBSW	zmmreg	mask z, zmmreg*, zmmrmm512	AVX512BW
VPMADDWD	xmmreg	mask z, xmmreg*, xmmrmm128	AVX512VL/BW
VPMADDWD	ymmreg	mask z, ymmreg*, ymmrmm256	AVX512VL/BW
VPMADDWD	zmmreg	mask z, zmmreg*, zmmrmm512	AVX512BW
VPMAXSB	xmmreg	mask z, xmmreg*, xmmrmm128	AVX512VL/BW
VPMAXSB	ymmreg	mask z, ymmreg*, ymmrmm256	AVX512VL/BW
VPMAXSB	zmmreg	mask z, zmmreg*, zmmrmm512	AVX512BW
VPMAXSD	xmmreg	mask z, xmmreg*, xmmrmm128	b32 AVX512VL
VPMAXSD	ymmreg	mask z, ymmreg*, ymmrmm256	b32 AVX512VL
VPMAXSD	zmmreg	mask z, zmmreg*, zmmrmm512	b32 AVX512
VPMAXSQ	xmmreg	mask z, xmmreg*, xmmrmm128	b64 AVX512VL
VPMAXSQ	ymmreg	mask z, ymmreg*, ymmrmm256	b64 AVX512VL
VPMAXSQ	zmmreg	mask z, zmmreg*, zmmrmm512	b64 AVX512
VPMAXSW	xmmreg	mask z, xmmreg*, xmmrmm128	AVX512VL/BW
VPMAXSW	ymmreg	mask z, ymmreg*, ymmrmm256	AVX512VL/BW
VPMAXSW	zmmreg	mask z, zmmreg*, zmmrmm512	AVX512BW
VPMAXUB	xmmreg	mask z, xmmreg*, xmmrmm128	AVX512VL/BW
VPMAXUB	ymmreg	mask z, ymmreg*, ymmrmm256	AVX512VL/BW
VPMAXUB	zmmreg	mask z, zmmreg*, zmmrmm512	AVX512BW
VPMAXUD	xmmreg	mask z, xmmreg*, xmmrmm128	b32 AVX512VL
VPMAXUD	ymmreg	mask z, ymmreg*, ymmrmm256	b32 AVX512VL
VPMAXUD	zmmreg	mask z, zmmreg*, zmmrmm512	b32 AVX512
VPMAXUQ	xmmreg	mask z, xmmreg*, xmmrmm128	b64 AVX512VL
VPMAXUQ	ymmreg	mask z, ymmreg*, ymmrmm256	b64 AVX512VL
VPMAXUQ	zmmreg	mask z, zmmreg*, zmmrmm512	b64 AVX512
VPMAXUW	xmmreg	mask z, xmmreg*, xmmrmm128	AVX512VL/BW
VPMAXUW	ymmreg	mask z, ymmreg*, ymmrmm256	AVX512VL/BW
VPMAXUW	zmmreg	mask z, zmmreg*, zmmrmm512	AVX512BW
VPMINSB	xmmreg	mask z, xmmreg*, xmmrmm128	AVX512VL/BW
VPMINSB	ymmreg	mask z, ymmreg*, ymmrmm256	AVX512VL/BW
VPMINSB	zmmreg	mask z, zmmreg*, zmmrmm512	AVX512BW

VPMINS	xmmreg	mask	z, xmmreg*, xmmrm128	b32 AVX512VL
VPMINS	ymmreg	mask	z, ymmreg*, ymmrm256	b32 AVX512VL
VPMINS	zmmreg	mask	z, zmmreg*, zmmrm512	b32 AVX512
VPMINSQ	xmmreg	mask	z, xmmreg*, xmmrm128	b64 AVX512VL
VPMINSQ	ymmreg	mask	z, ymmreg*, ymmrm256	b64 AVX512VL
VPMINSQ	zmmreg	mask	z, zmmreg*, zmmrm512	b64 AVX512
VPMINSW	xmmreg	mask	z, xmmreg*, xmmrm128	AVX512VL/BW
VPMINSW	ymmreg	mask	z, ymmreg*, ymmrm256	AVX512VL/BW
VPMINSW	zmmreg	mask	z, zmmreg*, zmmrm512	AVX512BW
VPMINUB	xmmreg	mask	z, xmmreg*, xmmrm128	AVX512VL/BW
VPMINUB	ymmreg	mask	z, ymmreg*, ymmrm256	AVX512VL/BW
VPMINUB	zmmreg	mask	z, zmmreg*, zmmrm512	AVX512BW
VPMINUD	xmmreg	mask	z, xmmreg*, xmmrm128	b32 AVX512VL
VPMINUD	ymmreg	mask	z, ymmreg*, ymmrm256	b32 AVX512VL
VPMINUD	zmmreg	mask	z, zmmreg*, zmmrm512	b32 AVX512
VPMINUQ	xmmreg	mask	z, xmmreg*, xmmrm128	b64 AVX512VL
VPMINUQ	ymmreg	mask	z, ymmreg*, ymmrm256	b64 AVX512VL
VPMINUQ	zmmreg	mask	z, zmmreg*, zmmrm512	b64 AVX512
VPMINUW	xmmreg	mask	z, xmmreg*, xmmrm128	AVX512VL/BW
VPMINUW	ymmreg	mask	z, ymmreg*, ymmrm256	AVX512VL/BW
VPMINUW	zmmreg	mask	z, zmmreg*, zmmrm512	AVX512BW
VPMOVB2M	kreg, xmmreg			AVX512VL/BW
VPMOVB2M	kreg, ymmreg			AVX512VL/BW
VPMOVB2M	kreg, zmmreg			AVX512BW
VPMOVD2M	kreg, xmmreg			AVX512VL/DQ
VPMOVD2M	kreg, ymmreg			AVX512VL/DQ
VPMOVD2M	kreg, zmmreg			AVX512DQ
VPMOVB	xmmreg	mask	z, xmmreg	AVX512VL
VPMOVB	xmmreg	mask	z, ymmreg	AVX512VL
VPMOVB	xmmreg	mask	z, zmmreg	AVX512
VPMOVB	mem32	mask, xmmreg		AVX512VL
VPMOVB	mem64	mask, ymmreg		AVX512VL
VPMOVB	mem128	mask, zmmreg		AVX512
VPMOVDW	xmmreg	mask	z, xmmreg	AVX512VL
VPMOVDW	xmmreg	mask	z, ymmreg	AVX512VL
VPMOVDW	ymmreg	mask	z, zmmreg	AVX512
VPMOVDW	mem64	mask, xmmreg		AVX512VL
VPMOVDW	mem128	mask, ymmreg		AVX512VL
VPMOVDW	mem256	mask, zmmreg		AVX512
VPMOVM2B	xmmreg, kreg			AVX512VL/BW
VPMOVM2B	ymmreg, kreg			AVX512VL/BW
VPMOVM2B	zmmreg, kreg			AVX512BW
VPMOVM2D	xmmreg, kreg			AVX512VL/DQ
VPMOVM2D	ymmreg, kreg			AVX512VL/DQ
VPMOVM2D	zmmreg, kreg			AVX512DQ
VPMOVM2Q	xmmreg, kreg			AVX512VL/DQ
VPMOVM2Q	ymmreg, kreg			AVX512VL/DQ
VPMOVM2Q	zmmreg, kreg			AVX512DQ
VPMOVM2W	xmmreg, kreg			AVX512VL/BW
VPMOVM2W	ymmreg, kreg			AVX512VL/BW
VPMOVM2W	zmmreg, kreg			AVX512BW
VPMOVQ2M	kreg, xmmreg			AVX512VL/DQ
VPMOVQ2M	kreg, ymmreg			AVX512VL/DQ
VPMOVQ2M	kreg, zmmreg			AVX512DQ

VPMOVQB	xmmreg	mask	z, xmmreg	AVX512VL
VPMOVQB	xmmreg	mask	z, ymmreg	AVX512VL
VPMOVQB	xmmreg	mask	z, zmmreg	AVX512
VPMOVQB	mem16	mask, xmmreg		AVX512VL
VPMOVQB	mem32	mask, ymmreg		AVX512VL
VPMOVQB	mem64	mask, zmmreg		AVX512
VPMOVQD	xmmreg	mask	z, xmmreg	AVX512VL
VPMOVQD	xmmreg	mask	z, ymmreg	AVX512VL
VPMOVQD	ymmreg	mask	z, zmmreg	AVX512
VPMOVQD	mem64	mask, xmmreg		AVX512VL
VPMOVQD	mem128	mask, ymmreg		AVX512VL
VPMOVQD	mem256	mask, zmmreg		AVX512
VPMOVQW	xmmreg	mask	z, xmmreg	AVX512VL
VPMOVQW	xmmreg	mask	z, ymmreg	AVX512VL
VPMOVQW	xmmreg	mask	z, zmmreg	AVX512
VPMOVQW	mem32	mask, xmmreg		AVX512VL
VPMOVQW	mem64	mask, ymmreg		AVX512VL
VPMOVQW	mem128	mask, zmmreg		AVX512
VPMOVSDB	xmmreg	mask	z, xmmreg	AVX512VL
VPMOVSDB	xmmreg	mask	z, ymmreg	AVX512VL
VPMOVSDB	xmmreg	mask	z, zmmreg	AVX512
VPMOVSDB	mem32	mask, xmmreg		AVX512VL
VPMOVSDB	mem64	mask, ymmreg		AVX512VL
VPMOVSDB	mem128	mask, zmmreg		AVX512
VPMOVSDW	xmmreg	mask	z, xmmreg	AVX512VL
VPMOVSDW	xmmreg	mask	z, ymmreg	AVX512VL
VPMOVSDW	ymmreg	mask	z, zmmreg	AVX512
VPMOVSDW	mem64	mask, xmmreg		AVX512VL
VPMOVSDW	mem128	mask, ymmreg		AVX512VL
VPMOVSDW	mem256	mask, zmmreg		AVX512
VPMOVSQB	xmmreg	mask	z, xmmreg	AVX512VL
VPMOVSQB	xmmreg	mask	z, ymmreg	AVX512VL
VPMOVSQB	xmmreg	mask	z, zmmreg	AVX512
VPMOVSQB	mem16	mask, xmmreg		AVX512VL
VPMOVSQB	mem32	mask, ymmreg		AVX512VL
VPMOVSQB	mem64	mask, zmmreg		AVX512
VPMOVSQD	xmmreg	mask	z, xmmreg	AVX512VL
VPMOVSQD	xmmreg	mask	z, ymmreg	AVX512VL
VPMOVSQD	ymmreg	mask	z, zmmreg	AVX512
VPMOVSQD	mem64	mask, xmmreg		AVX512VL
VPMOVSQD	mem128	mask, ymmreg		AVX512VL
VPMOVSQD	mem256	mask, zmmreg		AVX512
VPMOVSQW	xmmreg	mask	z, xmmreg	AVX512VL
VPMOVSQW	xmmreg	mask	z, ymmreg	AVX512VL
VPMOVSQW	xmmreg	mask	z, zmmreg	AVX512
VPMOVSQW	mem32	mask, xmmreg		AVX512VL
VPMOVSQW	mem64	mask, ymmreg		AVX512VL
VPMOVSQW	mem128	mask, zmmreg		AVX512
VPMOVSWB	xmmreg	mask	z, xmmreg	AVX512VL/BW
VPMOVSWB	xmmreg	mask	z, ymmreg	AVX512VL/BW
VPMOVSWB	ymmreg	mask	z, zmmreg	AVX512BW
VPMOVSWB	mem64	mask, xmmreg		AVX512VL/BW
VPMOVSWB	mem128	mask, ymmreg		AVX512VL/BW
VPMOVSWB	mem256	mask, zmmreg		AVX512BW

VPMOVSXBD	xmmreg	mask	z, xmmrmm32	AVX512VL
VPMOVSXBD	ymmreg	mask	z, xmmrmm64	AVX512VL
VPMOVSXBD	zmmreg	mask	z, xmmrmm128	AVX512
VPMOVSXBQ	xmmreg	mask	z, xmmrmm16	AVX512VL
VPMOVSXBQ	ymmreg	mask	z, xmmrmm32	AVX512VL
VPMOVSXBQ	zmmreg	mask	z, xmmrmm64	AVX512
VPMOVSXBW	xmmreg	mask	z, xmmrmm64	AVX512VL/BW
VPMOVSXBW	ymmreg	mask	z, xmmrmm128	AVX512VL/BW
VPMOVSXBW	zmmreg	mask	z, ymmrmm256	AVX512BW
VPMOVSXDQ	xmmreg	mask	z, xmmrmm64	AVX512VL
VPMOVSXDQ	ymmreg	mask	z, xmmrmm128	AVX512VL
VPMOVSXDQ	zmmreg	mask	z, ymmrmm256	AVX512
VPMOVSXWD	xmmreg	mask	z, xmmrmm64	AVX512VL
VPMOVSXWD	ymmreg	mask	z, xmmrmm128	AVX512VL
VPMOVSXWD	zmmreg	mask	z, ymmrmm256	AVX512
VPMOVSXWQ	xmmreg	mask	z, xmmrmm32	AVX512VL
VPMOVSXWQ	ymmreg	mask	z, xmmrmm64	AVX512VL
VPMOVSXWQ	zmmreg	mask	z, xmmrmm128	AVX512
VPMOVUSDB	xmmreg	mask	z, xmmreg	AVX512VL
VPMOVUSDB	xmmreg	mask	z, ymmreg	AVX512VL
VPMOVUSDB	xmmreg	mask	z, zmmreg	AVX512
VPMOVUSDB	mem32	mask, xmmreg		AVX512VL
VPMOVUSDB	mem64	mask, ymmreg		AVX512VL
VPMOVUSDB	mem128	mask, zmmreg		AVX512
VPMOVUSDW	xmmreg	mask	z, xmmreg	AVX512VL
VPMOVUSDW	xmmreg	mask	z, ymmreg	AVX512VL
VPMOVUSDW	ymmreg	mask	z, zmmreg	AVX512
VPMOVUSDW	mem64	mask, xmmreg		AVX512VL
VPMOVUSDW	mem128	mask, ymmreg		AVX512VL
VPMOVUSDW	mem256	mask, zmmreg		AVX512
VPMOVUSQB	xmmreg	mask	z, xmmreg	AVX512VL
VPMOVUSQB	xmmreg	mask	z, ymmreg	AVX512VL
VPMOVUSQB	xmmreg	mask	z, zmmreg	AVX512
VPMOVUSQB	mem16	mask, xmmreg		AVX512VL
VPMOVUSQB	mem32	mask, ymmreg		AVX512VL
VPMOVUSQB	mem64	mask, zmmreg		AVX512
VPMOVUSQD	xmmreg	mask	z, xmmreg	AVX512VL
VPMOVUSQD	xmmreg	mask	z, ymmreg	AVX512VL
VPMOVUSQD	ymmreg	mask	z, zmmreg	AVX512
VPMOVUSQD	mem64	mask, xmmreg		AVX512VL
VPMOVUSQD	mem128	mask, ymmreg		AVX512VL
VPMOVUSQD	mem256	mask, zmmreg		AVX512
VPMOVUSQW	xmmreg	mask	z, xmmreg	AVX512VL
VPMOVUSQW	xmmreg	mask	z, ymmreg	AVX512VL
VPMOVUSQW	xmmreg	mask	z, zmmreg	AVX512
VPMOVUSQW	mem32	mask, xmmreg		AVX512VL
VPMOVUSQW	mem64	mask, ymmreg		AVX512VL
VPMOVUSQW	mem128	mask, zmmreg		AVX512
VPMOVUSWB	xmmreg	mask	z, xmmreg	AVX512VL/BW
VPMOVUSWB	xmmreg	mask	z, ymmreg	AVX512VL/BW
VPMOVUSWB	ymmreg	mask	z, zmmreg	AVX512BW
VPMOVUSWB	mem64	mask, xmmreg		AVX512VL/BW
VPMOVUSWB	mem128	mask, ymmreg		AVX512VL/BW
VPMOVUSWB	mem256	mask, zmmreg		AVX512BW

VPMOVW2M	kreg, xmmreg			AVX512VL/BW
VPMOVW2M	kreg, ymmreg			AVX512VL/BW
VPMOVW2M	kreg, zmmreg			AVX512BW
VPMOVWB	xmmreg	mask	z, xmmreg	AVX512VL/BW
VPMOVWB	xmmreg	mask	z, ymmreg	AVX512VL/BW
VPMOVWB	ymmreg	mask	z, zmmreg	AVX512BW
VPMOVWB	mem64	mask, xmmreg		AVX512VL/BW
VPMOVWB	mem128	mask, ymmreg		AVX512VL/BW
VPMOVWB	mem256	mask, zmmreg		AVX512BW
VPMOVZXBD	xmmreg	mask	z, xmmrmm32	AVX512VL
VPMOVZXBD	ymmreg	mask	z, xmmrmm64	AVX512VL
VPMOVZXBD	zmmreg	mask	z, xmmrmm128	AVX512
VPMOVZXBQ	xmmreg	mask	z, xmmrmm16	AVX512VL
VPMOVZXBQ	ymmreg	mask	z, xmmrmm32	AVX512VL
VPMOVZXBQ	zmmreg	mask	z, xmmrmm64	AVX512
VPMOVZXBW	xmmreg	mask	z, xmmrmm64	AVX512VL/BW
VPMOVZXBW	ymmreg	mask	z, xmmrmm128	AVX512VL/BW
VPMOVZXBW	zmmreg	mask	z, ymmrmm256	AVX512BW
VPMOVZXDQ	xmmreg	mask	z, xmmrmm64	AVX512VL
VPMOVZXDQ	ymmreg	mask	z, xmmrmm128	AVX512VL
VPMOVZXDQ	zmmreg	mask	z, ymmrmm256	AVX512
VPMOVZXWD	xmmreg	mask	z, xmmrmm64	AVX512VL
VPMOVZXWD	ymmreg	mask	z, xmmrmm128	AVX512VL
VPMOVZXWD	zmmreg	mask	z, ymmrmm256	AVX512
VPMOVZXWQ	xmmreg	mask	z, xmmrmm32	AVX512VL
VPMOVZXWQ	ymmreg	mask	z, xmmrmm64	AVX512VL
VPMOVZXWQ	zmmreg	mask	z, xmmrmm128	AVX512
VPMULDQ	xmmreg	mask	z, xmmreg*, xmmrmm128	b64 AVX512VL
VPMULDQ	ymmreg	mask	z, ymmreg*, ymmrmm256	b64 AVX512VL
VPMULDQ	zmmreg	mask	z, zmmreg*, zmmrmm512	b64 AVX512
VPMULHSW	xmmreg	mask	z, xmmreg*, xmmrmm128	AVX512VL/BW
VPMULHSW	ymmreg	mask	z, ymmreg*, ymmrmm256	AVX512VL/BW
VPMULHSW	zmmreg	mask	z, zmmreg*, zmmrmm512	AVX512BW
VPMULHUW	xmmreg	mask	z, xmmreg*, xmmrmm128	AVX512VL/BW
VPMULHUW	ymmreg	mask	z, ymmreg*, ymmrmm256	AVX512VL/BW
VPMULHUW	zmmreg	mask	z, zmmreg*, zmmrmm512	AVX512BW
VPMULHW	xmmreg	mask	z, xmmreg*, xmmrmm128	AVX512VL/BW
VPMULHW	ymmreg	mask	z, ymmreg*, ymmrmm256	AVX512VL/BW
VPMULHW	zmmreg	mask	z, zmmreg*, zmmrmm512	AVX512BW
VPMULLD	xmmreg	mask	z, xmmreg*, xmmrmm128	b32 AVX512VL
VPMULLD	ymmreg	mask	z, ymmreg*, ymmrmm256	b32 AVX512VL
VPMULLD	zmmreg	mask	z, zmmreg*, zmmrmm512	b32 AVX512
VPMULLQ	xmmreg	mask	z, xmmreg*, xmmrmm128	b64 AVX512VL/DQ
VPMULLQ	ymmreg	mask	z, ymmreg*, ymmrmm256	b64 AVX512VL/DQ
VPMULLQ	zmmreg	mask	z, zmmreg*, zmmrmm512	b64 AVX512DQ
VPMULLW	xmmreg	mask	z, xmmreg*, xmmrmm128	AVX512VL/BW
VPMULLW	ymmreg	mask	z, ymmreg*, ymmrmm256	AVX512VL/BW
VPMULLW	zmmreg	mask	z, zmmreg*, zmmrmm512	AVX512BW
VPMULTISHIFTQB	xmmreg	mask	z, xmmreg*, xmmrmm128	b64 AVX512VL/VBMI
VPMULTISHIFTQB	ymmreg	mask	z, ymmreg*, ymmrmm256	b64 AVX512VL/VBMI
VPMULTISHIFTQB	zmmreg	mask	z, zmmreg*, zmmrmm512	b64 AVX512VBMI
VPMULUDQ	xmmreg	mask	z, xmmreg*, xmmrmm128	b64 AVX512VL
VPMULUDQ	ymmreg	mask	z, ymmreg*, ymmrmm256	b64 AVX512VL
VPMULUDQ	zmmreg	mask	z, zmmreg*, zmmrmm512	b64 AVX512

VPORD	xmmreg	mask	z, xmmreg*, xmmrm128	b32 AVX512VL
VPORD	ymmreg	mask	z, ymmreg*, ymmrm256	b32 AVX512VL
VPORD	zmmreg	mask	z, zmmreg*, zmmrm512	b32 AVX512
VPOREQ	xmmreg	mask	z, xmmreg*, xmmrm128	b64 AVX512VL
VPOREQ	ymmreg	mask	z, ymmreg*, ymmrm256	b64 AVX512VL
VPOREQ	zmmreg	mask	z, zmmreg*, zmmrm512	b64 AVX512
VPROLD	xmmreg	mask	z, xmmrm128	b32*, imm8 AVX512VL
VPROLD	ymmreg	mask	z, ymmrm256	b32*, imm8 AVX512VL
VPROLD	zmmreg	mask	z, zmmrm512	b32*, imm8 AVX512
VPROLQ	xmmreg	mask	z, xmmrm128	b64*, imm8 AVX512VL
VPROLQ	ymmreg	mask	z, ymmrm256	b64*, imm8 AVX512VL
VPROLQ	zmmreg	mask	z, zmmrm512	b64*, imm8 AVX512
VPROLVD	xmmreg	mask	z, xmmreg*, xmmrm128	b32 AVX512VL
VPROLVD	ymmreg	mask	z, ymmreg*, ymmrm256	b32 AVX512VL
VPROLVD	zmmreg	mask	z, zmmreg*, zmmrm512	b32 AVX512
VPROLVQ	xmmreg	mask	z, xmmreg*, xmmrm128	b64 AVX512VL
VPROLVQ	ymmreg	mask	z, ymmreg*, ymmrm256	b64 AVX512VL
VPROLVQ	zmmreg	mask	z, zmmreg*, zmmrm512	b64 AVX512
VPRORD	xmmreg	mask	z, xmmrm128	b32*, imm8 AVX512VL
VPRORD	ymmreg	mask	z, ymmrm256	b32*, imm8 AVX512VL
VPRORD	zmmreg	mask	z, zmmrm512	b32*, imm8 AVX512
VPRORQ	xmmreg	mask	z, xmmrm128	b64*, imm8 AVX512VL
VPRORQ	ymmreg	mask	z, ymmrm256	b64*, imm8 AVX512VL
VPRORQ	zmmreg	mask	z, zmmrm512	b64*, imm8 AVX512
VPRORVD	xmmreg	mask	z, xmmreg*, xmmrm128	b32 AVX512VL
VPRORVD	ymmreg	mask	z, ymmreg*, ymmrm256	b32 AVX512VL
VPRORVD	zmmreg	mask	z, zmmreg*, zmmrm512	b32 AVX512
VPRORVQ	xmmreg	mask	z, xmmreg*, xmmrm128	b64 AVX512VL
VPRORVQ	ymmreg	mask	z, ymmreg*, ymmrm256	b64 AVX512VL
VPRORVQ	zmmreg	mask	z, zmmreg*, zmmrm512	b64 AVX512
VPSADBW	xmmreg, xmmreg*		xmmrm128	AVX512VL/BW
VPSADBW	ymmreg, ymmreg*		ymmrm256	AVX512VL/BW
VPSADBW	zmmreg, zmmreg*		zmmrm512	AVX512BW
VPSCATTERDD	xmem32	mask, xmmreg		AVX512VL
VPSCATTERDD	yem32	mask, ymmreg		AVX512VL
VPSCATTERDD	zmem32	mask, zmmreg		AVX512
VPSCATTERDQ	xmem64	mask, xmmreg		AVX512VL
VPSCATTERDQ	yem64	mask, ymmreg		AVX512VL
VPSCATTERDQ	zmem64	mask, zmmreg		AVX512
VPSCATTERQD	xmem32	mask, xmmreg		AVX512VL
VPSCATTERQD	yem32	mask, xmmreg		AVX512VL
VPSCATTERQD	zmem32	mask, ymmreg		AVX512
VPSCATTERQQ	xmem64	mask, xmmreg		AVX512VL
VPSCATTERQQ	yem64	mask, ymmreg		AVX512VL
VPSCATTERQQ	zmem64	mask, zmmreg		AVX512
VPSHUFB	xmmreg	mask	z, xmmreg*, xmmrm128	AVX512VL/BW
VPSHUFB	ymmreg	mask	z, ymmreg*, ymmrm256	AVX512VL/BW
VPSHUFB	zmmreg	mask	z, zmmreg*, zmmrm512	AVX512BW
VPSHUFD	xmmreg	mask	z, xmmrm128	b32, imm8 AVX512VL
VPSHUFD	ymmreg	mask	z, ymmrm256	b32, imm8 AVX512VL
VPSHUFD	zmmreg	mask	z, zmmrm512	b32, imm8 AVX512
VPSHUFHW	xmmreg	mask	z, xmmrm128, imm8	AVX512VL/BW
VPSHUFHW	ymmreg	mask	z, ymmrm256, imm8	AVX512VL/BW
VPSHUFHW	zmmreg	mask	z, zmmrm512, imm8	AVX512BW

VPSHUFLW	xmmreg	mask	z, xmmrm128, imm8	AVX512VL/BW
VPSHUFLW	ymmreg	mask	z, ymmrm256, imm8	AVX512VL/BW
VPSHUFLW	zmmreg	mask	z, zmmrm512, imm8	AVX512BW
VPSLLD	xmmreg	mask	z, xmmreg*, xmmrm128	AVX512VL
VPSLLD	ymmreg	mask	z, ymmreg*, xmmrm128	AVX512VL
VPSLLD	zmmreg	mask	z, zmmreg*, xmmrm128	AVX512
VPSLLD	xmmreg	mask	z, xmmrm128 b32*, imm8	AVX512VL
VPSLLD	ymmreg	mask	z, ymmrm256 b32*, imm8	AVX512VL
VPSLLD	zmmreg	mask	z, zmmrm512 b32*, imm8	AVX512
VPSLLDQ	xmmreg, xmmrm128*	imm8		AVX512VL/BW
VPSLLDQ	ymmreg, ymmrm256*	imm8		AVX512VL/BW
VPSLLDQ	zmmreg, zmmrm512*	imm8		AVX512BW
VPSLLQ	xmmreg	mask	z, xmmreg*, xmmrm128	AVX512VL
VPSLLQ	ymmreg	mask	z, ymmreg*, xmmrm128	AVX512VL
VPSLLQ	zmmreg	mask	z, zmmreg*, xmmrm128	AVX512
VPSLLQ	xmmreg	mask	z, xmmrm128 b64*, imm8	AVX512VL
VPSLLQ	ymmreg	mask	z, ymmrm256 b64*, imm8	AVX512VL
VPSLLQ	zmmreg	mask	z, zmmrm512 b64*, imm8	AVX512
VPSLLVD	xmmreg	mask	z, xmmreg*, xmmrm128 b32	AVX512VL
VPSLLVD	ymmreg	mask	z, ymmreg*, ymmrm256 b32	AVX512VL
VPSLLVD	zmmreg	mask	z, zmmreg*, zmmrm512 b32	AVX512
VPSLLVQ	xmmreg	mask	z, xmmreg*, xmmrm128 b64	AVX512VL
VPSLLVQ	ymmreg	mask	z, ymmreg*, ymmrm256 b64	AVX512VL
VPSLLVQ	zmmreg	mask	z, zmmreg*, zmmrm512 b64	AVX512
VPSLLVW	xmmreg	mask	z, xmmreg*, xmmrm128	AVX512VL/BW
VPSLLVW	ymmreg	mask	z, ymmreg*, ymmrm256	AVX512VL/BW
VPSLLVW	zmmreg	mask	z, zmmreg*, zmmrm512	AVX512BW
VPSLLW	xmmreg	mask	z, xmmreg*, xmmrm128	AVX512VL/BW
VPSLLW	ymmreg	mask	z, ymmreg*, xmmrm128	AVX512VL/BW
VPSLLW	zmmreg	mask	z, zmmreg*, xmmrm128	AVX512BW
VPSLLW	xmmreg	mask	z, xmmrm128*, imm8	AVX512VL/BW
VPSLLW	ymmreg	mask	z, ymmrm256*, imm8	AVX512VL/BW
VPSLLW	zmmreg	mask	z, zmmrm512*, imm8	AVX512BW
VPSRAD	xmmreg	mask	z, xmmreg*, xmmrm128	AVX512VL
VPSRAD	ymmreg	mask	z, ymmreg*, xmmrm128	AVX512VL
VPSRAD	zmmreg	mask	z, zmmreg*, xmmrm128	AVX512
VPSRAD	xmmreg	mask	z, xmmrm128 b32*, imm8	AVX512VL
VPSRAD	ymmreg	mask	z, ymmrm256 b32*, imm8	AVX512VL
VPSRAD	zmmreg	mask	z, zmmrm512 b32*, imm8	AVX512
VPSRAQ	xmmreg	mask	z, xmmreg*, xmmrm128	AVX512VL
VPSRAQ	ymmreg	mask	z, ymmreg*, xmmrm128	AVX512VL
VPSRAQ	zmmreg	mask	z, zmmreg*, xmmrm128	AVX512
VPSRAQ	xmmreg	mask	z, xmmrm128 b64*, imm8	AVX512VL
VPSRAQ	ymmreg	mask	z, ymmrm256 b64*, imm8	AVX512VL
VPSRAQ	zmmreg	mask	z, zmmrm512 b64*, imm8	AVX512
VPSRAVD	xmmreg	mask	z, xmmreg*, xmmrm128 b32	AVX512VL
VPSRAVD	ymmreg	mask	z, ymmreg*, ymmrm256 b32	AVX512VL
VPSRAVD	zmmreg	mask	z, zmmreg*, zmmrm512 b32	AVX512
VPSRAVQ	xmmreg	mask	z, xmmreg*, xmmrm128 b64	AVX512VL
VPSRAVQ	ymmreg	mask	z, ymmreg*, ymmrm256 b64	AVX512VL
VPSRAVQ	zmmreg	mask	z, zmmreg*, zmmrm512 b64	AVX512
VPSRAVW	xmmreg	mask	z, xmmreg*, xmmrm128	AVX512VL/BW
VPSRAVW	ymmreg	mask	z, ymmreg*, ymmrm256	AVX512VL/BW
VPSRAVW	zmmreg	mask	z, zmmreg*, zmmrm512	AVX512BW

VPSRAW	xmmreg	mask	z, xmmreg*, xmmrmm128	AVX512VL/BW
VPSRAW	ymmreg	mask	z, ymmreg*, xmmrmm128	AVX512VL/BW
VPSRAW	zmmreg	mask	z, zmmreg*, xmmrmm128	AVX512BW
VPSRAW	xmmreg	mask	z, xmmrmm128*, imm8	AVX512VL/BW
VPSRAW	ymmreg	mask	z, ymmrmm256*, imm8	AVX512VL/BW
VPSRAW	zmmreg	mask	z, zmmrmm512*, imm8	AVX512BW
VPSRLD	xmmreg	mask	z, xmmreg*, xmmrmm128	AVX512VL
VPSRLD	ymmreg	mask	z, ymmreg*, xmmrmm128	AVX512VL
VPSRLD	zmmreg	mask	z, zmmreg*, xmmrmm128	AVX512
VPSRLD	xmmreg	mask	z, xmmrmm128 b32*, imm8	AVX512VL
VPSRLD	ymmreg	mask	z, ymmrmm256 b32*, imm8	AVX512VL
VPSRLD	zmmreg	mask	z, zmmrmm512 b32*, imm8	AVX512
VPSRLDQ	xmmreg, xmmrmm128*, imm8			AVX512VL/BW
VPSRLDQ	ymmreg, ymmrmm256*, imm8			AVX512VL/BW
VPSRLDQ	zmmreg, zmmrmm512*, imm8			AVX512BW
VPSRLQ	xmmreg	mask	z, xmmreg*, xmmrmm128	AVX512VL
VPSRLQ	ymmreg	mask	z, ymmreg*, xmmrmm128	AVX512VL
VPSRLQ	zmmreg	mask	z, zmmreg*, xmmrmm128	AVX512
VPSRLQ	xmmreg	mask	z, xmmrmm128 b64*, imm8	AVX512VL
VPSRLQ	ymmreg	mask	z, ymmrmm256 b64*, imm8	AVX512VL
VPSRLQ	zmmreg	mask	z, zmmrmm512 b64*, imm8	AVX512
VPSRLVD	xmmreg	mask	z, xmmreg*, xmmrmm128	b32 AVX512VL
VPSRLVD	ymmreg	mask	z, ymmreg*, ymmrmm256	b32 AVX512VL
VPSRLVD	zmmreg	mask	z, zmmreg*, zmmrmm512	b32 AVX512
VPSRLVQ	xmmreg	mask	z, xmmreg*, xmmrmm128	b64 AVX512VL
VPSRLVQ	ymmreg	mask	z, ymmreg*, ymmrmm256	b64 AVX512VL
VPSRLVQ	zmmreg	mask	z, zmmreg*, zmmrmm512	b64 AVX512
VPSRLVW	xmmreg	mask	z, xmmreg*, xmmrmm128	AVX512VL/BW
VPSRLVW	ymmreg	mask	z, ymmreg*, ymmrmm256	AVX512VL/BW
VPSRLVW	zmmreg	mask	z, zmmreg*, zmmrmm512	AVX512BW
VPSRLW	xmmreg	mask	z, xmmreg*, xmmrmm128	AVX512VL/BW
VPSRLW	ymmreg	mask	z, ymmreg*, xmmrmm128	AVX512VL/BW
VPSRLW	zmmreg	mask	z, zmmreg*, xmmrmm128	AVX512BW
VPSRLW	xmmreg	mask	z, xmmrmm128*, imm8	AVX512VL/BW
VPSRLW	ymmreg	mask	z, ymmrmm256*, imm8	AVX512VL/BW
VPSRLW	zmmreg	mask	z, zmmrmm512*, imm8	AVX512BW
VPSUBB	xmmreg	mask	z, xmmreg*, xmmrmm128	AVX512VL/BW
VPSUBB	ymmreg	mask	z, ymmreg*, ymmrmm256	AVX512VL/BW
VPSUBB	zmmreg	mask	z, zmmreg*, zmmrmm512	AVX512BW
VPSUBD	xmmreg	mask	z, xmmreg*, xmmrmm128	b32 AVX512VL
VPSUBD	ymmreg	mask	z, ymmreg*, ymmrmm256	b32 AVX512VL
VPSUBD	zmmreg	mask	z, zmmreg*, zmmrmm512	b32 AVX512
VPSUBQ	xmmreg	mask	z, xmmreg*, xmmrmm128	b64 AVX512VL
VPSUBQ	ymmreg	mask	z, ymmreg*, ymmrmm256	b64 AVX512VL
VPSUBQ	zmmreg	mask	z, zmmreg*, zmmrmm512	b64 AVX512
VPSUBSB	xmmreg	mask	z, xmmreg*, xmmrmm128	AVX512VL/BW
VPSUBSB	ymmreg	mask	z, ymmreg*, ymmrmm256	AVX512VL/BW
VPSUBSB	zmmreg	mask	z, zmmreg*, zmmrmm512	AVX512BW
VPSUBSW	xmmreg	mask	z, xmmreg*, xmmrmm128	AVX512VL/BW
VPSUBSW	ymmreg	mask	z, ymmreg*, ymmrmm256	AVX512VL/BW
VPSUBSW	zmmreg	mask	z, zmmreg*, zmmrmm512	AVX512BW
VPSUBUSB	xmmreg	mask	z, xmmreg*, xmmrmm128	AVX512VL/BW
VPSUBUSB	ymmreg	mask	z, ymmreg*, ymmrmm256	AVX512VL/BW
VPSUBUSB	zmmreg	mask	z, zmmreg*, zmmrmm512	AVX512BW

VPSUBUSW	xmmreg	mask	z, xmmreg*, xmmrm128	AVX512VL/BW
VPSUBUSW	ymmreg	mask	z, ymmreg*, ymmrm256	AVX512VL/BW
VPSUBUSW	zmmreg	mask	z, zmmreg*, zmmrm512	AVX512BW
VPSUBW	xmmreg	mask	z, xmmreg*, xmmrm128	AVX512VL/BW
VPSUBW	ymmreg	mask	z, ymmreg*, ymmrm256	AVX512VL/BW
VPSUBW	zmmreg	mask	z, zmmreg*, zmmrm512	AVX512BW
VPTERNLOGD	xmmreg	mask	z, xmmreg, xmmrm128	b32, imm8 AVX512VL
VPTERNLOGD	ymmreg	mask	z, ymmreg, ymmrm256	b32, imm8 AVX512VL
VPTERNLOGD	zmmreg	mask	z, zmmreg, zmmrm512	b32, imm8 AVX512
VPTERNLOGQ	xmmreg	mask	z, xmmreg, xmmrm128	b64, imm8 AVX512VL
VPTERNLOGQ	ymmreg	mask	z, ymmreg, ymmrm256	b64, imm8 AVX512VL
VPTERNLOGQ	zmmreg	mask	z, zmmreg, zmmrm512	b64, imm8 AVX512
VPTESTMB	kreg	mask, xmmreg, xmmrm128	AVX512VL/BW	
VPTESTMB	kreg	mask, ymmreg, ymmrm256	AVX512VL/BW	
VPTESTMB	kreg	mask, zmmreg, zmmrm512	AVX512BW	
VPTESTMD	kreg	mask, xmmreg, xmmrm128	b32 AVX512VL	
VPTESTMD	kreg	mask, ymmreg, ymmrm256	b32 AVX512VL	
VPTESTMD	kreg	mask, zmmreg, zmmrm512	b32 AVX512	
VPTESTMQ	kreg	mask, xmmreg, xmmrm128	b64 AVX512VL	
VPTESTMQ	kreg	mask, ymmreg, ymmrm256	b64 AVX512VL	
VPTESTMQ	kreg	mask, zmmreg, zmmrm512	b64 AVX512	
VPTESTMW	kreg	mask, xmmreg, xmmrm128	AVX512VL/BW	
VPTESTMW	kreg	mask, ymmreg, ymmrm256	AVX512VL/BW	
VPTESTMW	kreg	mask, zmmreg, zmmrm512	AVX512BW	
VPTESTNMB	kreg	mask, xmmreg, xmmrm128	AVX512VL/BW	
VPTESTNMB	kreg	mask, ymmreg, ymmrm256	AVX512VL/BW	
VPTESTNMB	kreg	mask, zmmreg, zmmrm512	AVX512BW	
VPTESTNMD	kreg	mask, xmmreg, xmmrm128	b32 AVX512VL	
VPTESTNMD	kreg	mask, ymmreg, ymmrm256	b32 AVX512VL	
VPTESTNMD	kreg	mask, zmmreg, zmmrm512	b32 AVX512	
VPTESTNMQ	kreg	mask, xmmreg, xmmrm128	b64 AVX512VL	
VPTESTNMQ	kreg	mask, ymmreg, ymmrm256	b64 AVX512VL	
VPTESTNMQ	kreg	mask, zmmreg, zmmrm512	b64 AVX512	
VPTESTNMW	kreg	mask, xmmreg, xmmrm128	AVX512VL/BW	
VPTESTNMW	kreg	mask, ymmreg, ymmrm256	AVX512VL/BW	
VPTESTNMW	kreg	mask, zmmreg, zmmrm512	AVX512BW	
VPUNPCKHBW	xmmreg	mask	z, xmmreg*, xmmrm128	AVX512VL/BW
VPUNPCKHBW	ymmreg	mask	z, ymmreg*, ymmrm256	AVX512VL/BW
VPUNPCKHBW	zmmreg	mask	z, zmmreg*, zmmrm512	AVX512BW
VPUNPCKHDQ	xmmreg	mask	z, xmmreg*, xmmrm128	b32 AVX512VL
VPUNPCKHDQ	ymmreg	mask	z, ymmreg*, ymmrm256	b32 AVX512VL
VPUNPCKHDQ	zmmreg	mask	z, zmmreg*, zmmrm512	b32 AVX512
VPUNPCKHQDQ	xmmreg	mask	z, xmmreg*, xmmrm128	b64 AVX512VL
VPUNPCKHQDQ	ymmreg	mask	z, ymmreg*, ymmrm256	b64 AVX512VL
VPUNPCKHQDQ	zmmreg	mask	z, zmmreg*, zmmrm512	b64 AVX512
VPUNPCKHWD	xmmreg	mask	z, xmmreg*, xmmrm128	AVX512VL/BW
VPUNPCKHWD	ymmreg	mask	z, ymmreg*, ymmrm256	AVX512VL/BW
VPUNPCKHWD	zmmreg	mask	z, zmmreg*, zmmrm512	AVX512BW
VPUNPCKLBW	xmmreg	mask	z, xmmreg*, xmmrm128	AVX512VL/BW
VPUNPCKLBW	ymmreg	mask	z, ymmreg*, ymmrm256	AVX512VL/BW
VPUNPCKLBW	zmmreg	mask	z, zmmreg*, zmmrm512	AVX512BW
VPUNPCKLDQ	xmmreg	mask	z, xmmreg*, xmmrm128	b32 AVX512VL
VPUNPCKLDQ	ymmreg	mask	z, ymmreg*, ymmrm256	b32 AVX512VL
VPUNPCKLDQ	zmmreg	mask	z, zmmreg*, zmmrm512	b32 AVX512

VPUNPCKLQDQ	xmmreg	mask	z, xmmreg*, xmmrm128	b64 AVX512VL
VPUNPCKLQDQ	ymmreg	mask	z, ymmreg*, ymmrm256	b64 AVX512VL
VPUNPCKLQDQ	zmmreg	mask	z, zmmreg*, zmmrm512	b64 AVX512
VPUNPCKLWD	xmmreg	mask	z, xmmreg*, xmmrm128	AVX512VL/BW
VPUNPCKLWD	ymmreg	mask	z, ymmreg*, ymmrm256	AVX512VL/BW
VPUNPCKLWD	zmmreg	mask	z, zmmreg*, zmmrm512	AVX512BW
VPXORD	xmmreg	mask	z, xmmreg*, xmmrm128	b32 AVX512VL
VPXORD	ymmreg	mask	z, ymmreg*, ymmrm256	b32 AVX512VL
VPXORD	zmmreg	mask	z, zmmreg*, zmmrm512	b32 AVX512
VPXORQ	xmmreg	mask	z, xmmreg*, xmmrm128	b64 AVX512VL
VPXORQ	ymmreg	mask	z, ymmreg*, ymmrm256	b64 AVX512VL
VPXORQ	zmmreg	mask	z, zmmreg*, zmmrm512	b64 AVX512
VRANGEPD	xmmreg	mask	z, xmmreg*, xmmrm128	b64, imm8 AVX512VL/DQ
VRANGEPD	ymmreg	mask	z, ymmreg*, ymmrm256	b64, imm8 AVX512VL/DQ
VRANGEPD	zmmreg	mask	z, zmmreg*, zmmrm512	b64 sae, imm8 AVX512DQ
VRANGEPS	xmmreg	mask	z, xmmreg*, xmmrm128	b32, imm8 AVX512VL/DQ
VRANGEPS	ymmreg	mask	z, ymmreg*, ymmrm256	b32, imm8 AVX512VL/DQ
VRANGEPS	zmmreg	mask	z, zmmreg*, zmmrm512	b32 sae, imm8 AVX512DQ
VRANGESD	xmmreg	mask	z, xmmreg*, xmmrm64	sae, imm8 AVX512DQ
VRANGESS	xmmreg	mask	z, xmmreg*, xmmrm32	sae, imm8 AVX512DQ
VRCP14PD	xmmreg	mask	z, xmmrm128	b64 AVX512VL
VRCP14PD	ymmreg	mask	z, ymmrm256	b64 AVX512VL
VRCP14PD	zmmreg	mask	z, zmmrm512	b64 AVX512
VRCP14PS	xmmreg	mask	z, xmmrm128	b32 AVX512VL
VRCP14PS	ymmreg	mask	z, ymmrm256	b32 AVX512VL
VRCP14PS	zmmreg	mask	z, zmmrm512	b32 AVX512
VRCP14SD	xmmreg	mask	z, xmmreg*, xmmrm64	AVX512
VRCP14SS	xmmreg	mask	z, xmmreg*, xmmrm32	AVX512
VRCP28PD	zmmreg	mask	z, zmmrm512	b64 sae AVX512ER
VRCP28PS	zmmreg	mask	z, zmmrm512	b32 sae AVX512ER
VRCP28SD	xmmreg	mask	z, xmmreg*, xmmrm64	sae AVX512ER
VRCP28SS	xmmreg	mask	z, xmmreg*, xmmrm32	sae AVX512ER
VREDUCEPD	xmmreg	mask	z, xmmrm128	b64, imm8 AVX512VL/DQ
VREDUCEPD	ymmreg	mask	z, ymmrm256	b64, imm8 AVX512VL/DQ
VREDUCEPD	zmmreg	mask	z, zmmrm512	b64 sae, imm8 AVX512DQ
VREDUCEPS	xmmreg	mask	z, xmmrm128	b32, imm8 AVX512VL/DQ
VREDUCEPS	ymmreg	mask	z, ymmrm256	b32, imm8 AVX512VL/DQ
VREDUCEPS	zmmreg	mask	z, zmmrm512	b32 sae, imm8 AVX512DQ
VREDUCESD	xmmreg	mask	z, xmmreg*, xmmrm64	sae, imm8 AVX512DQ
VREDUCESS	xmmreg	mask	z, xmmreg*, xmmrm32	sae, imm8 AVX512DQ
VRNDSCALEPD	xmmreg	mask	z, xmmrm128	b64, imm8 AVX512VL
VRNDSCALEPD	ymmreg	mask	z, ymmrm256	b64, imm8 AVX512VL
VRNDSCALEPD	zmmreg	mask	z, zmmrm512	b64 sae, imm8 AVX512
VRNDSCALEPS	xmmreg	mask	z, xmmrm128	b32, imm8 AVX512VL
VRNDSCALEPS	ymmreg	mask	z, ymmrm256	b32, imm8 AVX512VL
VRNDSCALEPS	zmmreg	mask	z, zmmrm512	b32 sae, imm8 AVX512
VRNDSCALESD	xmmreg	mask	z, xmmreg*, xmmrm64	sae, imm8 AVX512
VRNDSCALESS	xmmreg	mask	z, xmmreg*, xmmrm32	sae, imm8 AVX512
VSQRT14PD	xmmreg	mask	z, xmmrm128	b64 AVX512VL
VSQRT14PD	ymmreg	mask	z, ymmrm256	b64 AVX512VL
VSQRT14PD	zmmreg	mask	z, zmmrm512	b64 AVX512
VSQRT14PS	xmmreg	mask	z, xmmrm128	b32 AVX512VL
VSQRT14PS	ymmreg	mask	z, ymmrm256	b32 AVX512VL
VSQRT14PS	zmmreg	mask	z, zmmrm512	b32 AVX512

VRSQRT14SD	xmmreg	mask	z, xmmreg*, xmmrm64	AVX512
VRSQRT14SS	xmmreg	mask	z, xmmreg*, xmmrm32	AVX512
VRSQRT28PD	zmmreg	mask	z, zmmrm512	b64 sae AVX512ER
VRSQRT28PS	zmmreg	mask	z, zmmrm512	b32 sae AVX512ER
VRSQRT28SD	xmmreg	mask	z, xmmreg*, xmmrm64	sae AVX512ER
VRSQRT28SS	xmmreg	mask	z, xmmreg*, xmmrm32	sae AVX512ER
VSCALEFPD	xmmreg	mask	z, xmmreg*, xmmrm128	b64 AVX512VL
VSCALEFPD	ymmreg	mask	z, ymmreg*, ymmrm256	b64 AVX512VL
VSCALEFPD	zmmreg	mask	z, zmmreg*, zmmrm512	b64 er AVX512
VSCALEFPS	xmmreg	mask	z, xmmreg*, xmmrm128	b32 AVX512VL
VSCALEFPS	ymmreg	mask	z, ymmreg*, ymmrm256	b32 AVX512VL
VSCALEFPS	zmmreg	mask	z, zmmreg*, zmmrm512	b32 er AVX512
VSCALEFSD	xmmreg	mask	z, xmmreg*, xmmrm64	er AVX512
VSCALEFSS	xmmreg	mask	z, xmmreg*, xmmrm32	er AVX512
VSCATTERDPD	xmem64	mask, xmmreg		AVX512VL
VSCATTERDPD	xmem64	mask, ymmreg		AVX512VL
VSCATTERDPD	yem64	mask, zmmreg		AVX512
VSCATTERDPS	xmem32	mask, xmmreg		AVX512VL
VSCATTERDPS	yem32	mask, ymmreg		AVX512VL
VSCATTERDPS	zmem32	mask, zmmreg		AVX512
VSCATTERPF0DPD	yem64	mask		AVX512PF
VSCATTERPF0DPS	zmem32	mask		AVX512PF
VSCATTERPF0QPD	zmem64	mask		AVX512PF
VSCATTERPF0QPS	zmem32	mask		AVX512PF
VSCATTERPF1DPD	yem64	mask		AVX512PF
VSCATTERPF1DPS	zmem32	mask		AVX512PF
VSCATTERPF1QPD	zmem64	mask		AVX512PF
VSCATTERPF1QPS	zmem32	mask		AVX512PF
VSCATTERQPD	xmem64	mask, xmmreg		AVX512VL
VSCATTERQPD	yem64	mask, ymmreg		AVX512VL
VSCATTERQPD	zmem64	mask, zmmreg		AVX512
VSCATTERQPS	xmem32	mask, xmmreg		AVX512VL
VSCATTERQPS	yem32	mask, xmmreg		AVX512VL
VSCATTERQPS	zmem32	mask, ymmreg		AVX512
VSHUFF32X4	ymmreg	mask	z, ymmreg*, ymmrm256	b32, imm8 AVX512VL
VSHUFF32X4	zmmreg	mask	z, zmmreg*, zmmrm512	b32, imm8 AVX512
VSHUFF64X2	ymmreg	mask	z, ymmreg*, ymmrm256	b64, imm8 AVX512VL
VSHUFF64X2	zmmreg	mask	z, zmmreg*, zmmrm512	b64, imm8 AVX512
VSHUF132X4	ymmreg	mask	z, ymmreg*, ymmrm256	b32, imm8 AVX512VL
VSHUF132X4	zmmreg	mask	z, zmmreg*, zmmrm512	b32, imm8 AVX512
VSHUF164X2	ymmreg	mask	z, ymmreg*, ymmrm256	b64, imm8 AVX512VL
VSHUF164X2	zmmreg	mask	z, zmmreg*, zmmrm512	b64, imm8 AVX512
VSHUFPD	xmmreg	mask	z, xmmreg*, xmmrm128	b64, imm8 AVX512VL
VSHUFPD	ymmreg	mask	z, ymmreg*, ymmrm256	b64, imm8 AVX512VL
VSHUFPD	zmmreg	mask	z, zmmreg*, zmmrm512	b64, imm8 AVX512
VSHUFPS	xmmreg	mask	z, xmmreg*, xmmrm128	b32, imm8 AVX512VL
VSHUFPS	ymmreg	mask	z, ymmreg*, ymmrm256	b32, imm8 AVX512VL
VSHUFPS	zmmreg	mask	z, zmmreg*, zmmrm512	b32, imm8 AVX512
VSQRTPD	xmmreg	mask	z, xmmrm128	b64 AVX512VL
VSQRTPD	ymmreg	mask	z, ymmrm256	b64 AVX512VL
VSQRTPD	zmmreg	mask	z, zmmrm512	b64 er AVX512
VSQRTPS	xmmreg	mask	z, xmmrm128	b32 AVX512VL
VSQRTPS	ymmreg	mask	z, ymmrm256	b32 AVX512VL
VSQRTPS	zmmreg	mask	z, zmmrm512	b32 er AVX512

VSQRTSD	xmmreg	mask	z, xmmreg*, xmmrm64	er AVX512
VSQRTSS	xmmreg	mask	z, xmmreg*, xmmrm32	er AVX512
VSUBPD	xmmreg	mask	z, xmmreg*, xmmrm128	b64 AVX512VL
VSUBPD	ymmreg	mask	z, ymmreg*, ymmrm256	b64 AVX512VL
VSUBPD	zmmreg	mask	z, zmmreg*, zmmrm512	b64 er AVX512
VSUBPS	xmmreg	mask	z, xmmreg*, xmmrm128	b32 AVX512VL
VSUBPS	ymmreg	mask	z, ymmreg*, ymmrm256	b32 AVX512VL
VSUBPS	zmmreg	mask	z, zmmreg*, zmmrm512	b32 er AVX512
VSUBSD	xmmreg	mask	z, xmmreg*, xmmrm64	er AVX512
VSUBSS	xmmreg	mask	z, xmmreg*, xmmrm32	er AVX512
VUCOMISD	xmmreg, xmmrm64	sae		AVX512
VUCOMISS	xmmreg, xmmrm32	sae		AVX512
VUNPCKHPD	xmmreg	mask	z, xmmreg*, xmmrm128	b64 AVX512VL
VUNPCKHPD	ymmreg	mask	z, ymmreg*, ymmrm256	b64 AVX512VL
VUNPCKHPD	zmmreg	mask	z, zmmreg*, zmmrm512	b64 AVX512
VUNPCKHPS	xmmreg	mask	z, xmmreg*, xmmrm128	b32 AVX512VL
VUNPCKHPS	ymmreg	mask	z, ymmreg*, ymmrm256	b32 AVX512VL
VUNPCKHPS	zmmreg	mask	z, zmmreg*, zmmrm512	b32 AVX512
VUNPCKLPD	xmmreg	mask	z, xmmreg*, xmmrm128	b64 AVX512VL
VUNPCKLPD	ymmreg	mask	z, ymmreg*, ymmrm256	b64 AVX512VL
VUNPCKLPD	zmmreg	mask	z, zmmreg*, zmmrm512	b64 AVX512
VUNPCKLPS	xmmreg	mask	z, xmmreg*, xmmrm128	b32 AVX512VL
VUNPCKLPS	ymmreg	mask	z, ymmreg*, ymmrm256	b32 AVX512VL
VUNPCKLPS	zmmreg	mask	z, zmmreg*, zmmrm512	b32 AVX512
VXORPD	xmmreg	mask	z, xmmreg*, xmmrm128	b64 AVX512VL/DQ
VXORPD	ymmreg	mask	z, ymmreg*, ymmrm256	b64 AVX512VL/DQ
VXORPD	zmmreg	mask	z, zmmreg*, zmmrm512	b64 AVX512DQ
VXORPS	xmmreg	mask	z, xmmreg*, xmmrm128	b32 AVX512VL/DQ
VXORPS	ymmreg	mask	z, ymmreg*, ymmrm256	b32 AVX512VL/DQ
VXORPS	zmmreg	mask	z, zmmreg*, zmmrm512	b32 AVX512DQ

B.1.41 Intel memory protection keys for userspace (PKU aka PKEYs)

RDPKRU	X64
WRPKRU	X64

B.1.42 Read Processor ID

RDPID	reg32	NOLONG
RDPID	reg64	X64
RDPID	reg32	X64, UNDOC

B.1.43 New memory instructions

CLFLUSHOPT	mem	
CLWB	mem	
PCOMMIT		UNDOC, OBSOLETE
CLZERO		AMD

B.1.44 Systematic names for the hinting nop instructions

HINT_NOP0	rm16	P6, UNDOC
HINT_NOP0	rm32	P6, UNDOC
HINT_NOP0	rm64	X64, UNDOC
HINT_NOP1	rm16	P6, UNDOC
HINT_NOP1	rm32	P6, UNDOC
HINT_NOP1	rm64	X64, UNDOC

HINT_NOP2	rm16	P6, UNDOC
HINT_NOP2	rm32	P6, UNDOC
HINT_NOP2	rm64	X64, UNDOC
HINT_NOP3	rm16	P6, UNDOC
HINT_NOP3	rm32	P6, UNDOC
HINT_NOP3	rm64	X64, UNDOC
HINT_NOP4	rm16	P6, UNDOC
HINT_NOP4	rm32	P6, UNDOC
HINT_NOP4	rm64	X64, UNDOC
HINT_NOP5	rm16	P6, UNDOC
HINT_NOP5	rm32	P6, UNDOC
HINT_NOP5	rm64	X64, UNDOC
HINT_NOP6	rm16	P6, UNDOC
HINT_NOP6	rm32	P6, UNDOC
HINT_NOP6	rm64	X64, UNDOC
HINT_NOP7	rm16	P6, UNDOC
HINT_NOP7	rm32	P6, UNDOC
HINT_NOP7	rm64	X64, UNDOC
HINT_NOP8	rm16	P6, UNDOC
HINT_NOP8	rm32	P6, UNDOC
HINT_NOP8	rm64	X64, UNDOC
HINT_NOP9	rm16	P6, UNDOC
HINT_NOP9	rm32	P6, UNDOC
HINT_NOP9	rm64	X64, UNDOC
HINT_NOP10	rm16	P6, UNDOC
HINT_NOP10	rm32	P6, UNDOC
HINT_NOP10	rm64	X64, UNDOC
HINT_NOP11	rm16	P6, UNDOC
HINT_NOP11	rm32	P6, UNDOC
HINT_NOP11	rm64	X64, UNDOC
HINT_NOP12	rm16	P6, UNDOC
HINT_NOP12	rm32	P6, UNDOC
HINT_NOP12	rm64	X64, UNDOC
HINT_NOP13	rm16	P6, UNDOC
HINT_NOP13	rm32	P6, UNDOC
HINT_NOP13	rm64	X64, UNDOC
HINT_NOP14	rm16	P6, UNDOC
HINT_NOP14	rm32	P6, UNDOC
HINT_NOP14	rm64	X64, UNDOC
HINT_NOP15	rm16	P6, UNDOC
HINT_NOP15	rm32	P6, UNDOC
HINT_NOP15	rm64	X64, UNDOC
HINT_NOP16	rm16	P6, UNDOC
HINT_NOP16	rm32	P6, UNDOC
HINT_NOP16	rm64	X64, UNDOC
HINT_NOP17	rm16	P6, UNDOC
HINT_NOP17	rm32	P6, UNDOC
HINT_NOP17	rm64	X64, UNDOC
HINT_NOP18	rm16	P6, UNDOC
HINT_NOP18	rm32	P6, UNDOC
HINT_NOP18	rm64	X64, UNDOC
HINT_NOP19	rm16	P6, UNDOC
HINT_NOP19	rm32	P6, UNDOC
HINT_NOP19	rm64	X64, UNDOC

HINT_NOP20	rm16	P6, UNDOC
HINT_NOP20	rm32	P6, UNDOC
HINT_NOP20	rm64	X64, UNDOC
HINT_NOP21	rm16	P6, UNDOC
HINT_NOP21	rm32	P6, UNDOC
HINT_NOP21	rm64	X64, UNDOC
HINT_NOP22	rm16	P6, UNDOC
HINT_NOP22	rm32	P6, UNDOC
HINT_NOP22	rm64	X64, UNDOC
HINT_NOP23	rm16	P6, UNDOC
HINT_NOP23	rm32	P6, UNDOC
HINT_NOP23	rm64	X64, UNDOC
HINT_NOP24	rm16	P6, UNDOC
HINT_NOP24	rm32	P6, UNDOC
HINT_NOP24	rm64	X64, UNDOC
HINT_NOP25	rm16	P6, UNDOC
HINT_NOP25	rm32	P6, UNDOC
HINT_NOP25	rm64	X64, UNDOC
HINT_NOP26	rm16	P6, UNDOC
HINT_NOP26	rm32	P6, UNDOC
HINT_NOP26	rm64	X64, UNDOC
HINT_NOP27	rm16	P6, UNDOC
HINT_NOP27	rm32	P6, UNDOC
HINT_NOP27	rm64	X64, UNDOC
HINT_NOP28	rm16	P6, UNDOC
HINT_NOP28	rm32	P6, UNDOC
HINT_NOP28	rm64	X64, UNDOC
HINT_NOP29	rm16	P6, UNDOC
HINT_NOP29	rm32	P6, UNDOC
HINT_NOP29	rm64	X64, UNDOC
HINT_NOP30	rm16	P6, UNDOC
HINT_NOP30	rm32	P6, UNDOC
HINT_NOP30	rm64	X64, UNDOC
HINT_NOP31	rm16	P6, UNDOC
HINT_NOP31	rm32	P6, UNDOC
HINT_NOP31	rm64	X64, UNDOC
HINT_NOP32	rm16	P6, UNDOC
HINT_NOP32	rm32	P6, UNDOC
HINT_NOP32	rm64	X64, UNDOC
HINT_NOP33	rm16	P6, UNDOC
HINT_NOP33	rm32	P6, UNDOC
HINT_NOP33	rm64	X64, UNDOC
HINT_NOP34	rm16	P6, UNDOC
HINT_NOP34	rm32	P6, UNDOC
HINT_NOP34	rm64	X64, UNDOC
HINT_NOP35	rm16	P6, UNDOC
HINT_NOP35	rm32	P6, UNDOC
HINT_NOP35	rm64	X64, UNDOC
HINT_NOP36	rm16	P6, UNDOC
HINT_NOP36	rm32	P6, UNDOC
HINT_NOP36	rm64	X64, UNDOC
HINT_NOP37	rm16	P6, UNDOC
HINT_NOP37	rm32	P6, UNDOC
HINT_NOP37	rm64	X64, UNDOC

HINT_NOP38	rm16	P6, UNDOC
HINT_NOP38	rm32	P6, UNDOC
HINT_NOP38	rm64	X64, UNDOC
HINT_NOP39	rm16	P6, UNDOC
HINT_NOP39	rm32	P6, UNDOC
HINT_NOP39	rm64	X64, UNDOC
HINT_NOP40	rm16	P6, UNDOC
HINT_NOP40	rm32	P6, UNDOC
HINT_NOP40	rm64	X64, UNDOC
HINT_NOP41	rm16	P6, UNDOC
HINT_NOP41	rm32	P6, UNDOC
HINT_NOP41	rm64	X64, UNDOC
HINT_NOP42	rm16	P6, UNDOC
HINT_NOP42	rm32	P6, UNDOC
HINT_NOP42	rm64	X64, UNDOC
HINT_NOP43	rm16	P6, UNDOC
HINT_NOP43	rm32	P6, UNDOC
HINT_NOP43	rm64	X64, UNDOC
HINT_NOP44	rm16	P6, UNDOC
HINT_NOP44	rm32	P6, UNDOC
HINT_NOP44	rm64	X64, UNDOC
HINT_NOP45	rm16	P6, UNDOC
HINT_NOP45	rm32	P6, UNDOC
HINT_NOP45	rm64	X64, UNDOC
HINT_NOP46	rm16	P6, UNDOC
HINT_NOP46	rm32	P6, UNDOC
HINT_NOP46	rm64	X64, UNDOC
HINT_NOP47	rm16	P6, UNDOC
HINT_NOP47	rm32	P6, UNDOC
HINT_NOP47	rm64	X64, UNDOC
HINT_NOP48	rm16	P6, UNDOC
HINT_NOP48	rm32	P6, UNDOC
HINT_NOP48	rm64	X64, UNDOC
HINT_NOP49	rm16	P6, UNDOC
HINT_NOP49	rm32	P6, UNDOC
HINT_NOP49	rm64	X64, UNDOC
HINT_NOP50	rm16	P6, UNDOC
HINT_NOP50	rm32	P6, UNDOC
HINT_NOP50	rm64	X64, UNDOC
HINT_NOP51	rm16	P6, UNDOC
HINT_NOP51	rm32	P6, UNDOC
HINT_NOP51	rm64	X64, UNDOC
HINT_NOP52	rm16	P6, UNDOC
HINT_NOP52	rm32	P6, UNDOC
HINT_NOP52	rm64	X64, UNDOC
HINT_NOP53	rm16	P6, UNDOC
HINT_NOP53	rm32	P6, UNDOC
HINT_NOP53	rm64	X64, UNDOC
HINT_NOP54	rm16	P6, UNDOC
HINT_NOP54	rm32	P6, UNDOC
HINT_NOP54	rm64	X64, UNDOC
HINT_NOP55	rm16	P6, UNDOC
HINT_NOP55	rm32	P6, UNDOC
HINT_NOP55	rm64	X64, UNDOC

HINT_NOP56	rm16	P6, UNDOC
HINT_NOP56	rm32	P6, UNDOC
HINT_NOP56	rm64	X64, UNDOC
HINT_NOP57	rm16	P6, UNDOC
HINT_NOP57	rm32	P6, UNDOC
HINT_NOP57	rm64	X64, UNDOC
HINT_NOP58	rm16	P6, UNDOC
HINT_NOP58	rm32	P6, UNDOC
HINT_NOP58	rm64	X64, UNDOC
HINT_NOP59	rm16	P6, UNDOC
HINT_NOP59	rm32	P6, UNDOC
HINT_NOP59	rm64	X64, UNDOC
HINT_NOP60	rm16	P6, UNDOC
HINT_NOP60	rm32	P6, UNDOC
HINT_NOP60	rm64	X64, UNDOC
HINT_NOP61	rm16	P6, UNDOC
HINT_NOP61	rm32	P6, UNDOC
HINT_NOP61	rm64	X64, UNDOC
HINT_NOP62	rm16	P6, UNDOC
HINT_NOP62	rm32	P6, UNDOC
HINT_NOP62	rm64	X64, UNDOC
HINT_NOP63	rm16	P6, UNDOC
HINT_NOP63	rm32	P6, UNDOC
HINT_NOP63	rm64	X64, UNDOC

Appendix C: NASM Version History

C.1 NASM 2 Series

The NASM 2 series supports x86-64, and is the production version of NASM since 2007.

C.1.1 Version 2.13.03

- Added AVX and AVX512 VAES* and VPCLMULQDQ instructions.
- Fixed missing dwarf record in x32 ELF output format.

C.1.2 Version 2.13.02

- Fix false positive in testing of numeric overflows.
- Fix generation of PEXTRW instruction.
- Fix ~~smartalign package which could trigger an error during optimization if the alignment code~~ expanded too much due to optimization of the previous code.
- Fix a case where negative value in TIMES directive causes panic instead of an error.
- Always finalize .debug_abbrev section with a null in dwarf output format.
- Support debug flag in section attributes for macho output format. See section 7.8.
- Support up to 16 characters in section names for macho output format.
- Fix ~~missing update of global BITS setting~~ SECTION directive specified bit size using output format-specific extensions (e.g. USE32 for the obj output format.)
- Fix the ~~incorrect generation of EVEX-encoded instructions when static mode decorators are specified~~ on scalar instructions, losing the decorators as they require EVEX encoding.
- Option ~~MM to quote dependency outputs according to Watcom Make conventions instead of POSIX~~ Make conventions. See section 2.1.11.
- The ~~obj output format now contains embedded dependency file information, unless disabled with~~ %pragma obj nodepend. See section 7.4.9.
- Fix generation of dependency lists.
- Fix a number of null pointer reference and memory allocation errors.
- Always generate symbol-relative relocations for the macho64 output format, at least some of the XCode/LLVM linker fails for section-relative relocations.

C.1.3 Version 2.13.01

- Fix ~~incorrect output for some types of FAR SEG references in the obj output format and possibly~~ other 16-bit output formats.
- Fix the address in the list file for an instruction containing a TIMES directive.
- Fix error with TIMES used together with an instruction which can vary in size, e.g.
- Fix breakage on some uses of the DZ pseudo-op.

C.1.4 Version 2.13

- Support the official forms of the UD0 and UD1 instructions.

- Allow self-segment-relative expressions in immediates and displacements, even when combined with an external or otherwise out-of-segment special symbol, e.g.:

```
extern foo
mov eax,[foo - $ + ebx]           ; Now legal
```

- Handle a 64-bit origin in NDISASM.
- NASM now generates parse output files for relevant output formats, if the underlying operating system supports them.
- The macho object format now supports the subsections_via_symbols and no_dead_strip directives, see section 7.8.4.
- The macho object format now supports the no_dead_strip, live_support and strip_static_syms section flags, see section 7.8.1.
- The macho object format now supports the dwarf debugging format, as required by newer toolchains.
- All warnings can now be suppressed if desired, warnings not otherwise part of any warning class are now considered its own warning class called other (e.g. -w-other). Furthermore, warning-as-error can now be controlled on a per warning class basis, using the syntax -w:error=**warning-class** and is equivalent to all the warning control options. See section 2.1.2 for the command-line options and warning classes and section 6.10 for the [WARNING] directive.
- Fix a number of bugs related to AVX-512 decorators.
- Significant improvements to building NASM with Microsoft Visual Studio in Mkfiles/msvc.mak. It is possible to build the full Windows installer binary, as long as the necessary prerequisites are installed; see Mkfiles/README
- To build NASM with custom modifications (table changes) from the git tree now requires Perl 5.8 at the very minimum, quite possibly higher version (Perl 5.24.1 tested). There is no requirement to have Perl on your system at all if all you want to do is build unmodified NASM from source.
- Fix the {z} decorator on AVX-512 VMOVDQ* instructions.
- Add new warnings for certain dangerous constructs which never ought to have been allowed. In particular, the RESB family of instructions should have been taking a critical expression.
- Fix the EVEX (AVX-512) versions of the VPBROADCAST, VPEXTR, and VPINSR instructions.
- Support contracted forms of additional instructions. As a general rule, if an instruction has a non-destructive source immediately after a destination register that isn't used as input, NASM supports omitting that source register, using the destination register as the value. This, among other things, makes it easier to convert SSE code to the equivalent AVX code:


```
addps xmm1,xmm0           ; SSE instruction
vaddps ymm1,ymm1,ymm0     ; AVX official long form
vaddps ymm1,ymm0         ; AVX contracted form
```
- Fix Codeview malformed compiler version record.
- Add the CLWB and COMMIT instructions. Note that the COMMIT instruction has been deprecated and will never be included in a shipping product; it is included for completeness.
- Add the %pragma preprocessor directive for soft-error directives.
- Add the RDPID instruction.

C.1.5 Version 2.12.02

- Fix preprocessor errors, especially %error and %warning, inside %if statements.
- Fix relative relocations in 32-bit Mach-O.
- More Codeview debug format fixes.
- If the `MASM_PTR` keyword is encountered, issue a warning. This is much more likely to indicate a MASM-ism encountered in NASM than it is a valid label. This warning can be suppressed with `-w-ptr`, the [warning] directive (see section 2.1.25) or by the macro definition `%define ptr $%?` (see section 4.1.5).
- When an error or warning comes from the expansion of a multi-line macro, display the file and line numbers for the expanded macros. Macros defined with `.nolist` do not get displayed.
- Add macros `ilog2fw()` and `ilog2cw()` to the ifunc macro package. See section 5.4.1.

C.1.6 Version 2.12.01

- Portability fixes for some platforms.
- Fix error when not specifying a list file.
- Correct the handling of macro-local labels in the Codeview debugging format.
- Add `CLZERO`, `MONITORX` and `MWAITX` instructions.

C.1.7 Version 2.12

- Major fixes to the mach backend (section 7.8) earlier versions would produce invalid symbol and relocations on a regular basis.
- Support for thread-local storage in Mach-O.
- Support for arbitrary sections in Mach-O.
- Fix wrong negative size treated as a big positive value passed into backend causing errors.
- Fix handling of zero-extending unsigned relocations, we have been printing wrong message and forgot to assign segment with predefined value before passing it into output format.
- Fix potential write of oversized (with size greater than allowed in output format) relocations.
- Portability fixes for building NASM with the LLVM compiler.
- Add support to Codeview version 8 (cv8) debug format for win32 and win64 formats in the COFF backend, see section 7.5.3.
- Allow 64-bit output in 32-bit only backends. Unsigned 64-bit relocations are zero-extended from 32-bit with a warning (suppressible via `-w-zext-reloc`), signed 64-bit relocations are an error.
- Line numbers in list files now correspond to the lines in the source files, instead of simply being sequential.
- There is now an official 64-bit (x64 a.k.a. x86-64) build for Windows.

C.1.8 Version 2.11.09

- Fix potential stack overwrite in macho32 backend.
- Fix relocation records in macho64 backend.
- Fix symbol lookup computation in macho64 backend.
- Adjust `.symtab` and `.rela.text` sections alignments to 8 bytes in elf64 backed.

- Fix section length computation in bin backend which led in incorrect relocation

C.1.9 Version 2.11.08

- Fix section length computation in bin backend which led in incorrect relocation
- Add warning for numeric preprocessor definitions passed via command line which might have unexpected results otherwise.
- Add ability to specify a module name record in rdoff linker with -mn option.
- Increase label length capacity up to 255 bytes in rdoff backend of FreePascal backend, which tends to generate very long labels for procedures.
- Fix segmentation failure when rip addressing is used in macho64 backend.
- Fix access out of memory when handling strings with a single grave. We have seen a similar problem in previous release but not all cases were covered.
- Fix NULL dereference in disassembled on BND instruction.

C.1.10 Version 2.11.07

- Fix 256 bit VMOVNTPS instruction.
- Fix -MD option handling, which was rather broken in previous release changing comm
- Fix access to uninitialized space when handling strings with a single grave.
- Fix nil dereference in handling memory reference parsing.

C.1.11 Version 2.11.06

- Update AVX512 instructions based on the Extension Reference (319433-021 Sept 2014)
- Fix the behavior of -MF and -MD options (Bugzilla 3392280)
- Updated Win32 Makefile to fix issue with build

C.1.12 Version 2.11.05

- Add --v as an alias for -v (see section 2.1.26), for command-line compatibility wi
- Fix a bug introduced in 2.11.04 where certain instructions would contain multiple REX prefixes, and thus be corrupt.

C.1.13 Version 2.11.04

- Removed an invalid error checking code. Sometimes memref only with displacement can also set an evex flag. For example:

```
vmovdqu32 [0xabcd]{k1}, zmm0
```
- Fixed a bug in disassembler that EVEX.L' I vector length was not matched when EVEX.b was set because it was simply considered as EVEC.RC. Separated EVEX.L' I case from EVEX.RC which is ignored in matching.

C.1.14 Version 2.11.03

- Fix a bug there REX prefixes were missing on instructions inside a TIMES statement

C.1.15 Version 2.11.02

- Add the XSAVEC, XSAVES and XRSTORS family instructions.
- Add the CLFLUSHOPT instruction.

C.1.16 Version 2.11.01

- Allow instructions which implicitly use XMM0 (VBLENDVPD, VBLENDVPS, PBLENDVB and SHA256RND\$2) to be specified without an explicit xmm0 on the assembly line. In other words, the following two lines produce the same output:

```
    vblendvpd xmm2,xmm1,xmm0      ; Last operand is fixed xmm0
    vblendvpd xmm2,xmm1           ; Implicit xmm0 omitted
```

- In the ELF backends, don't crash the assembler if section align is specified without

C.1.17 Version 2.11

- Add support for the Intel AVX-512 instruction set:
- 16 new, 512-bit SIMD registers. Total 32 (ZMM0 ~ ZMM31)
- 8 new opmask registers (K0~K7). One of 7 registers (K1~K7) can be used as an opmask for conditional execution.
- A new EVEX encoding prefix. EVEX is based on VEX and provides more capabilities: opmasks, broadcasting, embedded rounding and compressed displacements.
- opmask

```
    VDIVPD zmm0{k1}{z}, zmm1, zmm3 ; conditional vector operation
                                   ; using opmask k1.
                                   ; {z} is for zero-masking
```
- broadcasting

```
    VDIVPS zmm4, zmm5, [rbx]{1to16} ; load single-precision float and
                                   ; replicate it 16 times. 32 * 16 = 512
```
- embedded rounding

```
    VCVTSI2SD xmm6, xmm7, {rz-sae}, rax ; round toward zero. note that it
                                   ; is used as if a separate operand.
                                   ; it comes after the last SIMD operand
```
- Add support for ZWORD (512 bits), DZ and RESZ.
- Add support for the MPX and SHA instruction sets.
- Better handling of section redefinition.
- Generate manpages when running 'make dist'.
- Handle all token chains in mmacro params range.
- Support split [base,index] effective address:

```
    mov eax,[eax+8,ecx*4] ; eax=base, ecx=index, 4=scale, 8=disp
```

This is expected to be most useful for the MPX instructions.

- Support BND prefix for branch instructions (for MPX).
- The DEFAULT directive can now take BND and NOBND options to indicate whether all relevant branches should be getting BND prefixes. This is expected to be the normal for use.
- Add {evex}, {vex3} and {vex2} instruction prefixes to have NASM encode the corresponding instruction, if possible, with an EVEX, 3-byte VEX, or 2-byte VEX prefix, respectively.
- Support for section names longer than 8 bytes in Win32/Win64 COFF.
- The NOSPLIT directive by itself no longer forces a single register to become an index register unless it has an explicit multiplier.

```

    mov eax,[nosplit eax]      ; eax as base register
    mov eax,[nosplit eax*1]    ; eax as index register

```

C.1.18 Version 2.10.09

- Pregenerate man pages.

C.1.19 Version 2.10.08

- Fix VMOVNTDQA, MOVNTDQA and MOVLPD instructions.
- Fix collision for VGATHERQPS, VPGATHERQD instructions.
- Fix VPMOVSBQ, VGATHERQPD, VSPLW instructions.
- Add a bunch of AMD TBM instructions.
- Fix potential stack overwrite in numbers conversion.
- Allow byte size in PREFETCH instructions.
- Make manual pages up to date.
- Make F3 and F2 SSE prefixes to override 66.
- Support of AMD SVM instructions in 32 bit mode.
- Fix near offsets code generation for JMP, CALL instructions in long mode.
- Fix preprocessor parse regression when id is expanding to a whitespace.

C.1.20 Version 2.10.07

- Fix line continuation parsing being broken in previous version.

C.1.21 Version 2.10.06

- Always quote the dependency source names when using the automatic dependency generation options.
- If no dependency target name is specified via the -M or -M options, quote the default output name.
- Fix assembly of shift operations in CPU 8086 mode.
- Fix incorrect generation of explicit immediate byte for shift by 1 under certain c
- Fix assembly of the VPCMPGTQ instruction.
- Fix RIP-relative relocations in the macho64 backend.

C.1.22 Version 2.10.05

- Add the CLAC and STAC instructions.

C.1.23 Version 2.10.04

- Add back the inadvertently deleted 256-bit version of the VORPD instruction.
- Correct disassembly of instructions starting with byte 82 hex.
- Fix corner cases in token pasting, for example:

```

#define N 1e+++ 5
      dd N, 1e+5

```

C.1.24 Version 2.10.03

- Correct the assembly of the instruction:

```
XRELEASE MOV [absolute],AL
```

Previous versions would incorrectly generate `ESZ` for this instruction and issue a warning; correct behavior is to emit `F3 88 05`.

C.1.25 Version 2.10.02

- Add the `funct` macro package with integer functions; currently only integer logarithms (see section 5.4).
- Add the `RDSEED`, `ADCX` and `ADOX` instructions.

C.1.26 Version 2.10.01

- Add missing `VPMOVMASKB` instruction with `reg32`, `ymmreg` operands.

C.1.27 Version 2.10

- When optimization is enabled, `mov r64,imm` now optimizes to the shortest form possible:

```
mov r32,imm32          ; 5 bytes
mov r64,imm32          ; 7 bytes
mov r64,imm64          ; 10 bytes
```

To force a specific form, use the `STRICT` keyword, see section 3.7.

- Add support for the Intel AVX2 instruction set.
- Add support for Bit Manipulation Instructions 1 and 2.
- Add support for Intel Transactional Synchronization Extensions (TSX).
- Add support for x32 ELF (32-bit ELF with the CPU in 64-bit mode.) See section 7.9.
- Add support for bigendian UTF-16 and UTF-32. See section 3.4.5.

C.1.28 Version 2.09.10

- Fix `NSIS` script to protect uninstalled registry keys against corruption. It brings a few additional questions concerning installation procedure, but it is better than unpredictable file removal.

C.1.29 Version 2.09.09

- Fix initialization of section attributes of bin output format.
- Fix mach64 output format bug that crashes NASM due to NULL symbols.

C.1.30 Version 2.09.08

- Fix `__OUTPUT_FORMAT__` assignment when output driver alias is used. For example when `-f elf` is used `__OUTPUT_FORMAT__` must be set to `elf`, if `-f elf32` is used `__OUTPUT_FORMAT__` must be assigned accordingly, i.e. `elf32`. The rule applies to all output driver aliases. See section 4.11.6.

C.1.31 Version 2.09.07

- Fix attempts to close same file several times when `-a` option is used.
- Fixes for `VEXTRACTF128`, `VMASKMOVPS` encoding.

C.1.32 Version 2.09.06

- Fix missed section attribute initialization in bin output target.

C.1.33 Version 2.09.05

- Fix arguments encoding for VPEXTRW instruction.
- Remove invalid form of VPEXTRW instruction.
- Add VLDDQU as alias for VLDQQU to match specification.

C.1.34 Version 2.09.04

- Fix incorrect labels offset for VEX instructions.
- Eliminate bogus warning on implicit operand size override.
- %if term could not handle 64 bit numbers.
- The COFF backend was limiting relocation numbers to 64 bit even if there were away more relocations.

C.1.35 Version 2.09.03

- Print %macro name inside %rep blocks on error.
- Fix preprocessor expansion behaviour. It happened sometime too early and sometimes simply wrong. Move behaviour back to the origins (down to NASM 2.05.01).
- Fix uninitialized data dereference on OMF output format.
- Issue warning on unterminated %{ construct.
- Fix for documentation typo.

C.1.36 Version 2.09.02

- Fix reversed tokens when %deftok produces more than one output token.
- Fix segmentation fault on disassembling some VEX instructions.
- Missing %endif did not always cause error.
- Fix typo in documentation.
- Compound context local preprocessor single line macro identifiers were not expanded early enough and as result lead to unresolved symbols.

C.1.37 Version 2.09.01

- Fix NULL dereference on missed %deftok second parameter.
- Fix NULL dereference on invalid %substr parameters.

C.1.38 Version 2.09

- Fixed assignment the magnitude of %rep counter. It is limited to 62 bits now.
- Fixed NULL dereference if argument of %strlen resolves whitespace. For example if nonexistent macro parameter is used.
- %ifenv, %elifenv, %ifnenv, and %elifnenv directives introduced. See section 4.4.9.
- Fixed NULL dereference if environment variable is missed.
- Updates of new AVX v7 Intel instructions.

- PUSH imm32 is now officially documented.
- Fix for encoding the LFS, LGS and LSS in 64-bit mode.
- Fixes for compatibility with OpenWatcom compiler and DOS 8.3 file format limitations.
- Macros parameters range expansion introduced. See section 4.3.4.
- Backward compatibility on expanding of local single macros restored.
- 8 bit relocations for elf and bin output formats are introduced.
- Short intersegment jumps are permitted now.
- An alignment more than 64 bytes are allowed for win32, win64 output formats.
- SECTALIGN directive introduced. See section 4.11.13.
- nojmp option introduced in smartalign package. See section 5.2.
- Short aliases win, elf and macho for output formats are introduced. Each stands for win32, elf32 and macho32 accordingly.
- Faster handling of missing directives implemented.
- Various small improvements in documentation.
- No hang anymore if unable to open malloc.log file.
- The environments without vsnprintf function are able to build nasm again.
- AMD LWP instructions updated.
- Tighten EA checks. We warn a user if there overflow in EA addressing.
- Make `optimize` the default optimization level for the legacy behavior, specify `0` explicitly. See section 2.1.23.
- Environment variables read with `%!` or tested with `%ifenv` can now contain non-identifier characters if surrounded by quotes. See section 4.10.2.
- Add new standard macro package `usefp` for floating-point convenience macros. See section 5.3.

C.1.39 Version 2.08.02

- Fix crash under certain circumstances when using the `%+` operator.

C.1.40 Version 2.08.01

- Fix the `%use` statement, which was broken in 2.08.

C.1.41 Version 2.08

- A number of enhancements/fixes in macros area.
- Support for converting strings to tokens. See section 4.1.9.
- Fuzzy operand size logic introduced.
- Fix COFF stack overrun on too long export identifiers.
- Fix Macho-O alignment bug.
- Fix crashes with `-fwin32` on file with many exports.
- Fix stack overrun for too long `[DEBUG id]`.
- Fix incorrect `sbyte` usage in `IMUL` (hit only if optimization flag passed).

- Append ending token for .stabs records in the ELF output format.
- New NSIS script which uses ModernUI and MultiUser approach.
- Visual Studio 2008 NASM integration (rules file).
- Warn a user if a constant is too long (and as result will be stripped).
- The obsoleted pre-XOP AMD SSE5 instruction set which was never actualized was removed.
- Fix stack overrun on too long error file name passed from the command line.
- Bind symbols to the text section by default (increase SECTION directive was omitted) in the ELF output format.
- Fix sync points array index wrapping.
- A few fixes for FMA4 and XOP instruction templates.
- Add AMD Lightweight Profiling (LWP) instructions.
- Fix the offset for %arg in 64-bit mode.
- An undefined local macro (%\$) no longer matches a global macro with the same name.
- Fix NULL dereference on too long local labels.

C.1.42 Version 2.07

- NASM is now under the 2-clause BSD license. See section 1.1.1.
- Fix the section type for the .strtab section in the elf64 output format.
- Fix the handling of COMMON directives in the obj output format.
- New ~~with and re~~ output formats, these are variants of the bin output format which output Intel hex and Motorola S-records, respectively. See section 7.2 and section 7.3.
- ~~rd~~ ~~f2ih~~ replaced with an enhanced ~~rd~~ ~~f2bin~~, which can output binary, COM, Intel hex or Motorola S-records.
- The Windows installer now puts the NASM directory first in the PATH of the "NASM S...
- Revert the early expansion behavior of %+ to pre-2.06 behavior: %+ is only expanded...
- Yet another Mach-O alignment fix.
- Don't delete the list file on errors. Also, include error and warning information...
- Support for 64-bit Mach-O output, see section 7.8.
- Fix assert failure on certain operations that involve strings with high-bit bytes.

C.1.43 Version 2.06

- This release is dedicated to the memory of Charles A. Crayne, long time NASM developer as well as moderator of comp.lang.asm.x86 and author of the book *Serious Assembler*. We miss you, Chuck.
- Support for indirect macro expansion (%[...]). See section 4.1.3.
- %pop can now take an argument, see section 4.7.1.
- The argument to %use is no longer macro-expanded. Use %[...] if macro expansion is...
- Support for thread-local storage in ELF32 and ELF64. See section 7.9.4.
- Fix crash on %ifmacro without an argument.

- Correct the arguments to the POPCNT instruction.
- Fix section alignment in the Mach-O format.
- Update AVX support to version 5 of the Intel specification.
- Fix the handling of accesses to context-local macros from higher levels in the compiler.
- Treat `WAIT` as a prefix rather than an instruction, thereby allowing constructs like `016SAVE` to work correctly.
- Support for structures with a non-zero base offset. See section 4.11.10.
- Correctly handle preprocessor token concatenation (see section 4.3.9) involving floating-point numbers.
- The PINSR series of instructions have been corrected and rationalized.
- Removed AMD SSE5, replaced with the new XOP/FMA4/CVT16 (rev 3.03) spec.
- The ELF backends no longer automatically generate a `.comment` section.
- Add additional "well-known" ELF sections with default attributes. See section 7.9.

C.1.44 Version 2.05.01

- Fix the `-w/-W` option parsing, which was broken in NASM 2.05.

C.1.45 Version 2.05

- Fix redundant REX.W prefix on `JMP reg64`.
- Make the behaviour of `-O0` match NASM 0.98 legacy behavior. See section 2.1.23.
- `-w-user` can be used to suppress the output of `%warning` directives. See section 2.1.23.
- Fix bug where `ALIGN` would issue a full alignment datum instead of zero bytes.
- Fix offsets in list files.
- Fix `%include` inside multi-line macros or loops.
- Fix error where NASM would generate spurious warnings on valid optimizations of immediate values.
- Fix arguments to a number of the CVT SSE instructions.
- Fix RIP-relative offsets when the instruction carries an immediate.
- Massive overhaul of the ELF64 backend for spec compliance.
- Fix the Geode PFRCPV and PFRSQRTV instruction.
- Fix the SSE 4.2 CRC32 instruction.

C.1.46 Version 2.04

- Sanitize macro handling in the `%error` directive.
- New `%warning` directive to issue user-controlled warnings.
- `%error` directives are now deferred to the final assembly phase.
- New `%fatal` directive to immediately terminate assembly.
- New `%strcat` directive to join quoted strings together.
- New `%use` macro directive to support standard macro directives. See section 4.6.4.

- Excess default parameters to %macro now issues a warning by default. See section 4.3.11.
- Fix %ifn and %elifn.
- Fix nested %else clauses.
- Correct the handling of nested %reps.
- New %unmacro directive to undeclare a multi-line macro. See section 4.3.12.
- Builtin macro __PASS__ which expands to the current assembly pass. See section 4.1.1.
- __utf16__ and __utf32__ operators to generate UTF-16 and UTF-32 strings. See section 4.1.1.
- Fix bug in case-insensitive matching when compiled on platforms that don't use the configure script. Of the official release binaries, that only affected the OS/2 binary.
- Support for x87 packed BCD constants. See section 3.4.7.
- Correct the LTR and SLDT instructions in 64-bit mode.
- Fix unnecessary REX.W prefix on indirect jumps in 64-bit mode.
- Add AVX versions of the AES instructions (VAES...).
- Fix the 256-bit FMA instructions.
- Add 256-bit AVX stores per the latest AVX spec.
- VIA XCRYPT instructions can now be written either with or without REP, apparently different versions of the VIA spec wrote them differently.
- Add missing 64-bit MOVNTI instruction.
- Fix the operand size of VMREAD and VMWRITE.
- Numerous bug fixes, especially to the AES, AVX and VTX instructions.
- The optimizer now always runs until it converges. It also runs even when disabled, but doesn't optimize. This allows most forward references to be resolved properly.
- %pushbongemeeds context identifier, omitting the context identifier results in an anonymous context.

C.1.47 Version 2.03.01

- Fix buffer overflow in the listing module.
- Fix the handling of hexadecimal escape codes in `...` strings.
- The Postscript/PDF documentation has been reformatted.
- The -F option now implies -g.

C.1.48 Version 2.03

- Add support for Intel AVX, CLMUL and FMA instructions, including YMM registers.
- dy, resy and yword for 32-byte operands.
- Fix some SSE5 instructions.
- Intel INVEPT, INVVPID and MOVBE instructions.
- Fix checking for critical expressions when the optimizer is enabled.
- Support the DWARF debugging format for ELF targets.
- Fix optimizations of signed bytes.

- Fix operation on bigendian machines.
- Fix buffer overflow in the preprocessor.
- SAFSEH support for Win32, IMAGEREL for Win64 (SEH).
- `__typeof__` to refer to the name of a macro itself. In particular, `__typeof__` can be used to make a keyword "disappear".
- New options for dependency generation: `-MD`, `-MF`, `-MP`, `-MT`, `-MQ`.
- New preprocessor directives `%pathsearch` and `%depend`; `INCBIN` reimplemented as a macro.
- `%include` now resolves macros in a sane manner.
- `%substr` can now be used to get other than one-character substrings.
- New type of character/string constants, using backquotes ``...`` which support C-style escape sequences.
- `%defstr` and `%idefstr` to stringize macro definitions before creation.
- Fix forward references used in `EQU` statements.

C.1.49 Version 2.02

- Additional fixes for MMX operands with explicit word tags as well as (hopefully) SSE operands with oword.
- Fix handling of truncated strings with `DO`.
- Fix segfaults due to memory overwrites when floating-point constants were used.
- Fix segfaults due to missing include files.
- Fix OpenWatcom Makefiles for DOS and OS/2.
- Add autogenerated instruction list back into the documentation.
- ELF: Fix segfault when generating stabs, and no symbols have been defined.
- ELF: Experimental support for DWARF debugging information.
- New compile date and time standard macros.
- `%ifnum` now returns true for negative numbers.
- New `%iftoken` test for a single token.
- New `%ifempty` test for empty expansion.
- Add support for the XSAVE instruction group.
- Makefile for Netware/gcc.
- Fix issue with some warnings getting emitted way too many times.
- Autogenerated instruction list added to the documentation.

C.1.50 Version 2.01

- Fix the handling of MMX registers with explicit word tags on memory (broken in 2.00 due to 64-bit changes.)
- Fix the `PREFETCH` instructions.
- Fix the documentation.
- Fix debugging info when using `-f elf` (backwards compatibility alias for `-f elf32`).

- Man pages for rdoff tools (from the Debian project.)
- ELF: handle large numbers of sections.
- Fix corrupt output when the optimizer runs out of passes.

C.1.51 Version 2.00

- Added c99 data-type compliance.
- Added general x86-64 support.
- Added win64 (x86-64 COFF) output format.
- Added `__BITS__` standard macro.
- Renamed the elf output format to elf32 for clarity.
- Added elf64 and macho (MacOS X) output formats.
- Added Numeric constants in dq directive.
- Added oword, do and reso pseudo operands.
- Allow underscores in numbers.
- Added 8-, 16- and 128-bit floating-point formats.
- Added binary, octal and hexadecimal floating-point.
- Correct the generation of floating-point constants.
- Added floating-point option control.
- Added Infinity and NaN floating point support.
- Added ELF Symbol Visibility support.
- Added setting OSABI value in ELF header directive.
- Added Generate Makefile Dependencies option.
- Added Unlimited Optimization Passes option.
- Added %IFN and %ELIFN support.
- Added Logical Negation Operator.
- Enhanced Stack Relative Preprocessor Directives.
- Enhanced ELF Debug Formats.
- Enhanced Send Errors to a File option.
- Added SSSE3, SSE4.1, SSE4.2, SSE5 support.
- Added a large number of additional instructions.
- Significant performance improvements.
- `-w+warning` and `-w-warning` can now be written as `-Wwarning` and `-Wno-warning`, respectively. See section 2.1.25.
- Add `-w+error` to treat warnings as errors. See section 2.1.25.
- Add `-w+all` and `-w-all` to enable or disable all suppressible warnings. See section 2.1.25.

C.2 NASM 0.98 Series

The 0.98 series was the production versions of NASM from 1999 to 2007.

C.2.1 Version 0.98.39

- fix buffer overflow
- fix outas86's .bss handling
- "make spotless" no longer deletes config.h.in.
- %(el)if(n)idn insensitivity to string quotes difference (#809300).
- (nasm.c) __OUTPUT_FORMAT__ changed to string value instead of symbol.

C.2.2 Version 0.98.38

- Add Makefile for 16-bit DOS binaries under Open Watcom, and modify mkdep.plt to be able to generate completely pathless dependencies as required by Open Watcom make (it supports path searches, but not explicit paths.)
- Fix the STR instruction.
- Fix the ELF output format, which was broken under certain circumstances due to the addition of stabs support.
- Quick-fix Borland format debug-info for -f obj
- Fix for %rep with no arguments (#560568)
- Fix concatenation of preprocessor function call (#794686)
- Fix long label causes coredump (#677841)
- Use autoheader as well as autoconf to keep configure from generating ridiculously long command lines.
- Make sure that the ELF format, which supports debugging output, actually will suppress debugging output when -g not specified.

C.2.3 Version 0.98.37

- Paths given in -I switch searched for incbin-ed as well as %include-ed files.
- Added stabs debugging for the ELF output format, patch from Martin Wawro.
- Fix output/outbin.c to allow origin > 80000000h.
- Make -U switch work.
- Fix the use of relative offsets with explicit prefixes, e.g. a32 loop foo.
- Remove backslash().
- Fix the SMSW and SLDT instructions.
- -O2 and -O3 are no longer aliases for -O10 and -O15. If you mean the latter, please

C.2.4 Version 0.98.36

- Update rdiff - librarian/archiver - common rec - docs!
- Fix signed/unsigned problems.
- Fix JMP FAR label and CALL FAR label.
- Add new multisection support - map files - fix align bug
- Fix sysexit, movhps/movlps reg, reg bugs in insns.dat
- Q or O suffixes indicate octal

- Support Prescott new instructions (PNI).
- Cyrix XSTORE instruction.

C.2.5 Version 0.98.35

- Fix build failure on 16-bit DOS (Makefile.bc3 workaround for compiler bug.)
- Fix dependencies and compiler warnings.
- Add "const" in a number of places.
- Add -X option to specify error reporting format (use -Xvc to integrate with Microsoft Visual C++)
- Minor changes for code legibility.
- Drop use of tmpnam() in rdoff (security fix.)

C.2.6 Version 0.98.34

- Correct additional address-size vs. operand-size confusions.
- Generate dependencies for all Makefiles automatically.
- Add support for implemented (but theoretically available) registers such as rax and r5. Segment registers 6 and 7 are called segr6 and segr7 for the operations which they can be used for.
- Correct some disassemble bugs related to redundant address-size prefixes. Some work still remains in this area.
- Correctly generate an error for things like "SEG eax".
- Add the JMPE instruction, enabled by "CPU IA64".
- Correct compilation on newer gcc/glibc platforms.
- Issue an error on things like "jmp far eax".

C.2.7 Version 0.98.33

- New `NASM_PATCHLEVEL` and `NASM_VERSION_ID` standard macros to output the version query macro `version.plt` understands `X.YY.plt.WW.X.YY.ZZ.plt.WW` as version number, equivalent to `X.YY.ZZ.WW` (or `X.YY.0.WW`, as appropriate).
- New keyword `"strict"` to disable the optimization of specific operands.
- Fix the handling of size overrides with `JMP` instructions (instructions such as `"jmp`
- Fix the handling of `"ABSOLUTE label"`, where `"label"` points into a relocatable segment.
- Fix `OBJ` output format with lots of externs.
- More documentation updates.
- Add `-Ov` option to get verbose information about optimizations.
- Undo a braindead change which broke `%elif` directives.
- Makefile updates.

C.2.8 Version 0.98.32

- Fix NASM crashing when %macro directives were left unterminated.
- Lots of documentation updates.
- Complete rewrite of the PostScript/PDF documentation generator.
- The MS Visual C++ Makefile was updated and corrected.

- Recognize .rodata as a standard section name in ELF.
- Fix some obsolete Perl4-isms in Perl scripts.
- Fix configure.in to work with autoconf 2.5x.
- Fix a couple of "make cleaner" misses.
- Make the normal "./configure && make" work with Cygwin.

C.2.9 Version 0.98.31

- Correctly build in a separate object directory again.
- Derive all references to the version number from the version file.
- New standard macros `__NASM_SUBMINOR__` and `__NASM_VER__` macros.
- Lots of Makefile updates and bug fixes.
- New `%ifmacro` directive to test for multiline macros.
- Documentation updates.
- Fixes for 16-bit OBJ format output.
- Changed the NASM environment variable to `NASMENV`.

C.2.10 Version 0.98.30

- Changed `dofiles` to not completely remove old READMEs and wishlist files, incorporating all information in CHANGES and TODO.
- I waited a long time to rename `zoutieeee.c` to (original) `outieeee.c`
- moved all output modules to `output/` subdirectory.
- Added 'make strip' target to strip debug info from `nasm` & `ndisasm`.
- Added `INSTALL` file with installation instructions.
- Added `-v` option description to `nasm` man.
- Added `dist` makefile target to produce source distributions.
- 16-bit support for ELF output format (GNU extension, but useful.)

C.2.11 Version 0.98.28

- Fastcooked this for Debian's Woody release. Frank applied the NCBI bug patch to 0.98.25 and called it 0.98.28 to not confuse poor little apt-get.

C.2.12 Version 0.98.26

- Reorganised files even better from 0.98.25alt

C.2.13 Version 0.98.25alt

- Prettified the source tree. Moved files to more reasonable places.
- Added `findleak.pl` script to `misc/` directory.
- Attempted to fix doc.

C.2.14 Version 0.98.25

- Line continuation character `\`.
- Docs inadvertantly reverted - "dos packaging".

C.2.15 Version 0.98.24p1

- `FIXME`: Someone, document this please.

C.2.16 Version 0.98.24

- Documentation - Ndisasm doc added to Nasm.doc.

C.2.17 Version 0.98.23

- Attempted to remove `rdoff version1`
- Lino Mastrodomenico's patches to `preproc.c` (`$$$ bug?`).

C.2.18 Version 0.98.22

- Update `rdoff2` - attempt to remove `v1`.

C.2.19 Version 0.98.21

- Optimization fixes.

C.2.20 Version 0.98.20

- Optimization fixes.

C.2.21 Version 0.98.19

- H. J. Lu's patch back out.

C.2.22 Version 0.98.18

- Added `".rdata"` to `"-f win32"`.

C.2.23 Version 0.98.17

- H. J. Lu's "bogus elf" patch. (Red Hat problem?)

C.2.24 Version 0.98.16

- Fix whitespace before `"[section ..."` bug.

C.2.25 Version 0.98.15

- `Rdoff` changes (?).
- Fix fixes to memory leaks.

C.2.26 Version 0.98.14

- Fix memory leaks.

C.2.27 Version 0.98.13

- There was no 0.98.13

C.2.28 Version 0.98.12

- Update optimization (new function of `"-O1"`)
- Changes to `test/bintest.asm` (?).

C.2.29 Version 0.98.11

- Optimization changes.
- Ndisasm fixed.

C.2.30 Version 0.98.10

- There was no 0.98.10

C.2.31 Version 0.98.09

- Add multiple sections support to "-f bin".
- Changed GLOBAL_TEMP_BASE in outelf.c from 6 to 15.
- Add "-v" as an alias to the "-r" switch.
- Remove "#ifdef" from Tasm compatibility options.
- Remove redundant size-overrides on "mov ds, ex", etc.
- Fixes to SSE2, other insns.dat (?).
- Enable uppercase "I" and "P" switches.
- Case insensitive "seg" and "wrt".
- Update install.sh (?).
- Allocate tokens in blocks.
- Improve "invalid effective address" messages.

C.2.32 Version 0.98.08

- Add "%strlen" and "%substr" macro operators
- Fixed broken c16.mac.
- Unterminated string error reported.
- Fixed bugs as per 0.98bf

C.2.33 Version 0.98.09b with John Coffman patches released 28-Oct-2001

Changes from 0.98.07 release to 98.09b as of 28-Oct-2001

- More closely compatible with 0.98 when 00 is specified. Not strictly identical, since backward branches in range of short offset are recognized and signed byte values with explicit size specification will be assembled as a single byte.
- More forgiving with the BUS instruction. 0.98 requires size to be specified always. 0.98.09b will imply the size from the current BITS setting (16 or 32).
- Changed definition of the optimization flag:
 - 00 strict two-pass assembly, JMP and Jcc are handled more like 0.98, except that backward JMPs are short, if possible.
 - 01 strict two-pass assembly, but forward branches are assembled with code guaranteed to reach; may produce larger code than -00, but will produce successful assembly more often if branch offset sizes are not specified.
 - 02 multi-pass optimization, minimize branch offsets; also will minimize signed immediate bytes, overriding size specification.

-O3 like -O2, but more passes taken, if needed

C.2.34 Version 0.98.07 released 01/28/01

- Added Stepan Denis SSE2 instructions & a working version of the code some earlier versions were based on broken code - sorry 'bout that. version "0.98.07"
- Cosmetic modifications to nasm.c, nasm.h, AUTHORS, MODIFIED

C.2.35 Version 0.98.06f released 01/18/01

- Add "metalbrain"s jecxz bug fix in insns.dat
- Alter nasmdoc.src to match - version "0.98.06f"

C.2.36 Version 0.98.06e released 01/09/01

- Removed the 'outforms.h' file it appears to be someone's old backup of 'outform.h' version "0.98.06e"
- fbk finally added the fix for the "multiple %include bug", known since 7/27/99 reported originally(?) and sent to by Austin Lunnen here report that John Fin had fix within the day. Here it is...
- Nelson Rush resigns from the group Big thanks to Nelson for his leadership and enthusiasm in getting these changes incorporated into Nasm!
- fbk - [list +], [list -] directives - ineptly implemented, should be re-written or
- Brian Raiter / fbk - "elfso bug" fix - applied to aoutb format as well - testing m
- James Seter - -postfix, -prefix command line switches.
- Yuri Zaporozhets - rdoff utility changes.

C.2.37 Version 0.98p1

- GAS-like palign (Panos Minos)
- FIXME: Someone, fill this in with details

C.2.38 Version 0.98bf (bug-fixed)

- Fixed elf and aout bugs shared libraries multiple "%include" bug in -fbj "jcxz, jecxz bug unrecognized option bug in ndisasm

C.2.39 Version 0.98.03 with John Coffman's changes released 27-Jul-2000

- Added signed byte optimizations for the x86 class of instructions ADC, ADD, AND, CMP, OR, SBB, SUB, XOR, when used as ADD reg16, imm or ADD reg32, imm. Also optimization of signed byte form of 'PUSH imm' and 'IMUL reg, imm' / 'IMUL reg, reg, imm.' No size specification is
- Added multi-pass RPN for offset optimization. Offset of forward references will preferentially use the short form, without the need of code specific size (short or near) for the branch. Added instructions of Jcc label to use the form Jnotc \$+3/JMP label' in case where short offset is out of bounds. If compiling for a 386 or higher CPU, then the 386 form of Jcc will be used. This feature is controlled by a new command-line switch! "O", (upper case letter O) "-O0" reverts the assembler to no extra optimization passes, "-O1" allows up to 5 extra passes, and "-O2" (default), allows up to 10 extra optimization passes.

- Added new directive 'cpuXXX', where XXX is any of 8086,186,286,386,486,586,pentium,686,PPROP2P3KatmaiAlphasensitiveAl instructions will be selected only if they apply to the selected cpu or lower. Corrected a couple of bugs in cpu-dependence in 'insns.
- Added to standard.mac 'thuse16anduse32formofthebit16/32 directive This is something new, just conforms to a lot of other assemblers. (minor)
- Changed label allocation from 20/371000 labels (200K+132/371000 labels) makes running under DOS much easier Since additional label space is allocated dynamically this should have an effect on large programs with lots of labels The 37 is prime, believed to be better for hashing. (minor)

C.2.40 Version 0.98.03

"Integrated patch file 98-0.98.03 in version 98.03 for historical reasons 9: 98.02 crashed."
 --John Coffman <johninsd@san.rr.com>, 27-Jul-2000

- Kendall Bennett's SciTech MGL changes
- Note that you must define "TASM_COMPAT" at compile-time to get the TasmIdealMode compatibility.
- All changes can be compiled in and out using the TASM_COMPAT macros, and when compiled without TASM_COMPAT defined we get the exact same binary as the unmodified 0.98 so
- standard.mac, macros.c: Added macros to ignore TASM directives before first include
- nasm.h: Added extern declaration for tasm_compatible_mode
- nasm.c: Added global variable tasm_compatible_mode
- Added command line switch for TASM compatible mode (-t)
- Changed version command line to reflect when compiled with TASM additions
- Added response file processing to allow arguments to single line response file @resp rather than -@resp for NASM format).
- labels.c: Changes islocal() macro to support TASM style @@local labels.
- Added islocalchar() macro to support TASM style @@local labels.
- parser.c Added support for TASM style memory references (i.e. mov [DWORD eax], 1) rather than the NASM style mov DWORD [eax], 10).
- preproc.c: Added new directives, %arg, %local, %stacksize to directives table
- Added support for TASM style directives without a leading % symbol.
- Integrated a block of changes from Andrew Zabolotny <bit@eltech.ru>:
- A new keyword %xdefine and its case-insensitive counterpart %ixdefine. They work almost the same way as %define and %idefine but expand the definition immediately, not on the invocation. Something like a cross between %define and %assign. The "x" suffix stands for "eXpand", so "xdefine" can be deciphered as "expand-and-define". Thus you can do t

```
%assign ofs      0

%macro  arg      1
    %xdefine %1 dword [esp+ofs]
    %assign ofs ofs+4
%endmacro
```

- Changed the place where the expansion of `$$name` macros are expanded. Now they are converted into `._@ctxnum.name` for when tokenizing, so there are no quirks as before when using `$$name` arguments to macros, in macros etc. For example:

```
%macro abc 1
    %define %1 hello
%endm

abc    $$here
$$here
```

Now last line will be expanded into `hello` as expected. This also allows for lots of goodies, good example are extended "proc" macros included in this archive.

- Added a check for "cstk" in `smacro_defined()` before calling `get_ctx()` - this allows

```
%ifdef $$abc
%endif
```

to work without warnings even in no context.

- Added check for "cstk" in `%if*ctx` and `%elif*ctx` directives, this allows to use `%ifctx` without excessive warnings. If there is no active context, `%ifctx` goes through "false" branch.
- Removed `useerror` prefix with `%error` directive, it just clutters the output and is absolutely non-functionality. Besides, this allows to write macros that do something different from built-in functions in any way.
- Added expansion of string that is output by `%error` directive. Now you can do things

```
%define hello(x) Hello, x!

%define $$name andy
%error "hello($$name)"
```

Same happened with `%include` directive.

- Now all directives that expect a identifier will try to expand and concatenate everything without whitespaces in between before usage. For example, with "unfixed" nasm the commands

```
%define $$abc hello
%define __$abc goodbye
__$abc
```

would produce "incorrect" output: last line will expand to

```
hello goodbyehello
```

Not quite what you expected, eh? - The answer is that preprocessor treats `$$define` construct as if it would be

```
%define __ $$abc goodbye
```

(note the white space between `__` and `$$abc`). After my "fix" it will "correctly" expand to

```
goodbye
```

as expected. Note that I use quotes around words "correct", "incorrect" etc. because this is rather a feature, not a bug, however current behaviour is more logical (and allows more advanced macro usage :-).

Same change was applied to:
`%push, %macro, %imacro, %define, %idefine, %xdefine, %ixdefine,`
`%assign, %iassign, %undef`

- A new directive `{WARNING+|-}` warning-id have been added. It works only if the assembly phase is enabled (i.e. it doesn't work with `nasm -e`).
- A new warning type `macro-selfref`. By default this warning is disabled, when enabled NASM warns when a macro self-references itself; for example the following source:

```
[WARNING macro-selfref]
```

```
%macro          push    1-*
    %rep        %0
        push    %1
        %rotate 1
    %endrep
%endmacro
```

```
        push    eax,ebx,ecx
```

will produce a warning, but if we remove the first line we won't see it anymore (which is The Right Thing To Do {tm} IMHO since C preprocessor eats such constructs without warnings a

- Added a new error routine to preprocessor which always will use `ERR_PASS` in severity_code. This removes annoying repeated errors on first and second passes from preprocessor.
- Added the `%+` operator in single-line macros for concatenating two identifiers. Usage

```
%define _myfunc _otherfunc
%define cextern(x) _ %+ x
cextern (myfunc)
```

After first expansion, third line will become `_myfunc`. After this expansion performed against it becomes `"_otherunc"`.

- Now if preprocessor is in a non-emitting state, no warning or error will be emitted.

```
%if 1
        mov     eax,ebx
%else
    put anything you want between these two brackets,
    even macro-parameter references %1 or local
    labels %$zz or macro-local labels %%zz - no
    warning will be emitted.
%endif
```

- Context-local variables expansion as a resort are looked up in outer contexts. For example, the following piece:

```
%push    outer
%define  %$a [esp]

        %push    inner
        %$a
        %pop

%pop
```

will expand correctly the fourth line to `[esp]`; if we'll define another `%$` inside the inner context it will take precedence over outer definition. However, this modification has been applied only to `expand_macro` and `macro_define` as consequence expansion looks in outer contexts but `%ifdef` won't look in outer contexts.

This behaviour is needed because we don't want nested contexts & a macro already defined local macros. Example:

```
%define %$arg1 [esp+4]
test    eax,eax
if      nz
        mov     eax,%$arg1
endif
```

In this example the "if" macro enters into the "if" context, so %\$arg1 is no valid anymore inside "if". Of course it could be worked around by using explicitly %%\$arg1 but this is

- Fixed memory leak in %undef. The origline wasn't freed before exiting on success.
- Fixed a preprocessor whel line expanded to empty set of tokens. This happens for example in the following case:

```
#define SOMETHING
SOMETHING
```

C.2.41 Version 0.98

All changes since NASM 0.98p3 have been produced by H. Peter Anvin <hpa@zytor.com>.

- The documentation comment delimiter is
- Allow EQU definitions to refer to external labels; reported by Pedro Gimeno.
- Re-enable support for RDOFF v1; reported by Pedro Gimeno.
- Updated License file per OK from Simon and Julian.

C.2.42 Version 0.98p9

- Updated documentation (although the instruction references will have to wait until we hold up the 0.98 release for it.)
- Verified that the NASM implementation of the EXTRN and MOVMSK instructions is correct. The encoding differs from what the Intel manuals document, but the Pentium II behaviour matches NASM, not the Intel manuals.
- Fix handling of implicit sizes in PSHUFW and PINSRW, reported by Stefan Hoffmeister
- Resurrect the -s option, which was removed when changing the diagnostic output to

C.2.43 Version 0.98p8

- Fix for "DB" when NASM is running on a bigendian machine.
- Invoke insns.pl once for each output script, making Makefile.in legal for "make -j"
- Improve the Unix configure-based makefiles to make package creation easier.
- Included an RPM spec file for building RPM (Red Hat Package Manager) packages on Linux or Unix systems.
- Fix Makefile dependency problems.
- Change src/rdsr.pl to include sectioning information in info output; required for
- Updated the RDOFF distribution to version 2 from rules, minor massaging to make it compile in my environment.
- Split doc files that can be built by anyone with a Perl interpreter off into a separate
- "Dress rehearsal" release!

C.2.44 Version 0.98p7

- Fixed opcodes with a third byte-sized immediate argument to complain if given "byte" in the immediate.
- Allowed `%undef` to remove single-line macros with arguments. This matches the behaviour of `#undef` in the C preprocessor.
- Allowed `-d`, `-u`, and `-p` to be specified as `-D`, `-U`, and `-P` for compatibility with most compilers and preprocessors. This allows Makefile options to be shared between `cc` and `nasm`.
- Minor cleanups.
- Went through the list of Katmai instructions and hopefully fixed the (rather few) bugs.
- (Hopefully) fixed a number of assembler bugs related to ambiguous instructions (disambiguated by `-p`) and SSE instructions with `REP`.
- Fixed a bug reported by Mark Junger: `"call dword 0x12345678"` should work and may add an `OSP` (affected `CALL`, `JMP`, `Jcc`).
- Fix for environments when `"stderr"` isn't a compile-time constant.

C.2.45 Version 0.98p6

- Took official coordination of the 0.98 release, dropping the 3.x notation. Skipped `p4` and `p5` to avoid confusion with John Fine's J4 and J5 releases.
- Updated the documentation, however it still doesn't include documentation for the various new instructions. Somehow wonder if it makes sense to have an instruction set reference in the assembler manual when Intel et al have PDF versions of their manuals online.
- Recognize `"idt"` or `"centaur"` for the `-p` option to `ndisasm`.
- Changed error messages back to `stderr` where they belong, but added an option to redirect them elsewhere (the DOS shell cannot redirect `stderr`.)
- `-M` option to generate Makefile dependencies (based on code from Alex Verstak.)
- `%undef` preprocessor directive, and `-u` option, that undefines a single-line macro.
- OS/2 Makefile (`Mkfiles/Makefile.os2`) for Borland under OS/2; from Chuck Crayne.
- Various minor bugfixes (reported by):
 - Dangling `%s` in `preproc.c` (Martin Junker)
- THERE ARE KNOWN BUGS IN SSE AND THE OTHER KATMAI INSTRUCTIONS. I am on a trip and didn't bring the Katmai instruction reference, so I can't work on them right now.
- Updated the License file per agreement with Simon and Jules to include a GPL distribution.

C.2.46 Version 0.98p3.7

- (Hopefully) fixed the canned Makefiles to include the `outrdf2` and `zoutieee` modules.
- Renamed `changes.asm` to `changed.asm`.

C.2.47 Version 0.98p3.6

- Fixed a bunch of instructions that were added in 0.98p3.5 which had memory operands, and the address-size prefix was missing from the instruction pattern.

C.2.48 Version 0.98p3.5

- Merged in changes from John S. Fine's 0.98-J5 release. John's based 0.98-J5 on my 0.98p3.3 release; this merges the changes.

- Expanded the instructions flag field so we can fit more flags, mark SSE (KNI) and AMD or Katmai-specific instructions as such.
- Fixed the PRIV flag bunch of instructions and created a new WPROT flag for protected-mode-only instructions (orthogonal to the instruction-privileged!) and a new SMM flag for SMM-only instructions.
- Added AMD-only SYSCALL and SYSRET instructions.
- Make SSE actually work, and add new Katmai MMX instructions.
- Added a (preferred vendor) option to disasm so that it can distinguish, e.g. Cyrix opcodes also used in SSE. For example:

```

ndisasm -p cyrix aliased.bin
00000000 670F514310          paddsiw mm0,[ebx+0x10]
00000005 670F514320          paddsiw mm0,[ebx+0x20]
ndisasm -p intel aliased.bin
00000000 670F514310          sqrtps xmm0,[ebx+0x10]
00000005 670F514320          sqrtps xmm0,[ebx+0x20]

```

- Added a bunch of Cyrix-specific instructions.

C.2.49 Version 0.98p3.4

- Made at least an attempt to modify all the additional Makefiles (\$INHMKfile directory) I can't test it, but this was the best I could do.
- DOS DJGPP+"Opus Make" Makefile from John S. Fine.
- changes.asm changes from John S. Fine.

C.2.50 Version 0.98p3.3

- Patch from Conan Brink to allow nesting of %rep directives.
- If we're going to allow INT03 as an alias for INT1/ICEBP (one of Jules 0.98p3 changes), then we should allow INT03 as an alias for INT3 as well.
- Updated changes.asm to include the latest changes.
- Tried to clean up the <CR> stuff that had snuck in from a DOS/Windows environment into my Unix environment, and try to make sure that DOS/Windows users get them back.
- We would silently generate broken tools if nsns.dat wasn't sorted properly. Change nsns.p so that the order doesn't matter.
- Fixed nsns.pl (introduced by me) which would cause conditional instructions to have an extra "cc" in disassembly, e.g. "jnz" disassembled as "jccnz".

C.2.51 Version 0.98p3.2

- Merged in John S. Fine's changes from his 0.98-J4 prerelease; see <http://www.csoft.com>
- Changed previous "spotless" Makefile target (appropriate for distribution) to "distclean", and added "cleaner" target which is same as "clean" except delete files generated by scripts; "spotless" is union.
- Removed BASIC programs from distribution. Get a Perl interpreter instead (see below).
- Calling this "pre-release 3.2" rather than "p3-hpa2" because of John's contribution.
- Actually yinked the IEEE output format (zoutieee.c) file bunch of compile warnings in that file. Note I don't know what IEEE output is supposed to look like, so these changes were made.

C.2.52 Version 0.98p3-hpa

- Merged `ndasm098p3.zip` with `asm-0.97.tar.gz` to create a fully buildable version for Unix systems (Makefile.in updates, etc.)
- Changed `insns.pl` to create the instruction table in `asm.h` and `ames.c` so that a new instruction can be added by adding it *only* to `insns.dat`.
- Added the following new instructions: `SYSENTER`, `SYSEXIT`, `FXSAVE`, `FXRSTOR`, `JD1`, `JD2`. (The latter two are two opcodes that Intel guarantees will never be used; one of them is documented as JD2 in Intel documentation, the other one just as "Undefined Opcode" - calling it JD seemed to make sense.)
- `MAX_SYMBOL` was defined to be 9, but `LOADALL286` and `LOADALL386` are 10 characters long. Now `MAX_SYMBOL` is derived from `insns.dat`.
- Note that the `ASIP` programs included for get them in `insns.bas` already update Get yourself a Perl interpreter for your platform of choice at <http://www.cpan.org/ports/index.htm>

C.2.53 Version 0.98 pre-release 3

- added response file support, improved command line handling, new layout help screen
- fixed limit checking bug; OUByte an reg bug and couple of doffelated bugs; updated Wishlist; 0.98 Prerelease 3.

C.2.54 Version 0.98 pre-release 2

- fixed bug in `outcoff.c` with truncating section names longer than 8 characters referencing beyond end of string; 0.98 pre-release 2

C.2.55 Version 0.98 pre-release 1

- Fixed a bug whereby `STRUC` didn't work at all in RDF.
- Fixed a problem with group specification in `PUBDEFs` in `OBJ`.
- Improved ease of adding new output formats. Contribution due to Fox Cutter.
- Fixed bug in relocation in the bin format was showing where a relocatable reference crossed an 8192-byte boundary in any output section.
- Fixed bug in local labels: local-label lookup were inconsistent between passes and if an `EQW` occurred between the definition of a global label and the subsequent use of a local label local to that global.
- Fixed seg-fault in the preprocessor (again) which happened when you used a blank line as the first line of a multi-line macro definition and then defined a label on the same line as the macro.
- Fixed stale-pointer bug in the handling of the `NASM` environment variable. Thanks to Thomas McWilliams.
- ELF had a hard limit on the number of sections which caused segfaults when transgressed.
- Added ability for `ndisasm` to read from stdin by using '-' as the filename.
- `ndisasm` wasn't outputting the `TO` keyword. Fixed.
- Fixed error cascade on bogus expression if an error in evaluation was causing the entire `%if` to be discarded, thus creating trouble later when the `%else` or `%endif` was encountered.
- Forward reference tracking was an instruction-granular operand granular which was causing 286-specific code to be generated needlessly. Note the form `shword[forwardref],1`. Thanks to Jim Hague for sending a patch.

- All messages now appear on stdout, as sending them to stderr serves no useful purpose other than to make redirection difficult.
- Fixed the problem with EQUs pointing to an external symbol - this now generates an error.
- Allowed multiple size prefixes to an operand, of which only the first is taken into account.
- Incorporated John Fine's changes, including fixes for a large number of preprocessor bugs, some small problems in OBJ, and reworking of label handling (define label before the line it is assembled, rather than after).
- Reformatted a lot of the source code to be more readable. Included coding.txt as a guideline for how to format code for contributors.
- Stopped the stderr causing a panic; they now cause a slightly more friendly error message instead.
- Fixed floating point constant problems (patch by Pedro Gimeno)
- Fixed the return value of insn_size() not being checked for -1, indicating an error.
- Incorporated 3DNow! instructions.
- Fixed the 'mov eax, eax + ebx' bug.
- Fixed the GLOBAL EQU bug in ELF. Released developers release 3.
- Incorporated John Fine's command line parsing changes
- Incorporated David Lindauer's OMF debug support
- Made changes to LCC. Support for __NASM_CDECL__ removed (register size specification warning when sizes agree).

C.3 NASM 0.9 Series

Revisions before 0.98.

C.3.1 Version 0.97 released December 1997

- This was entirely a bug-fix release to 0.96, which seems to have got cursed. Silly.
- Fixed a stupid mistake in OBJ which caused MOV EAX, <constant> to fail. Caused by an error in the 'MOV EAX, <segment>' support.
- ndisasm hung at EOF when compiled with cc on Linux because cc on Linux somehow breaks feof(). ndisasm now does not rely on feof().
- A heading in the documentation was missing due to a markup error in the indexing.
- Fixed a failure to update all pointers in realloc() within extended operand code parser.c. Was causing wrong behaviour and seg faults on lines such as 'dd 0.0,0.0,0.0,0.0,...'
- Fixed a subtle preprocessor bug whereby invoking one multi-line macro on the first line of the expansion of another, when the second had been invoked with a label defined before it, didn't expand the inner macro.
- Added internal.doc back in to the distribution archives - it was missing in 0.96.*
- Fixed a bug causing 0.96 to be unable to assemble to whes files, specifically objtest.asm*blush again*
- Fixed seg-faults and bogus error messages caused by mismatching %rep and %endrep within multi-line macro definitions.

- Fixed a problem with buffer overrun in OBJ, which was causing corruption at ends of long PUBDEF records.
- Separated DOS archives into main-program and documentation to reduce download size

C.3.2 Version 0.96 released November 1997

- Fixed a bug whereby, if nasm source file would cause filename collision warning and output into nasm.out, then nasm source file output file still gave the warning even though the -o was honoured. Fixed a pollution under Digital UNIX one of its header files defined _SP which broke the enum in nasm.h.
- Fixed minor instruction table problems: FUCOM and FUCOMB didn't have two-operand forms; NDISASM didn't recognise the longer register forms of PUSH and POP (e.g. FF3 for PUSH BX); TEST mem, imm32 was flagged as undocumented; the 32-bit forms of FCMOV had 16-bit operand size prefixes; 'AAD imm' and 'AAM imm' are no longer flagged as undocumented because the Intel Architecture reference documents them.
- Fixed a problem with the local-label mechanism, whereby strange types of symbol (EQUs, auto-defined OBJ segment base symbols) interfered with the previous global label value and screwed up local labels.
- Fixed a bug whereby the stub preprocessor didn't communicate with the listing generator so that the -a and -l options in conjunction would produce a useless listing file.
- Merged os2 object file format back into obj, after discovering that obj also shouldn't have link pass separator in module containing non-trivial MODEND flat segments are now declared using the FLAT attribute. 'os2' is no longer a valid object format name: use 'obj'
- Removed the fixed-size temporary storage in the evaluator. Very long expressions like mov ax, 1+1+1+1+... for two hundred 1s or so) should now no longer crash NASM.
- Fixed a bug involving segfaults on disassembly of MMX instructions by changing the meaning of one of the operand-type flags in masm.h. This may cause the apparently unrelated MMX problems it needs to be tested thoroughly.
- Fixed some buffer overrun problems with large OBJ output files. Thanks to D. Delorie for the bug report and fix.
- Made preprocess-only mode actually listen to the line markers and print them, so that it can report errors more sanely.
- Re-designed the evaluator to cope with sensible recursive expressions involving forward references: can now cope with previously-nightmare situations such as:

```
mov ax, foo | bar
foo equ 1
bar equ 2
```
- Added the ALIGN and ALIGNB standard macros.
- Added PIC support in ELF: use of WRT to obtain the four extra relocation types needed.
- Added the ability for output file formats to define their own extensions to the GLOBAL, COMMON and EXTERN directives.
- Implemented common-variable alignment, and global-symbol type and size declaration.
- Implemented NEAR and FAR keywords for common variables, plus far-common elements size specification, in OBJ.
- Added a feature whereby EXTERNS and COMMONS in OBJ can be given a default WRT specification (either a segment or a group).

- Transformed the Unix NASM archive into an auto-configuring package.
- Added a sanity-check for people applying SEG things which are already segment bases this previously went unnoticed by the SEG processing and caused OBJ-driver panics later
- Added the ability in OBJ format to deal with MOVAX, <segment> type references OBJ doesn't directly support word-size segment base fixups, but as long as the low bytes of the constant term are zero, a word-size fixup can be generated instead and it will work.
- Added the ability to specify sections alignment requirements in 32-bit object files and binary files.
- Added preprocessor-time expression evaluation, the assign and assign directive and the bar if and elif conditional. Added relational operators to the evaluator for only if constructs: the standard relationals = < > = < > (and C-like synonyms == and !=) plus low-precedence logical operators &&, ^^ and ||.
- Added a preprocessor repeat construct: %rep / %exitrep / %endrep.
- Added the __FILE__ and __LINE__ standard macros.
- Added a sanity check for number constants being greater than 0xFFFFFFFF. The warning can be disabled.
- Added the % token whereby a variable multi-line macro can tell how many parameters it's been given in a specific invocation.
- Added %rotate, allowing multi-line macro parameters to be cycled.
- Added the * option for the maximum parameter count to multi-line macros, allowing them to take arbitrarily many parameters.
- Added the ability for the user-level forms of EXTERN, GLOBAL and COMMON to take more than one argument.
- Added the IMPORT and EXPORT directives in OBJ format, to deal with Windows DLLs.
- Added some more preprocessor %if constructs: %ifidn (exact textual identity) and %ifid / %ifnum / %ifstr (token type testing).
- Added the ability to distinguish SHLAX, 1 (the 8086 version) from SHLAX, BYTE 1 (the 286-and-upwards version whose constant happens to be 1).
- Added NetBSD/FreeBSD/OpenBSD's variant of .out format, complete with ELF shared library features.
- Changed NASM's idiosyncratic handling of CLEX, DISIF, ENIF, FINIT, FSAVE, FSTCW, FSTENV and FSTSW to bring it in line with the otherwise accepted standard. The previous behaviour, though it was a deliberate feature, was a deliberate feature based on a misunderstanding. Apologies for the inconvenience.
- Improved the flexibility of ABSOLUTE; you can now give an expression rather than being restricted to a constant, and it can take relocatable arguments as well.
- Added the ability for a variable to be declared as EXTERN multiple times, and the subsequent definitions are just ignored.
- We now allow instruction prefixes (CS, DS, LOCK, REP, etc.) to be on a line (without following instruction).
- Improved sanity checks on whether the arguments to EXTERN, GLOBAL and COMMON are valid identifiers.

- Added `misc/exebin.mak` to allow direct generation of EXE files by hacking up EXE headers using `DLL` and `WAL`, also added `test/binexe.asm` to demonstrate the use of this. Thanks to Yan Guido for contributing the EXE header code.
- `ndisasm` forgot to check whether the input file had been successfully opened. Now it is.
- Added the Cyrix extensions to the MMX instruction set.
- Added hinting mechanism to allow `[EAX+EBX]` and `[EBX+EAX]` to be assembled differently. This is important since `[ESI+EBP]` and `[EBP+ESI]` have different default base segment registers.
- Added support for the PharLap OMF extension for 4096-byte segment alignment.

C.3.3 Version 0.95 released July 1997

- Fixed yet another ELF bug. This one manifested if the user relied on the default segment, and attempted to define global symbols without first explicitly declaring the target segment.
- Added `makefiles` (for NASM and the RDT tools) to build Win32 console apps under Symantec C++.
- Added `macros.bas` and `insns.bas` to Basic versions of the scripts that convert `standard.mac` to `'macros.c'` and convert `'insns.dat'` to `'insnsa.c'` and `'insnsd.c'`. Also thanks to Ulrich Doewich.
- Changed the disassembled forms of the conditional instructions that use `TEST` and other similar changes. Suggested list by Ulrich Doewich.
- Added `'@'` to the list of valid characters to begin an identifier with.
- Documentary changes, notably the addition of the 'Common Problems' section in `nasmm`.
- Fixed a bug relating to 32-bit PC-relative fixups in OBJ.
- Fixed a bug in `perm_copy()` and `labels`, which was causing exceptions in `cleanup_labels()` on some systems.
- Positivity sanity check in `TIMES` argument changed from warning to error following further complaint.
- Changed the acceptable limits on byte and word operands to allow things like `'~101'`.
- Fixed a major problem in the preprocessor which caused seg-faults if macro definitions contained blank lines or comment-only lines.
- Fixed inadequate error checking on the commas separating the arguments to `'db'`, `'dw'`, `'dd'`.
- Fixed a crippling bug in the handling of macros with operand counts defined with a macro.
- Fixed a bug whereby object file formats which stored the input file name in the output file (such as OBJ and COFF) weren't doing so correctly when the output file name was specified on the command line.
- Removed `[INC]` and `[INCLUDE]` support for good, since they were obsolete anyway.
- Fixed a bug in OBJ which caused all fixups to be output in 16-bit (old-format) FIXUP records, rather than putting the 32-bit ones in FIXUP32 (new-format) records.
- Added, tentatively, OS/2 object file support (as a minor variant on OBJ).
- Updates to Fox Cutter's Borland C makefile, `Makefile.bc2`.
- Removed a spurious second `fclose()` on the output file.
- Added the `'-s'` command line option to redirect all messages which would go to `stderr` (errors/help text) to `stdout` instead.

- Added the '-w' command line option to selectively suppress some classes of assembly warning messages.
- Added the '-p' pre-include and '-d' pre-define command-line options.
- Added an include file search path: the '-i' command line option.
- Fixed a silly little preprocess bug whereby starting a line with '%!' environment-variable reference caused an 'unknown directive' error.
- Added the long-awaited listing file support: the '-l' command line option.
- Fixed a problem with OBJ format whereby, in the absence of any explicit segment definition, non-global symbols declared in the implicit default segment generated spurious EXTDEF records in the output.
- Added the NASM environment variable.
- From this version forward Win32 console-mode binaries will be included in the BCD distribution in addition to the 16-bit binaries. Added Makefile.vc for this purpose.
- Added 'return 0;' to test/objlink.c to prevent compiler warnings.
- Added the __NASM_MAJOR__ and __NASM_MINOR__ standard defines.
- Added an alternative memory-reference syntax which prefixing an operand with % is equivalent to enclosing it in square brackets, at the request of Fox Cutter.
- Errors in pass two now cause the program to return a non-zero error code, which the linker can then use to decide whether to continue.
- Fixed the single-line macro cycle detection which didn't work at all on macros with parameters (caused an infinite loop). Also changed the behaviour of single-line macro cycle detection to work like cpp, so that macros like 'extrn' as given in the documentation can be implemented.
- Fixed the implementation of WRT which was so restrictive that you couldn't do `mov ax, [di+abc wrt dgroup]` because `(di+abc)` wasn't a relocatable reference.

C.3.4 Version 0.94 released April 1997

- Major item: added the macro processor.
- Added and documented instructions SMI, IBT, XBT and LOADALL286. Also reorganised CMPXCHG instruction into early-486 and Pentium forms. Thanks to Tobias Jones for the info.
- Fixed two more stupid bugs in ELF, which were causing 'ld' to continue to seg-fault in a lot of non-trivial cases.
- Fixed a seg-fault in the label manager.
- Stopped FBLD and FBSTP from requiring the WORD keyword, which is the only option for BCD loads/stores in any case.
- Ensured FLDCW, FSTCW and FSTSW can cope with the WORD keyword, if anyone bothers to provide it. Previously they complained unless no keyword at all was present.
- Some forms of FDIV/FDIV and FSUB/FSUB were still inverted a vestige of a bug that had been fixed in 0.92. This was fixed, hopefully for good this time...
- Another minor phase error (insofar as a phase error can ever be minor) fixed this one occurring in code of the form


```
rol ax, forward_reference
forward_reference equ 1
```

- The number supplied to TIMES is now sanity-checked for positivity and is also may be greater than 64K (which previously didn't work on 16-bit systems).
- Added Watcom C makefiles, and misc/pmw.bat, donated by Dominik Behr.
- Added the INCBIN pseudo-opcode.
- Due to the advent of the preprocessor the INCLUDE and INC directives have become obsolete. They are still supported in this version, with a warning, but won't be in the next.
- Fixed a bug in OBJ format which caused incorrect object records to be output when absolute labels were made global.
- Updates to RDOFF subdirectory, and changes to outrdf.c.

C.3.5 Version 0.93 released January 1997

This release went out in a great hurry after semi-crippling bugs were found in 0.92.

- Really *did* fix the stack overflows this time. *blush*
- Had problems with EAs instructions sizes changing between passes, when an offset contained a forward reference and bytes were allocated for the offset in pass one, by pass two the symbol had been defined and happened to be a small absolute value, so only 1 byte got allocated, causing instruction size mismatch between passes and hence incorrect address calculations.
- Stupid bug in the revised ELF section generation fixed (a associated string-table section for symtab was hard-coded as 7, even when this didn't fit with the real section table) was causing 'ld' to seg-fault under Linux.
- Included a new Borland C makefile, Makefile.bc2, donated by Fox Cutter <lmb@comtch

C.3.6 Version 0.92 released January 1997

- The EDIVP/FDIVR and FSUBP/FSUBRP pair had been inverted this was fixed This also affected the LCC driver.
- Fixed a bug regarding 32-bit effective addresses of the form [other_register+ESP].
- Documentary changes, notably documentation of the fact that a Borland Win32 compiler uses 'obj' rather than 'win32' object format.
- Fixed the COMENT record in OBJ files, which was formatted incorrectly.
- Fixed a bug causing segfaults in large RDF files.
- OBJ format now strips initial periods from segment and group definitions, in order to avoid complications with the local label syntax.
- Fixed a bug in disassembling far calls and jumps in NDISASM.
- Added support for user-defined sections in COFF and ELF files.
- Compiled the DOS binaries with a sensible amount of stack, to prevent stack overflows on any arithmetic expression containing parentheses.
- Fixed a bug in handling of files that do not terminate in a newline.

C.3.7 Version 0.91 released November 1996

- Loads of bug fixes.
- Support for RDF added.
- Support for DBG debugging format added.

- Support for 32-bit extensions to Microsoft OBJ format added.
- Revised for Borland C: some variable names changed, makefile added.
- LCC support revised to actually work.
- JMP/CALL NEAR/FAR notation added.
- 'a16', 'o16', 'a32' and 'o32' prefixes added.
- Range checking on short jumps implemented.
- MMX instruction support added.
- Negative floating point constant support added.
- Memory handling improved to bypass 64K barrier under DOS.
- \$ prefix to force treatment of reserved words as identifiers added.
- Default-size mechanism for object formats added.
- Compile-time configurability added.
- #, @, ~ and c{?} are now valid characters in labels.
- -e and -k options in NDISASM added.

C.3.8 Version 0.90 released October 1996

First release version. First support for object file output. Other changes from previous version (0.3x) too numerous to document.

Appendix D: Building NASM from Source

The source code for NASM is available from our website, <http://www.nasm.us/>, see [see](#)

D.1 Building from a Source Archive

The source archive available on the website should be capable of building on a number of platforms. This is the recommended method of building NASM support platforms for which executables are not available.

On a system which has Unix shell (sh), run:

```
sh configure
make everything
```

A number of options can be passed to configure; see `sh configure --help`.

A set of Makefiles for some other environments are also available; please see the file `Mkfiles/README`.

To build the installer for the Windows platform, you will need the Nullsoft Scriptable Installer, NSIS, installed.

To build the documentation, you will need additional tools. The documentation is not likely to be able to build on non-Unix systems.

D.2 Building from the git Repository

The NASM development tree is kept in a source code repository using the git distributed source control system. The link is available on the website. This is recommended only if you participate in the development of NASM or to assist with testing the development code.

To build NASM from the git repository you will need Perl and, if building on a Unix system, GNU autoconf.

To build on a Unix system, run:

```
sh autogen.sh
```

to create the configure script and then build as listed above.

Appendix E: Contact Information

E.1 Website

NASM has a website at <http://www.nasm.us/>.

New releases, release candidates and daily development snapshots of NASM are available from the official web site in source form as well as binaries for a number of common platform

E.1.1 User Forums

Users of NASM may find the Forums on the website useful. These are, however, not frequented much by the developers of NASM, so they are not suitable for reporting bugs.

E.1.2 Development Community

The development of NASM is coordinated primarily through the [nasm-devel](#) mailing list. If you wish to participate in development of NASM, please join the mailing list. Subscription links and archives of past posts are available on the website.

E.2 Reporting Bugs

To report bugs in NASM, please use the bug tracker at <http://www.nasm.us/> (click on "Bug Tracker"), or if that fails then through one of the contacts in section E.1.

Please read section 2.1. First, don't report a bug if it's listed in the [known issues](#) (If you think the feature is badly thought out, feel free to send reasons why you think it should be changed, but don't just send a mail saying "This is a bug" if the documentation says *we did it on purpose*.) Then read section 12.1, and don't bother reporting the bug if it's listed there.

If you do report a bug, *please* make sure your bug report includes the following information:

- What operating system you're running NASM under. Linux, FreeBSD, NetBSD, MacOSX, Win16, Win32, Win64, MS-DOS, OS/2, VMS, whatever.
- If you compiled your own executable from source archive, compiled your own executable from git, used the standard distribution binaries from the website, or got an executable from somewhere else (e.g. a Linux distribution). If you are using a locally built executable, try to reproduce the problem using one of the standard binaries, as this will make it easier for us to reproduce your problem prior to fixing it.
- Which version of NASM you're using, and exactly how you invoked it. Give us the precise command line, and the contents of the NASMENV environment variable if any.
- Which versions of any supplementary programs you're using, and how you invoked them. If the problem only becomes visible at link time, tell us what linker you're using, what version of linker you've got, and the exact linker command line. If the problem involves linking against object files generated by a compiler, tell us what compiler, what version, and what command line options you used. (If you're compiling in IDE, please try to reproduce the problem with the command-line version of the compiler.)
- If at all possible, send us a NASM source file which exhibits the problem. If this causes a copyright problem (e.g. you can't reproduce the bug in restricted-distribution code), then bear in mind the following points: firstly, we guarantee that any source code sent to us for the purposes of debugging NASM will be used *only* for the purposes of debugging NASM, and that we will delete all our copies of it as soon as we have found and fixed the bug; bugs in question; and secondly, we would prefer *not* to be mailed large chunks of code anyway. The smaller the file, the better. A three-line sample file that does nothing useful *except* to demonstrate the problem is such as to

work with a fully fledged ten-thousand-line program. (Of course, some errors ~~do~~ only crop in large files, so this may not be possible.)

- ~~A description of what the problem actually is. 'It doesn't work' is not a helpful description. Please describe exactly what is happening that shouldn't be, what is n' happening that should. Examples might be: 'NASM generates an error message saying line 5 for an error that ' actually on line 5'; 'NASM generates an error message that I believe it shouldn't be generating at all'; 'NASM fails to generate an error message that I believe it should be generating'; the object file produced from this source code crashes my linker'; the ninth byte of the output file is 66 and I think it should be 77 instead'.~~
- If you believe the output file from NASM is faulty, send it to us. That allows us to determine whether our own copy of NASM generates the same file, or whether the problem is related to portability issues between our development platform and yours. We handle binary files mailed to us as MIME attachments, uuencoded, and even BinHex. Alternatively, we may be able to provide an FTP site you can upload the suspect files to; but mailing them is easier for us.
- Any other information or data files that might be helpful. If, for example, the problem involves NASM failing to generate an object file while TASM generates an equivalent file without trouble, then send us *both* object files, so we can see what TASM is doing differently from us.

Index

! operator, unary	37	a16	120
!= operator	54	A32	29
\$\$ token	36, 93	a32	120
\$		A64	29
Here token	36	a64	120
prefix	29, 33, 96	a86	26, 27
% operator	37	ABS	32, 74
%!	65	ABSOLUTE	75, 82
\$\$ and \$\$\$ prefixes	59	addition	37
% operator	37, 47	addressing, mixed-size	119
%+	43	address-size prefixes	29
%?	43	algebra	32
%%?	43	ALIGN	69, 71, 79, 82
%[43	smart	71
& operator	37	ALIGNB	69
&& operator	54	alignment	
* operator	37	in bin sections	79
+ modifier	48	in elf sections	93
+ operator		in obj sections	82
binary	37	in win32 sections	86
unary	37	of elf common variables	95
- operator		ALIGNMODE	71
binary	37	__ALIGNMODE__	71
unary	37	ALINK	99
..@ symbol prefix	39, 47	alink.sourceforge.net	99
/ operator	37	all	25
// operator	37	alloc	93
< operator	54	alternate register names	71
<< operator	37	altreg	71
<= operator	54	ambiguity	27
<> operator	54	a.out	
= operator	54	BSD version	95
== operator	54	Linux version	95
> operator	54	aout	95
>= operator	54	aoutb	95, 114
>> operator	37	%arg	62
? MASM syntax	30	arg	106, 113
^ operator	37	as86	96
^^ operator	54	assembler directives	73
operator	36	assembly-time options	23
operator	54	%assign	44
~ operator	37	ASSUME	27
%0 parameter count	50	AT	69
%00	50	Autoconf	
%+1 and %-1 syntax	52	auto-sync	130
16-bit mode, versus 32-bit mode	73	-b	129
64-bit displacement	124	bad-pragma	25
64-bit immediate	123	bin	20, 79
-a option	23, 130	multisection	80
A16	29	binary	33

binary files	30	conditional assembly	53
bit shift	37	conditional jumps	127
BITS	73, 79	conditional-return macro	52
__BITS__	66	constants	33
bitwise AND	37	context fall-through lookup	60
bitwise OR	36	context stack	58, 61
bitwise XOR	37	context-local labels	59
block IFs	61	context-local single-line macros	59
BND	74	counting macro parameters	50
bnd	25	CPU	77
boot loader	79	CPUID	34
boot sector	127	creating contexts	59
Borland		critical expression	30, 38, 44, 75
Pascal	107	cv8	87
Win32 compilers	81	-D option	23
braces		-d option	23
after % sign	52	daily development snapshots	267
around macro parameters	46	.data	93, 95, 96
BSD	114	_DATA	103
.bss	93, 95, 96	data	94, 97
bug tracker	267	data structure	106, 113
bugs	267	__DATE__	67
BYTE	127	__DATE_NUM__	67
C calling convention	104, 111	DB	30, 34, 35
C symbol names	102	dbg	97
c16.mac	106, 109	DD	30, 34, 35
c32.mac	113	debug information	21
CALL FAR	38	debug information format	21
case sensitivity	42, 44, 46, 55, 83	decimal	33
changing sections	74	declaring structures	68
character constant	30, 34	DEFAULT	74
character strings	33	default	94
circular references	41	default macro parameters	49
CLASS	82	default name	79
%clear	65	default-WRT mechanism	84
CodeView debugging format		%define	23, 41
coff	91	defining sections	74
colon	29	%defstr	45
.COM	79, 101	%deftok	45
comma	49	%depend	58
command-line	19, 79	design goals	26
commas in macro parameters	48	DevPac	30, 39
.comment	93	disabling listing expansion	52
COMMON	77, 81	division	37
elf extensions to	95	DJGPP	91, 111
obj extensions to	84	djlink	99
Common Object File Format	91	DLL symbols	
common variables	77	exporting	83
alignment in elf	95	importing	83
element size	84	DO	30, 34, 35
comp.os.msdos.programmer	102	DOS	22
concatenating macro parameters	51	DOS archive	
concatenating strings	45	DOS source archive	
condition codes as macro parameters	52	DQ	30, 34, 35

.drective	85	.EXE	81, 99
DT	30, 34, 35	EXE2BIN	101
DUP	28, 31	EXE_begin	100
DW	30, 34, 35	exebin.mac	100
DWORD	30	exec	93
DY	30, 34	Executable and Linkable Format	92
DZ	30	EXE_end	100
-E option	23	EXE_stack	100
-e option	23, 130	%exitrep	57
effective addresses	29, 31	EXPORT	83
element size, in common variable	84	export	96
ELF	92	exporting symbols	76
shared libraries		expressions	23, 36
16-bit code and	95	extension	19, 79
elf, debug formats and	95	EXTERN	76
elf32	92	obj extensions to	84
elf64	92	rdf extensions to	97
elfx32	92	extracting substrings	46
%elif	53, 54, 55	-F option	21
%elifctx	54	-f option	20, 79
%elifdef	54	far call	27
%elifempty	56	far common variables	84
%elifenv	56	far pointer	38
%elifid	56	FARCODE	107, 109
%elifidn	55	%fatal	64
%elifidni	55	__FILE__	66
%elifmacro	54	FLAT	82
%elifn	53, 55	flat memory model	111
%elifnctx	54	flat-form binary	79
%elifndef	54	FLOAT	78
%elifnempty	56	__FLOAT__	78
%elifnenv	56	__float128h__	35
%elifnid	56	__float128l__	35
%elifnidn	55	__float16__	35
%elifnidni	55	__float32__	35
%elifnmacro	54	__float64__	35
%elifnnum	56	__float8__	35
%elifnstr	56	__float80e__	35
%elifntoken	56	__float80m__	35
%elifnum	56	__FLOAT_DAZ__	78
%elifstr	56	float-denorm	25
%liftoken	56	floating-point	
%else	53	constants	35, 78
endproc	106, 113	packed BCD constants	36
%endrep	56	floating-point	27, 29, 30, 35
ENDSTRUC	68, 75	float-overflow	24
environment	26	__FLOAT_ROUND__	78
EQU	30, 31	float-toolong	25
%error	64	float-underflow	25
error messages	22	follows=	80
error reporting format	21	format-specific directives	73
escape sequences	33	fp	72
EVEN	69	frame pointer	104, 108, 111
exact matches	53	FreeBSD	95, 114

FreeLink	99	%ifnidn	55
ftp.simtel.net	99	%ifnidni	55
function	94, 96	%ifnmacro	54
functions		%ifnnum	56
C calling convention	104, 111	%ifnstr	56
Pascal calling convention	108	%ifntoken	56
-g option	21	%ifnum	55
git	265	%ifstr	55
GLOBAL	76	%iftoken	56
aoutb extensions to	94	ifunc	72
elf extensions to	94	ilog2()	72
rdf extensions to	96	ilog2c()	72
global offset table	114	ilog2cw()	72
_GLOBAL_OFFSET_TABLE_	93	ilog2e()	72
gnu-elf-extensions	24	ilog2f()	72
..got	93	ilog2fw()	72
GOT relocations	115	ilog2w()	72
GOT	93, 114	%imacro	46
..gotoff	93	IMPORT	83
GOTOFF relocations	115	import library	83
..gotpc	93	importing symbols	76
GOTPC relocations	115	INCBIN	30, 34
..gottpoff	94	%include	22, 57
graphics	30	include search path	22
greedy macro parameters	48	including other files	57
GROUP	82	inefficient code	127
groups	37	infinite loop	36
-h	129	__Infinity__	36
hexadecimal	33	infinity	36
hidden	94	informational section	85
hle	25	instances of structures	69
hybrid syntaxes	27	instruction list	133
-I option	22	integer functions	37, 72
-i option	22, 130	integer logarithms	72
%iassign	44	intel hex	80
%idefine	41	Intel number formats	36
%idefstr	45	internal	94
%ideftok	45	ISTRUC	69
IEND	69	iterating over macro parameters	50
%if	53, 54	ith	80
%ifctx	54, 61	%ixdefine	42
%ifdef	53	Jcc NEAR	127
%ifempty	56	JMP DWORD	119
%ifenv	56	jumps, mixed-size	119
%ifid	55	-k	131
%ifidn	55	-l option	20
%ifidni	55	label preceeding macro	50
%ifmacro	54	label prefix	39
%ifn	53, 55	last	49
%ifnctx	54	.lbss	93
%ifndef	54	ld86	96
%ifnempty	56	.ldata	93
%ifnenv	56	LIBRARY	96
%ifnid	56	license	17

%line	65	-MP option	21
__LINE__	66	-MQ option	21
linker, free	99	MS-DOS	79
Linux		MS-DOS device drivers	102
a.out	95	-MT option	21
as86	96	multi-line macros	24, 46
ELF	92	multipass optimization	23
listing file	20	multiple section names	79
little-endian	34	multiplication	37
%local	63	multipush macro	51
local labels	39	multisection	80
lock	25	-MW option	21
logical AND	54	__NaN__	36
logical negation	37	NaN	36
logical OR	54	NASM version	65
logical XOR	54	nasm version history	231
.lrodata	93	nasm version id	66
-M option	20	nasm version string	66
Mach, object file format	91	__NASMDEFSEG	81
Mach-O, object file format	91	nasm-devel	267
macho32	91	NASMENV	26
macho64	91	nasm -hf	20
MacOS X	91	__NASM_MAJOR__	65
%macro	46	__NASM_MINOR__	65
macro indirection	43	nasm.out	19
macro library	22	__NASM_PATCHLEVEL__	65
macro parameters range	48	__NASM_SNAPSHOT__	65
macro processor	41	__NASM_SUBMINOR__	65
macro-defaults	24	__NASM_VER__	66
macro-local labels	47	__NASM_VERSION_ID__	66
macro-params	24	ndisasm	129
macros	31	near call	27
macro-selfref	24	near common variables	84
makefile dependencies	20	NetBSD	95, 114
map files	80	new releases	267
MASM	26, 31, 81	noalloc	93
-MD option	20	nobits	80, 93
memory models	27, 103	NOBND	74
memory operand	30	no_dead_strip	92
memory references	26, 31	noexec	93
-MF option	20	.nolist	52
-MG option	20	not-my-pragma	25
Microsoft OMF	81	'nowait'	27
minifloat	35	nowrite	93
Minix	96	NSIS	265
misc subdirectory	100, 106, 113	Nullsoft Scriptable Installer	265
mixed-language program	102	number-overflow	24
mixed-size addressing	119	numeric constants	30, 33
mixed-size instruction	119	-O option	23
MMX registers		-o option	19, 129
ModR/M byte		O16	29
MODULE	96	o16	120
modulo operators	37	O32	29
motorola s-records	80	o32	121

O64	29	pre-including files	22
.OBJ	99	preprocess-only mode	23
obj	81	preprocessor	23, 31, 37, 41
object	94, 97	preprocessor expressions	23
octal	33	preprocessor loops	56
OF_DEFAULT	20	preprocessor variables	44
OFFSET	27	primitive directives	73
OMF	81	PRIVATE	81
omitted parameters	49	proc	96, 106, 113
one's complement	37	procedure linkage table	94, 116, 117
OpenBSD	95, 114	processor mode	73
operands	29	progbits	80, 93
operand-size prefixes	29	program entry point	84, 99
operating system	79	program origin	79
writing	119	protected	94
operators	36	pseudo-instructions	30
ORG	79, 101, 102, 127	ptr	25
orphan-labels	24, 29	PUBLIC	76, 81
OS/2	81, 82	pure binary	79
osabi	92	%push	58, 59
other	24	__QNaN__	36
other preprocessor directives	64	quick start	26
out of range, jumps	127	QWORD	30
output file format	20	-r	129
output formats	79	rdf	96
__OUTPUT_FORMAT__	66	rdoff subdirectory	96
overlapping segments	37	redirecting errors	22
OVERLAY	82	REL	32, 74
overloading		relational operators	54
multi-line macros	47	release candidates	267
single-line macros	41	Relocatable Dynamic Object File Format	96
-P option	22	relocations, PIC-specific	93
-p option	22, 58	removing contexts	59
paradox	38	renaming contexts	60
PASCAL	109	%rep	31, 56
Pascal calling convention	108	repeating	31, 56
__PASS__	67	%repl	60
passes, assembly		reporting bugs	267
%pathsearch	22, 58	RESB	28, 30
period	39	RESD	30
Perl		RESO	30
perverse	22	RESQ	30
PharLap	82	REST	30
PIC	93, 95, 114	RESW	30
..plt	93	RESY	30
PLT relocations	94, 116, 117	RESZ	30
plt relocations	117	.rodata	93
%pop	59	%rotate	50
position-independent code	93, 95, 114	rotating macro parameters	50
--postfix	26	-s option	22, 130
precedence	36	searching for include files	57
pre-defining macros	23, 42	__SECT__	74, 75
preferred	37	SECTALIGN	70
--prefix	26		

SECTION	74	string length	45
elf extensions to	93	string manipulation in macros	45
macho extensions to	91	strings	33
win32 extensions to	85	%strlen	45
section alignment		STRUC	68, 75, 106, 113
in bin	79	stub preprocessor	23
in elf	93	subsections_via_symbols	92
in obj	82	%substr	46
in win32	86	subtraction	37
section, bin extensions to	79	suppressing preprocessing	23
SEG	37, 81	switching between sections	74
SEGMENT	74	..sym	93
elf extensions to	81	symbol sizes, specifying	94
segment address	37	symbol types, specifying	94
segment alignment		symbols	
in bin	79	exporting from DLLs	83
in obj	82	importing from DLLs	83
segment names, Borland Pascal	109	synchronisation	130
segment override	27, 29	.SYS	79, 102
segments	37	-t	24
groups of	82	TASM	24
separator character	26	tasm	26, 81
shared libraries	95, 114	.tbss	93
shared library	94	TBYTE	27
shift command	50	.tdata	93
SIB byte		test subdirectory	99
signed division	37	testing	
signed modulo	37	arbitrary numeric expression	54
single-line macros	41	context stack	54
size, of symbols	94	exact text identity	55
smartalign	71	multi-line macro existence	54
__SNaN__	36	single-line macro existence	53
snapshots, daily development	267	token types	55
Solaris x86	92	.text	93, 95, 96
-soname	117	_TEXT	103
sound	30	thread local storage in elf	94
source-listing file	20	thread local storage in mach-o	92
square brackets	26, 31	__TIME__	67
srec	80	__TIME_NUM__	67
STACK	81	TIMES	30, 31, 38, 127, 128
stack relative preprocessor directives	62	TLINK	101
%stacksize	63	tls	92, 93, 94
standard macro packages	71	..tlsie	94
standard macros	65	trailing colon	29
standardized section names	74, 85, 93, 95, 96	TWORD	27, 30
..start	84, 99	type, of symbols	94
start=	80	-U option	23
stderr	22	-u option	23, 129
stdout	22	unary operators	37
%strcat	45	%undef	23, 44
STRICT	38	undefining macros	23
string constant	30	underscore, in C symbols	102
string constants	34	Unicode	34, 35
		uninitialized	30

uninitialized storage	28	Windows	99
Unix		Windows 95	
SCO	92	windows debugging formats	87
source archive		Windows NT	
System V	92	-Wno-error option	25
UnixWare	92	write	93
unknown-pragma	25	writing operating systems	119
unknown-warning	25	WRT	37, 81, 92, 93, 94, 95
%unmacro	53	WRT ..got	115
unrolled loops	31	WRT ..gotoff	115
unsigned division	37	WRT ..gotpc	115
unsigned modulo	37	WRT ..plt	117
UPPERCASE	26, 83	WRT ..sym	116
%use	58, 71	WWW page	
__USE_*__	67	www.delorie.com	99
USE16	74, 82	www.pcorner.com	99
USE32	74, 82	-X option	21
user	25	x2ftp.oulu.fi	99
user-defined errors	64	x32	92
user-level assembler directives	65	%xdefine	42
user-level directives	73	-y option	25
__UTC_DATE__	67	-Z option	22
__UTC_DATE_NUM__	67	zext-reloc	25
__UTC_TIME__	67		
__UTC_TIME_NUM__	67		
UTF-16	35		
UTF-32	35		
UTF-8	34		
__utf16__	35		
__utf16be__	35		
__utf16le__	35		
__utf32__	35		
__utf32be__	35		
__utf32le__	35		
--v	25		
-v option	25		
VAL	99		
valid characters	29		
variable types	27		
version	25		
version number of NASM	65		
vfollows=	80		
Visual C++	85		
vstart=	80		
-W option	24		
-w option	24		
%warning	64		
[WARNING]	25, 78		
warning classes	24		
warnings	24		
website	267		
-Werror option	25		
win64	87, 123		
Win64	81, 85, 111		